cap expiry

Bi Directional

DCSQM (Queue Manager)

AMADEUS.LOC.IN

DEF QL(AMADEUS.LOC.IN) DEFPSIST(YES) MAXDEPTH(100000)

CUSTOM('CAPEXPRY(600)')

DIS QL(AMADEUS.LOC.IN)

DEF QL(AMD.IN) DEFPSIST(YES) MAXDEPTH(100000) BOQNAME(AMD.IN.BOQ)

CUSTOM('CAPEXPRY(600)')

ALTER QL(AMADEUS.LOC.IN) STREAMQ(AMADEUS.RMT)

AMADEUS.TX

DEF QL(AMADEUS.TX) TRIGGER INITQ(SYSTEM.CHANNEL.INITQ)

TRIGDATA(AMADEUS.LOC.IN) USAGE(XMITQ) DEFPSIST(YES) MAXDEPTH(100000)

AMADEUS.RMT

DEF QREMOTE(AMADEUS.RMT) RNAME(IAPI.LOC) RQMNAME(IAPIQM) XMITQ(AMADEUS.TX) DEFPSIST(YES)

SENDER CHANNEL (AMADEUS.TO.IAPI)

DEF CHANNEL(AMADEUS.TO.IAPI) CHLTYPE(SDR) CONNAME('10.20.1.21(1514)') XMITQ(AMADEUS.TX)

DEFINE SERVICE(CHSERV.AMADEUS) CONTROL(QMGR) STARTCMD('runmqchi')

STARTARG('-m DCSQM -c AMADEUS.TO.IAPI') SERVTYPE(SERVER)

START SERVICE(CHSERV.AMADEUS)

DIS SVSTATUS(CHSERV.AMADEUS)

amgsput AMADEUS.LOC.IN DCSQM

amgsbcg <QN> <QMN>

TRAVELSKY.LOC.IN

DEF QL(TRAVELSKY.LOC.IN) DEFPSIST(YES) MAXDEPTH(100000)

CUSTOM('CAPEXPRY(600)')

DIS QL(AMADEUS.LOC.IN)

ALTER QL(TRAVELSKY.LOC.IN) STREAMQ(TRAVELSKY.RMT)

TRAVELSKY.TX

DEF QL(TRAVELSKY.TX) TRIGGER INITQ(SYSTEM.CHANNEL.INITQ)

TRIGDATA(TRAVELSKY.LOC.IN) USAGE(XMITQ) DEFPSIST(YES) MAXDEPTH(100000)

TRAVELSKY.RMT

DEF QREMOTE(TRAVELSKY.RMT) RNAME(IAPI.LOC) RQMNAME(IAPIQM)

XMITQ(TRAVELSKY.TX) DEFPSIST(YES)

SENDER CHANNEL (TRAVELSKY.TO.IAPI)
DEF CHANNEL(TRAVELSKY.TO.IAPI) CHLTYPE(SDR) CONNAME('10.20.1.21(1515)')
XMITQ(TRAVELSKY.TX)

DEFINE SERVICE(CHSERV.TRAVELSKY) CONTROL(QMGR) STARTCMD('runmqchl') STARTARG('-m DCSQM -c TRAVELSKY.TO.IAPI') SERVTYPE(SERVER) START SERVICE(CHSERV.TRAVELSKY) DIS SVSTATUS(CHSERV.TRAVELSKY)

TRAVELSKY.LOC.OUT

DEF QL(TRAVELSKY.LOC.OUT) DEFPSIST(YES) MAXDEPTH(100000)

CUSTOM('CAPEXPRY(600)')

RECIVER CHANNEL (IAPI.TO.TRAVELSKY)

DEF CHANNEL(IAPI.TO.TRAVELSKY) CHLTYPE(RCVR)

LISTNER (Port 1414)

DEF LISTENER(LSTR.DCS) TRPTYPE(TCP) PORT(1414) CONTROL(QMGR)

START LISTENER(LSTR.DCS)

AMADEUS.LOC.OUT
DEF QL(AMADEUS.LOC.OUT) DEFPSIST(YES) MAXDEPTH(100000)
CUSTOM('CAPEXPRY(600)')
RECIVER CHANNEL (IAPI.TO.AMADEUS)
DEF CHANNEL(IAPI.TO.AMADEUS) CHLTYPE(RCVR)

IAPIQM (queue manager)

crtmqm IAPIQM str IAPIQM runmqsc IAPIQM

IAPI.LOC

DEF QL(IAPI.LOC) DEFPSIST(YES) MAXDEPTH(100000) CUSTOM('CAPEXPRY(600)') ALT QL(IAPI.LOC) CUSTOM('CAPEXPRY()')

LISTNER (Port 1514)

DEF LISTENER(LSTR.IAPI) TRPTYPE(TCP) PORT(1514) CONTROL(QMGR) START LISTENER(LSTR.IAPI)

RECIVER CHANNEL
(AMADEUS.TO.IAPI)

DEF CHANNEL(AMADEUS.TO.IAPI) CHLTYPE(RCVR)
(TRAVELSKY.TO.IAPI)

DEF CHANNEL(TRAVELSKY.TO.IAPI) CHLTYPE(RCVR)

AMADEUS.LQ.DCS AMADEUS.TX.DCS AMADEUS.RMT.DCS

SENDER CHANNEL (IAPI.TO.AMADEUS)

AMADEUS.LQ.DCS
DEF QL(AMADEUS.LQ.DCS) DEFPSIST(YES) MAXDEPTH(100000)
CUSTOM('CAPEXPRY(600)')
DIS QL(AMADEUS.LQ.DCS)

ALTER QL(AMADEUS.LQ.DCS) STREAMQ(AMADEUS.RMT.DCS)

AMADEUS.TX.DCS

DEF QL(AMADEUS.TX.DCS) TRIGGER INITQ(SYSTEM.CHANNEL.INITQ)
TRIGDATA(AMADEUS.LQ.DCS) USAGE(XMITQ) DEFPSIST(YES) MAXDEPTH(100000)

AMADEUS.RMT.DCS

DEF QREMOTE(AMADEUS.RMT.DCS) RNAME(AMADEUS.LOC.OUT) RQMNAME(DCSQM) XMITQ(AMADEUS.TX.DCS) DEFPSIST(YES)

SENDER CHANNEL (IAPI.TO.AMADEUS)

DEF CHANNEL (IAPI.TO.AMADEUS) CHLTYPE (SDR) CONNAME ('10.0.0.22(1414)')

XMITQ (AMADEUS.TX.DCS)

DEFINE SERVICE(CHSERV.IAPI.AMADEUS) CONTROL(QMGR) STARTCMD('runmqchl') STARTARG('-m IAPIQM -c IAPI.TO.AMADEUS') SERVTYPE(SERVER) START SERVICE(CHSERV.IAPI.AMADEUS) DIS SVSTATUS(CHSERV.IAPI.AMADEUS)

TRAVELSKY.LQ.DCS
TRAVELSKY.TX.DCS
TRAVELSKY.RMT.DCS
SENDER CHANNEL (IAPI.TO.TRAVELSKY)

TRAVELSKY.LQ.DCS
DEF QL(TRAVELSKY.LQ.DCS) DEFPSIST(YES) MAXDEPTH(100000)
CUSTOM('CAPEXPRY(600)')
DIS QL(TRAVELSKY.LQ.DCS)

ALTER QL(TRAVELSKY.LQ.DCS) STREAMQ(TRAVELSKY.RMT.DCS)

TRAVELSKY.TX.DCS

DEF QL(TRAVELSKY.TX.DCS) TRIGGER INITQ(SYSTEM.CHANNEL.INITQ)
TRIGDATA(TRAVELSKY.LQ.DCS) USAGE(XMITQ) DEFPSIST(YES) MAXDEPTH(100000)

TRAVELSKY.RMT.DCS

DEF QREMOTE(TRAVELSKY.RMT.DCS) RNAME(TRAVELSKY.LOC.OUT) RQMNAME(DCSQM) XMITQ(TRAVELSKY.TX.DCS) DEFPSIST(YES)

SENDER CHANNEL (IAPI.TO.TRAVELSKY)

DEF CHANNEL(IAPI.TO.TRAVELSKY) CHLTYPE(SDR) CONNAME('10.0.0.22(1414)')

XMITQ(TRAVELSKY.TX.DCS)

DEFINE SERVICE(CHSERV.IAPI.TRAVELSKY) CONTROL(QMGR) STARTCMD('runmqchl') STARTARG('-m IAPIQM -c IAPI.TO.TRAVELSKY') SERVTYPE(SERVER) START SERVICE(CHSERV.IAPI.TRAVELSKY) DIS SVSTATUS(CHSERV.IAPI.TRAVELSKY)

Queue Manager (IAPI.RECEIVEQM)

crtmqm IAPI.RECEIVEQM strmqm IAPI.RECEIVEQM runmqsc IAPI.RECEIVEQM

IAPI.LOC

DEF QL(IAPI.LOC) DEFPSIST(YES) MAXDEPTH(100000) CUSTOM('CAPEXPRY(600)')

LISTNER (Port 1514)

DEF LISTENER(LSTR.IAPI) TRPTYPE(TCP) PORT(1514) CONTROL(QMGR) START LISTENER(LSTR.IAPI)

RECIVER CHANNEL
(AMADEUS.TO.IAPI)
DEF CHANNEL(AMADEUS.TO.IAPI) CHLTYPE(RCVR)
(TRAVELSKY.TO.IAPI)
DEF CHANNEL(TRAVELSKY.TO.IAPI) CHLTYPE(RCVR)