NTUA Top Tagger

Tag & Probe methodology





Overview

- BDT Input and Output in the SR_B Region
 - SR_B: Baseline selection + tight Mass Cut (120,220) GeV, no TopTagger Selection
 - Leading + subleading in different pT regions: [400,600], [600,800], [800,1200]
 - Find Data vs MC Input and Output for UL our Analysis <u>here</u>
- Top Tagger Scale Factors
 - Data is subtracted QCD and Subdominant bkgs (MC) so that the data sample is pure

$$efficiency = \frac{Tight \& SR}{Tight \& Probe} = \frac{\# (1 \, jet \, pass \, baseline + Tight \, TopTagger \, Cut \, AND \, 1 \, jet \, pass \, SR)}{\# (1 \, jet \, pass \, baseline + Tight \, TopTagger \, Cut \, AND \, 1 \, jet \, pass \, only \, baseline)}$$

- Implemented Randomization (check random jet) to fill histogram to avoid pT bias
- Divide the phase space into pT regions: [400-600]GeV, [600-800]GeV, [800-Inf]GeV
- For the QCD estimation, we perform a fit in both regions (Tight & Probe, Tight & SR):
 - Shape of QCD is estimated from Data while inverting btagging requirement
 - # QCD events in each region is calculated from fit using the Leading JetMassSoftDrop variable
 - To scale the ttbar → fit the Leading JetMassSoftDrop in each region and get the signal strength.
 - For the evaluation of Signal distribution from data, we do the following:

$$\forall region: S(x) = D(x) - N_{QCD}d_0(x) - Sub.Bkg(x)$$



Signal Selection


Variables	Selected Cut
pT leading jets	> 450 GeV
pT 2 nd leading jets	> 400 GeV
Njets	>1
N leptons	= 0
eta (both leading jets)	< 2.4
mJJ	> 1000 GeV
jetMassSoftDrop (only for fit)	(50,300) GeV
Top Tagger	> 0.2
B tagging (2 btagged jets)	> Medium WP
Signal Trigger	

Control Region Selection

Variables	Selected Cut
pT leading jets	> 450 GeV
pT 2 nd leading jets	> 400 GeV
N leptons	= 0
eta (both leading jets)	< 2.4
mJJ	> 1000 GeV
jetMassSoftDrop (only for fit)	(50,300) GeV
Top Tagger	> 0.2
B tagging (0 btagged jets)	< Medium WP
Control Trigger	



TagAndProbe Efficiency per Pt region (2016 preVFP)




```
Efficiency--
eff data: 0.757 \pm 0.058
eff ttbar: 0.788 \pm (stat) 0.009 \pm (stat + systematic) 0.01
-----

Efficiency per Pt region
eff data pT[400-600]: 0.746 \pm 0.075
eff ttbar pT[400-600]: 0.792 \pm (stat) 0.012 \pm (stat + systematic) 0.014
-----
eff data pT[600-800]: 0.76 \pm 0.101
eff ttbar pT[600-800]: 0.786 \pm (stat) 0.014 \pm (stat + systematic) 0.016
------
eff data pT[800-Inf]: 0.824 \pm 0.197698
eff ttbar pT[800-Inf]: 0.765 \pm (stat) 0.037 \pm (stat + systematic) 0.052
```



TagAndProbe Efficiency per Pt region (2016 postVFP)



```
data: 0.79 \pm 0.052

ttbar: 0.781 \pm (stat) 0.008 \pm (stat + systematic) 0.009

ciency per Pt region

data pT[400-600]: 0.77 \pm 0.068

ttbar pT[400-600]: 0.791 \pm (stat) 0.011 \pm (stat + systematic) 0.013

data pT[600-800]: 0.809 \pm 0.085


ttbar pT[600-800]: 0.772 \pm (stat) 0.012 \pm (stat + systematic) 0.013

data pT[800-Inf]: 0.861 \pm 0.259

ttbar pT[800-Inf]: 0.758 \pm (stat) 0.034 \pm (stat + systematic) 0.037
```




TagAndProbe Efficiency per Pt region(2017)





TagAndProbe Efficiency per Pt region(2018)



```
Efficiency-- eff data: 0.792 \pm 0.03 eff ttbar: 0.815 \pm (stat) 0.005 \pm (stat + systematic) 0.006 ----------- Efficiency per Pt region eff data pT[400-600]: 0.785 \pm 0.043 eff ttbar pT[400-600]: 0.814 \pm (stat) 0.007 \pm (stat + systematic) 0.008 --------- eff data pT[600-800]: 0.81 \pm 0.044 eff ttbar pT[600-800]: 0.819 \pm (stat) 0.008 \pm (stat + systematic) 0.012 --------- eff data pT[800-Inf]: 0.753 \pm 0.11 eff ttbar pT[800-Inf]: 0.802 \pm (stat) 0.024 \pm (stat + systematic) 0.029
```

