NEURAL NETWORK VERIFICATION TOOLBOX

USER MANUAL V1.0

By

Dung Hoang Tran

TABLE OF CONTENTS

		Page
LI	ST OF TABLES	. iii
LI	ST OF FIGURES	iv
I	NNV's Overview and Features	1
	I.1 NNV's overview	1
	I.2 Features	
II	Installation	3
	II.1 Operating System	3
	II.2 Dependencies	
	II.3 Installation Steps	
	II.4 Execution without installation	
Ш	Verification of feedforward neural networks (FFNN) using NNV	4
	III.1 Main steps	4
	III.2 Construct an NNV FFNN	
	III.2.1 Construct an NNV FFNN object manually	
	III.2.2 Construct an NNV FFNN object automatically from a Matlab network.	
	III.2.3 Construct an FFNNS object automatically using NNVMT	
	III.3 Specify a property of an FFNN	10
	III.4 Choose a reachability method	11
	III.5 Construct an input set for an FFNN	12
	III.5.1 Construct a star input set	12
	III.5.2 Construct a polyhedron input set	14
	III.5.3 Construct a zonotope input set	16
	III.6 Choose a number of cores for computation	19
	III.7 Verify an FFNN	19
	III.7.1 Verify an FFNN manually	20
	III.7.1.1 Compute output reachable sets	20
	III.7.1.2 Verify output reachable sets	23
	III.7.2 Verify an FFNN automatically	27
	III.8 Visualize the results	31
IV	Verification of neural network control systems (NNCS) using NNV	34
	IV.1 NNCS architecture	34
	IV.2 Main steps	
	IV.3 Construct an NNV NNCS	
	IV.3.1 Four types of NNCS	34

IV.3.2 Construct an NNV continuous linear NNCS		et an NNV continuous linear NNCS	35
	IV.3.2.1	Construct an FFNN controller object	35
	IV.3.2.2	Construct a continuous linear plant object	35
	IV.3.2.3	Construct a continuous linear NNCS object	36
IV.3.3	Construc	et an NNV discrete linear NNCS	39
	IV.3.3.1	Construct an FFNN controller object	39
	IV.3.3.2	Construct a discrete linear plant object	39
	IV.3.3.3	Construct a discrete linear NNCS object	40
IV.3.4	Construc	et an NNV continuous nonlinear NNCS	42
	IV.3.4.1	Construct an FFNN controller object	42
	IV.3.4.2	Construct a continuous nonlinear plant object	43
	IV.3.4.3	Construct a continuous nonlinear NNCS object	45
IV.3.5	Construc		47
	IV.3.5.1	Construct an FFNN controller object	47
	IV.3.5.2	Construct a discrete nonlinear plant object	47
	IV.3.5.3	Construct a discrete nonlinear NNCS object	49
Speci	fy a proper	ty of an NNCS	51
			52
Const	ruct an init	ial set of states for an NNCS	53
Choo	se a numbe	r of cores for computation	53
Verify			53
IV.8.1	Verify a	continuous linear NNCS	53
IV.8.2	Verify a	discrete linear NNCS	57
IV.8.3	Verify a	continuous nonlinear NNCS	60
IV.8.4	Verify a	discrete nonlinear NNCS	63
Visua	lize results		65
OGRAP	HY		70
	IV.3.3 IV.3.4 IV.3.5 Speci Chood Const Chood Verify IV.8.1 IV.8.2 IV.8.3 IV.8.4 Visua	IV.3.2.1 IV.3.2.2 IV.3.2.3 IV.3.3 IV.3.3 IV.3.3 IV.3.4 IV.3.4.1 IV.3.4.2 IV.3.4.3 IV.3.5 IV.3.5.1 IV.3.5.2 IV.3.5.3 Specify a proper Choose a reacha Construct an init Choose a numbe Verify an NNCS IV.8.1 Verify a IV.8.2 Verify a IV.8.3 Verify a IV.8.4 Verify a Visualize results	IV.3.2.1 Construct an FFNN controller object IV.3.2.2 Construct a continuous linear plant object IV.3.2.3 Construct a continuous linear NNCS object IV.3.3 Construct an NNV discrete linear NNCS IV.3.3.1 Construct an FFNN controller object IV.3.3.2 Construct a discrete linear plant object IV.3.3.3 Construct a discrete linear NNCS object IV.3.4.1 Construct an FFNN controller object IV.3.4.1 Construct an FFNN controller object IV.3.4.2 Construct a continuous nonlinear NNCS object IV.3.4.3 Construct a continuous nonlinear NNCS object IV.3.5.1 Construct an FFNN controller object IV.3.5.2 Construct an FFNN controller object IV.3.5.3 Construct a discrete nonlinear NNCS object Specify a property of an NNCS Choose a reachability method for an NNCS Choose a number of cores for computation Verify an NNCS IV.8.1 Verify a continuous linear NNCS IV.8.2 Verify a discrete linear NNCS IV.8.3 Verify a continuous nonlinear NNCS Visualize results

LIST OF TABLES

Table		Page
I.1	Overview of major features available in NNV. Links refer to relevant files/classes in the NNV codebase. BN refers to batch normalization layers, FC to fully-	
	connected layers, AvgPool to average pooling layers, Conv to convolutional lay-	
	ers, and MaxPool to max pooling layers	2

LIST OF FIGURES

Figure		Page
I.1	An overview of NNV.	. 1
III.1	An visualization of verification results of an FFNN. The reachable sets of all methods reaches the unsafe region $P: y_1 \ge 0.4$ (the right unbounded region of the vertical black line). However, only the "exact-star" can prove the network is unsafe while the others cannot because the over-approximation errors of the reachable sets. (We do not know the unsafe region is reached because of the actual reachable sets or the over-approximation error).	
IV.1	An architecture of NNCS supported in NNV	. 34
IV.2	Reachable set of actual distance vs. the safe distance over time	. 67
IV.3	Reachable set of actual distance and the velocity of the ego car	. 68
IV.4	Reachable set of actual distance vs. the safe distance over time	. 68
IV.5	Reachable set of actual distance and the velocity of the ego car	. 69

CHAPTER I

NNV's Overview and Features

I.1 NNV's overview




Figure I.1: An overview of NNV.

NNV¹ is an object-oriented toolbox which is built on top of the MPT toolbox Kvasnica et al. (2004) and CORA Althoff (2015) in Matlab. NNV makes use of the neural network model transformation tool (nnmt ²) which supports transforming neural network models from Keras and Tensorflow into Matlab using Open Neural Network Exachange format, and the hybrid systems model transformation and translation tool (HyST) Bak et al. (2015) for plant configuration.

The NNV toolbox contains two main modules: a *computation engine* and an *analyzer*, shown in Figure I.1. The computation engine module consists of four subcomponents: 1) the *FFNN constructor*, 2) the *NNCS constructor*, 3) *the reachability solvers*, and 4) *the evaluator*. The FFNN constructor takes a network configuration file as an input and generates a FFNN object. The NNCS constructor takes the FFNN object and the plant configuration, which describes the dynamics of a system, as inputs and then creates an NNCS object. Depending on the application, either the FFNN (or NNCS) object will be fed into a reachability solver to compute the reachable set of the FFNN (or NNCS) from a given initial set of states. Then, the obtained reachable set will be passed to the analyzer module. The analyzer module consists of three subcomponents: 1) a *visualizer*, 2) a *safety checker*, and 3) a *falsifier*. The visualizer can be called to plot the obtained reachable set. Given a safety specification, the safety checker can reason about the safety of the FFNN or NNCS

¹https://github.com/verivital/nnv

²https://github.com/verivital/nnmt

with respect to the specification. When an exact (sound and complete) reachability solver is used, such as the star-based solver, the safety checker can return either "safe," or "unsafe" along with a set of counterexamples. When an over-approximate (sound) reachability solver is used, such as the zonotope-based scheme or the approximate star-based solvers, the safety checker can return either "safe" or "uncertain" (unknown). In this case, the falsifier automatically calls the evaluator to generate simulation traces to find a counterexample. If a such counterexample is found, then NNV returns unsafe. Otherwise, it returns unknown.

I.2 Features

NNV implements a set of reachability algorithms for sequential FFNNs and CNNs, as well as NNCS with FFNN controllers. A summary of NNV's major features is given in Table I.1.

Feature	Exact Analysis	Over-approximate Analysis
Components	FFNN, CNN, NNCS	FFNN, CNN, NNCS
Plant dynamics (for NNCS)	Linear ODE	Linear ODE, Nonlinear ODE
Discrete/Continuous (for NNCS)	Discrete Time	Discrete Time, Continuous Time
Activation functions	ReLU, Satlin	ReLU, Satlin, Sigmoid, Tanh
CNN Layers	MaxPool, Conv, BN, AvgPool, FC	MaxPool, Conv, BN, AvgPool, FC
Reachability methods	Star, Polyhedron, ImageStar	Star, Zonotope, Abstract-domain, ImageStar
Reachable set/Flow-pipe Visualization	Yes	Yes
Parallel computing	Yes	Partially supported
Safety verification	Yes	Yes
Falsification	Yes	Yes
Robustness verification (for FFNN/CNN)	Yes	Yes
Counterexample generation	Yes	Yes

Table I.1: Overview of major features available in NNV. Links refer to relevant files/classes in the NNV codebase. BN refers to batch normalization layers, FC to fully-connected layers, AvgPool to average pooling layers, Conv to convolutional layers, and MaxPool to max pooling layers.

CHAPTER II

Installation

II.1 Operating System

Window 10, Mac or Linux, but either should work (CodeOcean described below is run on Linux).

II.2 Dependencies

Matlab 2018b or later (may work on earlier versions, but untested).

II.3 Installation Steps

- Clone or download the nnv toolbox from https://github.com/verivital/nnv. To operate correctly, nnv depends on other tools (CORA, NNMT, HyST), which are included as git submodules. As such, you must clone recursively, e.g., with the following:
 git clone –recursive https://github.com/verivital/nnv.git
- Open matlab, go to the directory which contains nnv, then run the install.m script located at
 ../nnv/.

II.4 Execution without installation

NNV can be executed online without installing Matlab or other dependencies through CodeOcean via the CodeOcean capsule DOI 10.24433/CO.1314285.v1: (https://doi.org/10.24433/CO.1314285.v1).

CHAPTER III

Verification of feedforward neural networks (FFNN) using NNV

III.1 Main steps

Verification of feedforward neural networks (FFNNs) consists of seven main steps:

- Construct an NNV FFNN object.
- Specify a property of the network that we want to verify.
- Choose a reachability analysis method
- Construct an input set on which we want to verify the network.
- Choose a number of cores used for computation.
- Verify the network.
- Visualize the results.

III.2 Construct an NNV FFNN

There are two ways to construct an FFNN object. The first one is manual construction layer-by-layer. The second one is parsing a trained network from Matlab, Keras, Tensorflow or from the standard ONNX format.

III.2.1 Construct an NNV FFNN object manually.

This is suitable for the case when the users know all the information about the network, i.e., weight matrices, bias vectors and activation functions of the layers of the network. An FFNN object can be constructed by an array of layer objects. In the following example, we construct an FFNN with two layers and the activation functions are 'poslin' (ReLU) and 'pureline' (linear). The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_constructor.m.

```
Code 1: Construct an FFNN object manually

/* An example of manually created nnv FFNN object */

W1 = [1 -1; 0.5 2; -1 1]; % first layer weight matrix
b1 = [-1; 0.5; 0]; % first layer bias vector

W2 = [-2 1 1; 0.5 1 1]; % second layer weight matrix
b2 = [-0.5; -0.5]; % second layer bias vector

L1 = LayerS(W1, b1, 'poslin'); % 1st layer
L2 = LayerS(W2, b2, 'purelin'); % 2nd layer

F = FFNNS([L1 L2]); % nnv feedforward neural network
```

L1 = LayerS with properties: W: [3x2 double] % weight matrix b: [3x1 double] % bias vector f: 'poslin' % activation function N: 3 % number of neurons

LayerS with properties:

L2 =

Code 2: Result of the NNV Layer objects

W: [2x3 double] % weight matrix

b: [2x1 double] % bias vector

f: 'purelin' % activation function

N: 2 % number of neurons (or outputs)

```
Code 3: Result of the NNV FFNN object
F =
  FFNNS with properties:
              Name: 'net' % name of the network
            Layers: [1 2 LayerS] % layer objects
                nL: 2 % number of layers
                nN: 5 % total number of neurons
                nI: 2 % number of inputs
                nO: 2 % number of outputs
       reachMethod: 'exact-star'
       reachOption: []
          numCores: 1
          inputSet: []
          reachSet: []
         outputSet: []
         reachTime: []
       numReachSet: []
    totalReachTime: 0
        numSamples: 2000
      unsafeRegion: []
        Operations: []
```

III.2.2 Construct an NNV FFNN object automatically from a Matlab network.

If the users train a network in Matlab and save it in a mat file, NNV can conveniently parse the trained network and construct automatically an equivalent FFNN object that can be used for verification. In the following, we construct an NNV FFNN object by parsing a toy example which is trained by General Motor researchers using Matlab. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_parse.m.

Code 4: Construct an FFNN object automatically by parsing /* An example of parsing a network trained in Matlab */ load Engine_Toy_Tansig_net.mat; % load the network F = FFNNS.parse(net); % parse the network Result: FFNNS with properties: Name: 'net' Layers: [1x3 LayerS] % layer objects nL: 3 % number of layers nN: 21 % total number of neurons nI: 2 % number of inputs nO: 1 % number of outputs reachMethod: 'exact-star' reachOption: [] numCores: 1 inputSet: [] reachSet: [] outputSet: [] reachTime: [] numReachSet: [] totalReachTime: 0 numSamples: 2000 unsafeRegion: [] Operations: []

III.2.3 Construct an FFNNS object automatically using NNVMT

NNV can also construct a feedforward fully-connected neural network in different formats including the standard ONNX format using the tool called nnvmt.

We support importing these networks from Keras, Tensorflow, Sherlock's format () and Reluplex's format (.nnet). For all of these formats, we support the common activation functions considered in the community: sigmoid, tanh, ReLU and linear. If imported from Keras, we also support a saturation linear function, with ranges 0 to 1 and -1 to 1, named satlin and satlins respectively (in MATLAB). The syntax for the function is as follows:

```
Code 5: Construct a FFNNS using NNVMT

fnn = load_nn(in1, in2, in3, in4, in5, opt);
```

Where:

- fnn is the output of the function, the neural network in NNV format (FFNNS)
- *in1* = *python_path*: path to the python environment to use (where nnvmt requirements are installed)
- in2 = nnvmt_path: path to the nnmt folder installed
- in3 = input_path: path to the neural network file we want to transform/input to NNV
- *in4* = *output_path*: path to save the transformed neural network into (as .mat file)
- in5 = formatin: format of the neural network to transform. Choose one of the following:
 - keras
 - tensorflow
 - onnx
 - sherlock
 - reluplex

• *opt*: this is an optional input. Depending on the format we are converting from, we will choose a different input here, but we will mostly use it to load neural networks trained in Keras, only when we have both an *.h5* and *.json* file for our NN. The .h5 file will be the 3rd input (input_path), and the .json file will be the 6th input (opt).

Some examples of using NNVMT to create a FFNNS are

```
Code 6: Example from Reluplex

fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn.nnet',
   '../networks', 'reluplex');
```

Code 7: Example from Sherlock fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn', '../networks', 'sherlock');

```
Code 8: Example from Keras (1)

fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn.h5',
'../networks', 'keras');
```

```
Code 9: Example from Keras (2)

fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn.h5',
'../networks', 'keras', 'name_of_nn.json');
```

```
Code 10: Example from Tensorflow

fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn'*,
'../networks', 'tensorflow');
```

*Note: In the case of Tensorflow, based on the common practice of saving both the checkpoint

and the .meta file in the same folder, in3 (input_path) will point to the folder where these two files are located.

```
Code 11: Example from ONNX

fnn = load_nn('../python', 'nnv/engine/nnmt', 'name_of_nn.onnx',
   '../networks', 'onnx');
```

As an additional feature, after transforming any of these networks into a name_of_nn.mat file, you can load this file in a very simple way using load_nn.m as well. Simply use the function by leaving all inputs as blank and write the path to the .mat file in the opt position. Example:

```
Code 12: Construct a FFNNS after transforming to .mat

fnn = load_nn('','','','','','name_of_nn.mat');
```


For more detail, please visit this tool at: https://github.com/verivital/nnvmt.

III.3 Specify a property of an FFNN

After constructing a FFNN network, the users need to specify the property of the network that they want to verify. The property is a linear predicate over the outputs of the network which is defined in the form of $P \triangleq Gy \leq g$, where y is the output vector of the network. Let P be an unsafe region, if the reachable sets of the network reach the unsafe region, the network is unsafe, otherwise, it is safe. In NNV, we use a HalfSpace object to represent a property. In the following example, we specify an unsafe region for the network constructed in section III.2.1. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_specify_property.m.

III.4 Choose a reachability method

To verify whether a network violates its (safety) property or not, NNV computes reachable set of the network corresponding to a specific input set. NNV supports different reachability schemes for FFNN including "exact-star", "approx-star", "exact-polyhedron", "approx-zono", and "abs-dom" as depicted in Table I.1. The following example chooses "exact-star" as the reachability method for verification of the network constructed in section III.2.1. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_choose_reach_method.m.



III.5 Construct an input set for an FFNN

The input set to the network could be a *star set*, a *zonotope* or a *polyhedron*, depending on the reachability method we want to use for verification.

III.5.1 Construct a star input set

A star input set is required for verification of the network when we use the "exact-star", "approx-star", and "abs-dom" reachability methods. A star set (or simply star) Θ is a tuple $\langle c, V, P \rangle$ where $c \in \mathbb{R}^n$ is the center, $V = \{v_1, v_2, \cdots, v_m\}$ is a set of m vectors in \mathbb{R}^n called basis vectors, and $P : \mathbb{R}^m \to \{\top, \bot\}$ is a predicate. The basis vectors are arranged to form the star's $n \times m$ basis matrix. In NNV, we restrict the predicates to be a conjunction of linear constraints, $P(\alpha) \triangleq C\alpha \leq d$ where, for p linear constraints, $C \in \mathbb{R}^{p \times m}$, α is the vector of m-variables, i.e., $\alpha = [\alpha_1, \cdots, \alpha_m]^T$, and $d \in \mathbb{R}^{p \times 1}$. A star is an empty set if and only if $P(\alpha)$ is empty. The set of states represented by the star is given as:

$$\llbracket \Theta \rrbracket = \{ x \mid x = c + \sum_{i=1}^{m} (\alpha_i v_i) \text{ such that } P(\alpha_1, \dots, \alpha_m) = \top \}.$$
 (III.1)

To construct a star set, we have two common ways. The first one constructs a star set when all information of the set is known, i.e., we have $\{c, v_1, \ldots, v_m, C, d\}$. In NNV, we combine the center vector c and the basis vectors v_j into a single basis matrix $V = [c \ v_1 \ \ldots \ v_m]$. The second one constructs a star set from the ranges of all individual inputs. The following example

construct a star set using different approaches. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_choose_construct_star.m.

```
Code 15: Construct a star set when all information is known
/* An example of constructing a star set */
c1 = [1; -1]; % center vector
v1 = [1; 0]; % basis vector 1
v2 = [0; 0.5]; % basis vector 2
V = [c1 \ v1 \ v2]; \%  basis matrix
% predicate constraint: P = C*[a] <= d</pre>
% -1<= a1 <= 1, 0 <= a2 <= 1, a1 + a2 <= 1
C = [1 \ 0; -1 \ 0; \ 0 \ 1; \ 0 \ -1; \ 1 \ 1]; \% constraint matrix
d = [1; 1; 1; 0; 1];
                                   % constraint vector
I1 = Star(V, C, d); % star input set
Result
T1 =
  Star with properties:
                V: [2x3 double] % basis matrix
                C: [5x2 double] % constraint matrix
                d: [5x1 double] % constraint vector
              dim: 2 % dimension of star
            nVar: 2 % number of predicates variables
    predicate_lb: [2x1 double] % lower bound of predicate vars
    predicate_ub: [2x1 double] % upper bound of predicate vars
        state_lb: [] % lower bound state vector
        state_ub: [] % upper bound state vector
```

```
Code 16: Construct a star set from input ranges
/* An example of constructing a star set from input ranges */
% -2 <= x1 <= 2
% 0 <= x2 <= 1
1b = [-2; 0]; % lower bound vector
ub = [2; 1]; % upper bound vector
I2 = Star(lb, ub); % star input set
Result
I2 =
  Star with properties:
               V: [2x3 double] % basis matrix
               C: [4x2 double] % constraint matrix
               d: [4x1 double] % constraint vector
             dim: 2
% dimension of star
            nVar: 2 % number of predicates variables
    predicate_lb: [2x1 double] % lower bound of predicate vars
    predicate_ub: [2x1 double] % upper bound of predicate vars
        state_lb: [2x1 double] % lower bound state vector
        state_ub: [2x1 double] % upper bound state vector
```

III.5.2 Construct a polyhedron input set

A polyhedron input is required when we use the "exact-polyhedron" reachability method for verification. In NNV, we require the polyhedron input set is a bounded set. NNV uses MPT toolbox Kvasnica et al. (2004) to construct, manipulate and visualize a polyhedron. A polyhedron is defined

as.

$$P = \{x \mid Ax \le b, A_e x = b_e\}$$
 (III.2)

There are two common ways to construct a polyhedron. The first one uses the polyhedron related matrices A, B, A_e , and B_e . The second one constructs a polyhedron from the ranges of the states. In this case, a polyhedron is a hyper-rectangle. The following examples construct a polyhedron using different approaches. The code for these example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_choose_construct_polyhedron.m.

```
Code 18: Construct a polyhedron input set from matrices
/* An example of constructing a polyhedron input set */
A = [2 1; 1 0; -1 0; 0 1; 0 -1; 1 1]; % inequality matrix
b = [2; 1; 1; 0; 1; 1]; % inequality vector
I2 = Polyhedron('A', A, 'b', b);% polyhedron without equalities
Ae = [2 3]; % equality matrix
be = 1.5; % equality vector
% polyhedron with one equality
I3 = Polyhedron('A', A, 'b', b, 'Ae', Ae, 'be', be);
Results
Ι2
Polyhedron in R<sup>2</sup> with representations:
  H-rep (redundant) : Inequalities 6 | Equalities
  V-rep
                   : Unknown (call computeVRep() to compute)
Functions : none
Ι3
Polyhedron in R<sup>2</sup> with representations:
  H-rep (redundant) : Inequalities 6 | Equalities
                : Unknown (call computeVRep() to compute)
  V-rep
Functions : none
```

III.5.3 Construct a zonotope input set

A zonotope input set is required when we use "approx-zono" reachability method for verification.

A zonotope has a similar structure as a star except that all predicate variables are in the ranges of

[-1, 1]. Mathematically, a zonotope is defined as:

$$Z = \{ x \mid x = c + \sum_{i=1}^{m} \alpha_i \times v_i \}, \tag{III.3}$$

where c is the center vector, v_i is a *generator* (we just call a basis vector) and α_i is a predicate variable of the range [-1, 1].

In NNV, we can construct a zonotope if we know the center vector c and the basis matrix $V = [v_1 \ v_2 \ ... \ v_m]$. We can also construct a zonotope if we know the ranges of all individual inputs. The following example constructs a zonotope using different approaches. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_choose_construct_zonotope.m.

```
Code 19: Construct a zonotope input set
/* An example of constructing zonotope input set */
c = [-1; 0]; % center vector
v1 = [2; 1]; % 1st basis vector
v2 = [1; 1]; % 2nd basis vector
v3 = [-1; 1]; % 3rd basis vector
V = [v1 \ v2 \ v3]; \%  basis matrix
% zonotope from center vector and basis matrix
I1 = Zono(c, V);
lb = [-1; 1]; % lower bound vector
ub = [1; 2]; % upper bound vector
% zonotope from input ranges
I2 = Box(lb, ub); % a box object
I2 = I2.toZono;  % transform to zonotope
Results
I1 =
  Zono with properties:
     c: [2x1 double] % center vector
     V: [2x3 double] % basis matrix
    I2 =
  Zono with properties:
     c: [2x1 double] % center vector
     V: [2x2 double] % basis matrix
                    % dimension
    dim: 2
```

III.6 Choose a number of cores for computation

We only worry about the number of cores used for computation when using the exact reachability methods, i.e., "exact-star" and "exact-polyhedron". When over-approximate reachability methods, i.e., "approx-star", "approx-zono", and "abs-dom", NNV uses one core for the computation. For FFNN with piecwise linear activiation function such as ReLU (poslin) and Saturation (satlin), NNV can compute the exact reachable set of the network using the "exact-star" and "exact-polyhedron" reachability schemes. The "exact-star" method is faster and more scalable than the "exact-polyhedron" method.

NNV computes the reachable set of the network layer-by-layer, i.e., the output of the current layer is the input for the next layer. In the exact analysis, a single input set can split into multiple output sets after one layer. Therefore, to speed up the computation for the exact analysis, NNV uses "parfor" option in the Matlab Parallel Computing ToolBox, i.e., a layer can handle independently multiple input sets at the same time using multiple cores. Therefore, the users need to choose the number of cores they want to use for the computation which depend on the configuration of their machines. The following example simply chooses 4 cores for the computation.

Code 20: Choose number of cores for computation

```
/* An example of choosing a number of cores */
numCores = 4; % use 4 cores for computation
```

III.7 Verify an FFNN

All the steps have been done so far:

- Construct an NNV FFNN object.
- Specify a property of the network that we want to verify.
- Choose a reachability analysis method
- Construct an input set on which we want to verify the network.
- Choose a number of cores used for computation.

There are two options for users to verify an FFNN. The first option is that, the users first call *reach* method in the FFNN object to compute the output sets of the network. Then, users can verify if all the output sets satisfy the property. This option gives a deeper understanding how NNV verifies a network as we distinct the reachability problem and the verification problem into two seperate steps. The second option is just an automatic combination of these two steps into a method call *verify* in the FFNN object.

III.7.1 Verify an FFNN manually

III.7.1.1 Compute output reachable sets

To compute output reachable sets of an FFNN, we use the *reach* method in the network object. In the following example, we use different reachability methods to compute output reachable sets of the network constructed in section III.2.1. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_compute_reachSet.m.

Code 21: Compute reachable sets of an FFNN /* An example of computing reachable sets of an FFNN */ /* construct an NNV network W1 = [1 -1; 0.5 2; -1 1];b1 = [-1; 0.5; 0]; $W2 = [-2 \ 1 \ 1; \ 0.5 \ 1 \ 1];$ b2 = [-0.5; -0.5];L1 = LayerS(W1, b1, 'poslin'); L2 = LayerS(W2, b2, 'purelin'); F = FFNNS([L1 L2]); % construct an NNV FFNN /* choose the number of cores numCores = 2;/* construct input set lb = [-1; -2]; % lower bound vectorub = [1; 0]; % upper bound vector I = Star(lb, ub); % star input set I_Poly = Polyhedron('lb', lb, 'ub', ub); % polyhedron input set B = Box(lb, ub); % a box input set I_Zono = B.toZono; % convert to a zonotope /* compute the reachable sets with a selected method [R1, t1] = F.reach(I, 'exact-star', numCores); [R2, t2] = F.reach(I_Poly, 'exact-polyhedron', numCores); [R3, t3] = F.reach(I, 'approx-star'); [R4, t4] = F.reach(I_Zono, 'approx-zono'); [R5, t5] = F.reach(I, 'abs-dom');

Code 22: Reachable sets and computation time results R1 = 1x6 Star array with properties: С d dim nVar predicate_lb predicate_ub state_lb state_ub t1 = 0.1347R2 = Array of 6 polyhedra. t2 = 0.3003R3 = Star with properties: V: [2x6 double] C: [13x5 double] d: [13x1 double] dim: 2 nVar: 5 predicate_lb: [5x1 double] predicate_ub: [5x1 double] state_lb: [] state_ub: [] t3 = 0.0134

Code 23: Reachable sets and computation time results (cont.) R4 = Zono with properties: c: [2x1 double] V: [2x5 double] dim: 2 0.0069 R5 = Star with properties: V: [2x6 double] C: [10x5 double] d: [10x1 double] dim: 2 nVar: 5 predicate_lb: [5x1 double] predicate_ub: [5x1 double] state_lb: [] state_ub: [] t5 =0.0064

We can see that the exact reachable set of the network contains 6 star sets or 6 polyhedra. The "exact-star" method is faster than the "exact-polyhedron" method (t1 = 0.1347 < t2 = 0.3003). The over-approximate reachability method produces a single output set which can be a star or a zonotope depending on which method is used.

III.7.1.2 Verify output reachable sets

With the output reachable sets computed previously, we can verify whether or not they violates a property of the network. Assume that we want to verify the following property:

$$P = \{ y \in R^2 | y_1 \ge 1.5 \}. \tag{III.4}$$

To prove that the network satisfies (SAT) or does not satisfy (UNSAT) the property, we check the intersection between the reachable sets with the property which is given in the following example. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_verify_reachSet.m.

Code 24: Verify output reachable sets /* An example of verifying output reachable sets */ P = HalfSpace([-1 0], -1.5); % P: y1 >= 1.5P_Poly = Polyhedron('A', P.G, 'b', P.g); rs1 = cell(1, length(R1));rs2 = cell(1, length(R2));for i=1:length(R1) M = R1(i).intersectHalfSpace(P.G, P.g); % verifying R1 if isempty(M) $rs1{i} = 'UNSAT';$ else $rs1{i} = 'SAT';$ end end for i=1:length(R2) M = R2(i).intersect(P_Poly); % verifying R2 if M.isEmptySet $rs2{i} = 'UNSAT';$ else rs2{i} = 'SAT'; end Results rs1 = rs2 = 1x6 cell array {'UNSAT'}{'UNSAT'}{'UNSAT'}{'UNSAT'}{'UNSAT'}

```
Code 25: Verify output reachable sets (cont.)
/* An example of verifying output reachable sets */
M = R3.intersectHalfSpace(P.G, P.g); % verify R3
if isempty(M)
    rs3 = 'UNSAT';
else
   rs3 = 'SAT';
end
M = R4.intersectHalfSpace(P.G, P.g); % verify R4
if isempty(M)
    rs4 = 'UNSAT';
else
    rs4 = 'SAT';
end
M = R5.intersectHalfSpace(P.G, P.g); % verify R5
if isempty(M)
    rs5 = 'UNSAT';
else
    rs5 = 'SAT';
{\sf end}
Results
rs3 = 'UNSAT';
rs4 = 'SAT';
rs5 = 'SAT';
```

One can see that, when using the exact reachability methods, the output reachable sets do not

reach the property P which return UNSAT results for all reachable sets. When over-approximate reachability methods are used, only the "approx-star" method returns UNSAT whiles the "approx-zono" and the "abs-dom" methods return SAT. This is because the reachable sets obtained by the "approx-zono" and the "abs-dom" methods are conservative and reach the property. Users can observe the conservativeness of different over-approximate reachability approaches by visualizing the reachable sets of the network which is addressed in the next section.

The conservativeness of the computed reachable sets is very important to prove the safety of a network. When the reachable sets of the network reach an unsafe region, we say the network is unsafe, otherwise, it is safe. Due to the conservativeness in the reachable set computation, there is the case that the network is safe, however, the computed over-approximate reachable set reaches the unsafe region. In this case, we cannot prove the safety of the network using the over-approximate reachability.

III.7.2 Verify an FFNN automatically

After specifying a property, we can verify automatically an FFNN using its *verify* method. In this method, we specify the property as an unsafe property. The verification result may be "safe", "unsafe", or "unknown". In this method, we do not use "exact-polyhedron" method due to its low scalability. The verify method first runs some random simulations by sampling randomly the input set to see if the unsafe region is reached. If not, it performs reachability analysis to compute the reachable sets and then proves the safety of the network. Therefore, beside the input set, unsafe property, and number of cores parameters, we have one more parameter called the number of samples that is used for randomly generating simulations. If the users set this parameter to zero, then the verify method neglects the randomly generating simulations step.

Code 26: Verify an FFNN automatically

```
/* An example of automatically verifying an FFNN */
/* construct an NNV network
W1 = [1 -1; 0.5 2; -1 1];
b1 = [-1; 0.5; 0];
W2 = [-2 \ 1 \ 1; \ 0.5 \ 1 \ 1];
b2 = [-0.5; -0.5];
L1 = LayerS(W1, b1, 'poslin');
L2 = LayerS(W2, b2, 'purelin');
F = FFNNS([L1 L2]); % construct an NNV FFNN
/* construct input set
lb = [-1; -2]; % lower bound vector
ub = [1; 0]; % upper bound vector
I = Star(lb, ub); % star input set
B = Box(lb, ub); % a box input set
I_Zono = B.toZono; % convert to a zonotope
/* Properties
P = HalfSpace([-1 0], -1.5); % P: y1 >= 1.5
/* verify the network
nC = 1; % number of cores
nS = 100; % number of samples
[safe1, t1, cE1] = F.verify(I, P, 'exact-star', nC, nS);
[safe2, t2, cE2] = F.verify(I, P, 'approx-star', nC, nS);
[safe3, t3, cE3] = F.verify(I_Zono, P, 'approx-zono', nC, nS);
[safe4, t4, cE4] = F.verify(I, P, 'abs-dom', nC, nS);
```

```
Code 27: Results
                                           % safe
safe1 =
         0.3892;
                     % verification time
                     % counter examples
cE1
      = [];
safe2 =
         1;
                                           % safe
         0.2907;
                   % verification time
t2
cE2
      = [];
                     % counter examples
                                           % unknown
safe3 =
         2;
         0.3300;
                     % verification time
cE3
                     % counter examples
      = [];
safe4 =
         2;
                                           % unknown
         0.3213;
                     % verification time
cE4
      = [];
                     % counter examples
```

We can see that the "exact-star" and "approx-star" methods can prove the safety of the network. The reachable sets computed by these methods do not reach the unsafe region, i.e., property P. Because the network is safe, there are no counterexamples in this case. A counterexample is an input that make the network unsafe, i.e., the output of the network corresponding to the counter input relies in the unsafe region. When we use the "approx-zono" and "abs-dom" methods, we cannot prove the safety of the network. The reachable sets obtained by these methods reach the unsafe region. However, we do not know whether the exact reachable set of the network reaches the unsafe region or because of the conservativeness of the over-approximation reachable sets. We can conclude that the "approx-star" method is less conservative than the "approx-zono" and "abs-dom" methods.

If we change the property P into $y_1 \ge 0.4$, we have a new verification results as follows.

```
Code 28: Verify automatically an FFNN
/* An example of automatically verifying an FFNN */
/* Properties
P = HalfSpace([-1 0], -0.4); % P: y1 >= 1.5
/* verify the network
nC = 1; % number of cores
nS = 100; % number of samples
[safe1, t1, cE1] = F.verify(I, P, 'exact-star', nC, nS);
[safe2, t2, cE2] = F.verify(I, P, 'approx-star', nC, nS);
[safe3, t3, cE3] = F.verify(I_Zono, P, 'approx-zono', nC, nS);
[safe4, t4, cE4] = F.verify(I, P, 'abs-dom', nC, nS);
Results
t1 = 0.3079; % verification time
cE1 = 1x4 Star array; % counter examples
t2 = 0.2581; % verification time
cE2 = []; % counter examples
safe3 = 2 ; % unknown
t3 = 0.2478; % verification time
cE3 = [];
                % counter examples
safe4 = 2;
                % unknown
t4 = 0.2435;
                % verification time
                % counter examples
cE4 = [];
```

We can see that the "exact-star" can prove that the network is unsafe. Notably, it can computes

all subsets of the input set that cause the network unsafe. The counterexamples is an array of 4 star sets which are the subsets of the input set. This is a novel feature of NNV compared with other tools. The user can increase the number of samples to see how it affects the results. When the number of samples increase, we can find counterexamples by just using random simulations. However, this approach is not efficient in general. We need a better approach for falsification of neural networks in the future.

III.8 Visualize the results

Using NNV, users can intuitively observe the verification results by plotting the output reachable sets of the network and the unsafe region. After executing the "verify" method, if there is no counterexamples found by simulation, NNV performs reachability analysis to prove the safety of the network. The output reachable sets of the network are stored in the *FFNN.outputSet* property which can be visualized in some specific subspace using the "visualize" method in the *FFNN* object. This visualize method plots the mapped reachable sets of the output set in 2-D or 3-D space. The input to this method is a mapping matrix G and a offset vector g. Mathematically, if g is the output of the network, the visual method plots the set of g in g is the network, the visual method plots the set of g in g is the number of rows of the mapping matrix and the offset vector is 3. If users do not use the offset vector, they can simply set it as an empty array or a zero vector.

The following example visualizes the reachable sets and the unsafe region of the network used in previous example. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_ffnns_visualize.m.

Code 29: Visualize verification results /* An example of visualizing verification results of an FFNN */ map_mat = eye(2); map_vec = []; % mapping matrix & vector P_poly = Polyhedron('A', P.G, 'b', P.g); % polyhedron obj subplot(2, 2, 1); [safe1, t1, cE1] = F.verify(I, P, 'exact-star', nC, nS); F.visualize(map_mat, map_vec); % plot y1 y2 hold on; plot(P_poly); % plot unsafe region title('exact-star', 'FontSize', 13); subplot(2,2,2); [safe2, t2, cE2] = F.verify(I, P, 'approx-star', nC, nS); F.visualize(map_mat, map_vec); % plot y1 y2 hold on; plot(P_poly); % plot unsafe region title('approx-star', 'FontSize', 13); subplot(2,2,3); [safe3, t3, cE3] = F.verify(I_Zono, P, 'approx-zono', nC, nS); F.visualize(map_mat, map_vec); % plot y1 y2 hold on; plot(P_poly); % plot unsafe region title('approx-zono', 'FontSize', 13); subplot(2, 2, 4); [safe4, t4, cE4] = F.verify(I, P, 'abs-dom', nC, nS);F.visualize(map_mat, map_vec); % plot y1 y2 hold on; plot(P_poly); % plot unsafe region title('abs-dom', 'FontSize', 13);

The visualization of the verification results is depicted in Figure III.1. From the figure, one can see that the "approx-star" method produces a smaller reachable set than the "approx-zono" and the "abs-dom" methods. The reachable sets of all methods reaches the unsafe region $P: y_1 \ge 0.4$ (the right unbounded region of the vertical black line). However, only the "exact-star" can prove the network is unsafe while the others cannot because the over-approximation errors of the reachable sets. (We do not know the unsafe region is reached because of the actual reachable sets or the over-approximation error).




Figure III.1: An visualization of verification results of an FFNN. The reachable sets of all methods reaches the unsafe region $P: y_1 \ge 0.4$ (the right unbounded region of the vertical black line). However, only the "exact-star" can prove the network is unsafe while the others cannot because the over-approximation errors of the reachable sets. (We do not know the unsafe region is reached because of the actual reachable sets or the over-approximation error).

CHAPTER IV

Verification of neural network control systems (NNCS) using NNV

IV.1 NNCS architecture

NNV supports verification of closed loop control systems with an *FFNN controller with piecewise linear activation functions*. The architecture of such system is depicted in Figure IV.1. The plant model in the system can be continuous or discrete, linear or nonlinear.




Figure IV.1: An architecture of NNCS supported in NNV.

IV.2 Main steps

Verification of a neural network control system (NNCS) consists of seven main steps:

- Construct an NNV NNCS object.
- Specify a property of the system that we want to verify.
- Choose a reachability analysis method
- Construct an initial set of states of the system.
- Choose a number of cores used for computation.
- Verify the system.
- Visualize the results.

IV.3 Construct an NNV NNCS

IV.3.1 Four types of NNCS

Depending on the plant model, NNV provides different classes of NNCS including:

- 1. The *LinearNNCS* class for NNCS with continuous linear plant model.
- 2. The *DLinearNNCS* class for NNCS with dicrete linear plant model.
- 3. The *NonlinearNNCS* for NNCS with continuous nonlinear plant model.
- 4. The *DNonlinearNNCS* class for NNCS with discrete nonlinear plant model.

IV.3.2 Construct an NNV continuous linear NNCS

An NNV continuous linear NNCS object is constructed by the FFNN controller object and the continuous linear plant model object.

IV.3.2.1 Construct an FFNN controller object

This is construction of an FFNN object. Please refer to section III.2 for the detail.

IV.3.2.2 Construct a continuous linear plant object

A continuous linear plant is described by the following equation.

$$\dot{x}(t) = Ax(t) + Bu(t), y(t) = Cx(t) + Du(t).$$
 (IV.1)

A continuous linear plant object is constructed using the *LinearODE* class in NNV. The inputs to the constructor of the *LinearODE* class are:

- 1. The system matrices A, B, C and D.
- 2. The *control period*, i.e., the plant takes control input at every *control period* seconds.
- 3. The number of reachability steps in one control period.

the system matrices A, B, C and D. We note that in verification of NNCS, we only consider the case of y(t) = Cx(t). Therefore, the matrix D is set to empty. The following example constructs a continuous linear plant object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_linearODE.m.

```
Code 30: Construct a continuous linear plant object
/* An example of constructing a continuous linear plant model */
A = [0 \ 1; -5 \ -2]; \%  system matrix
B = [0;3]; % control matrix
C = [0 1]; % output feedback matrix
        % output control matrix
D = [];
Tc = 0.1; % control period
Nr = 20; % number of reachability steps in one control period
sys = LinearODE(A, B, C, D, Tc, Nr); % plant object
Result
sys =
  LinearODE with properties:
                A: [2x2 double]
                B: [2x1 double]
                C: [0 1]
                D: []
              dim: 2
               nI: 1
               n0: 1
    controlPeriod: 0.1000
      numReachSteps: 20
```

IV.3.2.3 Construct a continuous linear NNCS object

After constructing an FFNN controller and a continuous linear plant object. A linear NNCS object can be constructed by feeding the FFNN controller object and the linear plant object into the constructor of the *LinearNNCS* class. The following example constructs an NNV continuous lin-

ear NNCS object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_linearNNCS.m.

Code 31: Construct a continuous linear NNCS object /* An example of constructing a continuous linear NNCS object */ /* construct an FFNN controller L1 = LayerS([2; 1], [0.5; -1], 'poslin'); L2 = LayerS([1 -1], 0.2, 'purelin');F = FFNNS([L1 L2]);/* construct a plant model $A = [0 \ 1; -5 \ -2]; \%$ system matrix B = [0;3];% control matrix % output control matrix D = [];Tc = 0.1; % control period Nr = 20; % number of reachability steps in one control period sys = LinearODE(A, B, C, D, Tc, Nr); % plant object /* construct a linear NNCS object ncs = LinearNNCS(F, sys);

Code 32: Construction results ncs = LinearNNCS with properties: controller: [1x1 FFNNS] plant: [1x1 LinearODE] nO: 1 % number of outputs nI: 1 % number of inputs nI_ref: 0 % ** unused nI_fb: 1 % number of feedbacks method: 'exact-star' plantReachMethod: 'direct' transPlant: [1x1 LinearODE] plantReachSet: {} plantIntermediateReachSet: {} plantNumOfSimSteps: 20 controlPeriod: 0.1000 controllerReachSet: {} numCores: 1 ref_I: [] init_set: [] reachTime: 0 simTraces: {} controlTraces: {} falsifyTraces: {} falsifyTime: 0

IV.3.3 Construct an NNV discrete linear NNCS

Constructing an NNV discrete linear NNCS object is similar to constructing an NNV continuous linear NNCS object. The only difference is that we use the *DLinearODE* class to construct the discrete linear plant model.

IV.3.3.1 Construct an FFNN controller object

This is construction of an FFNN object. Please refer to section III.2 for the detail.

IV.3.3.2 Construct a discrete linear plant object

A discrete linear plant model is defined as follows.

$$x[k+1] = Ax[k] + Bu[k], \ y[k] = Cx[k] + Du[k].$$
 (IV.2)

We note that in verification of NNCS, we only consider the case of y[k] = Cx[k]. Therefore, the matrix D is set to empty. The following example constructs a discrete linear plant object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_dlinearODE.m.

```
Code 33: Construct a discrete linear plant object
/* An example of constructing a discrete linear plant model */
A = [0 \ 1; -5 \ -2]; \%  system matrix
B = [0;3]; % control matrix
D = [];
       % output control matrix
Ts = 0.1; % sampling time
sys = DLinearODE(A, B, C, D, Ts); % plant object
Result
sys =
  DLinearODE with properties:
     A: [2x2 double] % system matrix
     B: [2x1 double] % control matrix
     C: [0 1] % output feedback matrix
     D: [] % output control matrix
    nI: 1 % number of inputs
    nO: 1 % number of outputs
    dim: 2 % system dimension
    Ts: 0.1000 % sampling time
```

IV.3.3.3 Construct a discrete linear NNCS object

After constructing an FFNN controller and a discrete linear plant object. A discrete linear NNCS object can be constructed by feeding the FFNN controller object and the discrete linear plant object into the constructor of the *DLinearNNCS* class. The following example constructs an NNV discrete linear NNCS object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_dlinearNNCS.m.

Code 34: Construct a discrete linear NNCS /* An example of constructing an discrete linear NNCS object */ /* construct a FFNN controller L1 = LayerS([2; 1], [0.5; -1], 'poslin');L2 = LayerS([1 -1], 0.2, 'purelin');F = FFNNS([L1 L2]);/* construct a plant model $A = [0 \ 1; -5 \ -2]; \%$ system matrix % control matrix B = [0;3];% output feedback matrix C = [0 1];% output control matrix D = [];% sampling time Ts = 0.1;sys = DLinearODE(A, B, C, D, Ts); % plant object /* construct a linear NNCS object ncs = DLinearNNCS(F, sys);

```
Code 35: Construction results
ncs =
  DLinearNNCS with properties:
            controller: [1x1 FFNNS]
                  plant: [1x1 DLinearODE]
                     nO: 1 % number of output
                     nI: 1 % number of input
                 nI_ref: 0 % **unused
                  nI_fb: 1 % number of feedbacks
                 method: 'exact-star'
         plantReachSet: {}
    controllerReachSet: {}
               numCores: 1
                  ref_I: []
              init_set: []
              reachTime: 0
             simTraces: {}
         controlTraces: {}
         falsifyTraces: {}
           falsifyTime: 0
```

IV.3.4 Construct an NNV continuous nonlinear NNCS

IV.3.4.1 Construct an FFNN controller object

This is construction of an FFNN object. Please refer to section III.2 for the detail.

IV.3.4.2 Construct a continuous nonlinear plant object

We use the *NonLinearODE* class to construct a continuous nonlinear plant object. A nonlinear continuous plant is defined as:

$$\dot{x}(t) = f(x, u, t), \ y(t) = Cx(t).$$
 (IV.3)

where x(t) is the state vector, u(t) is the control input vector, y(t) is the output vector, and C is the output matrix.

The *NonLinearODE* class takes the following parameters as inputs:

- 1. The *number of states*.
- 2. The number of control inputs.
- 3. The dynamics function f(x, u, t).
- 4. The *reachability time step* of the plant.
- 5. The *control period* of the plant.
- 6. The *output matrix* defining the output vector of the plant.

In the following example, we construct a continuous nonlinear car model with 6 states and 1 control input. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_nonlinearODE.m.

Code 36: Construct a continuous nonlinear plant

```
/* An example of constructing a continuous nonlinear plant */
Tr = 0.01; % reachability time step for the plant
Tc = 0.1; % control period of the plant
% output matrix
C = [0 \ 0 \ 0 \ 1 \ 0; 1 \ 0 \ 0 \ -1 \ 0 \ 0; \ 0 \ 1 \ 0 \ 0 \ -1 \ 0]; \%  output matrix
car = NonLinearODE(6, 1, @car_dynamics, Tr, Tc, C);
function [dx]=car_dynamics(t,x,a_ego)
% note: t need to be here to do reachability
        mu=0.0001; % friction parameter
        % x1 = lead_car position
        % x2 = lead_car velocity
        % x3 = lead_car internal state
        % x4 = ego_car position
        % x5 = ego_car velocity
        % x6 = ego_car internal state
        % lead car dynamics
        a_{lead} = -5;
        dx(1,1)=x(2);
        dx(2,1) = x(3);
        dx(3,1) = -2 * x(3) + 2 * a_lead - mu*x(2)^2;
        % ego car dyanmics
        dx(4,1) = x(5);
        dx(5,1) = x(6);
        dx(6,1) = -2 * x(6) + 2 * a_ego - mu*x(5)^2;
end
```

IV.3.4.3 Construct a continuous nonlinear NNCS object

After constructing an FFNN controller and a continuous nonlinear plant object, a continuous nonlinear NNCS object can be constructed by feeding the FFNN controller object and the plant object into the constructor of the *NonlinearNNCS* class.

The following example constructs an NNV continuous nonliner NNCS object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_nonlinearNNCS.m.

Code 38: Construct a continuous nonlinear NNCS object

```
/* An example of constructing a continuous nonlinear NNCS */
/ FFNN controller
load controller_5_20.mat;
weights = network.weights;
bias = network.bias;
n = length(weights);
Layers = [];
for i=1:n - 1
    L = LayerS(weights{1, i}, bias{i, 1}, 'poslin');
    Layers = [Layers L];
end
L = LayerS(weights{1, n}, bias{n, 1}, 'purelin');
Layers = [Layers L];
controller = FFNNS(Layers);
/* car model
Tr = 0.01; % reachability time step for the plant
Tc = 0.1; % control period of the plant
% output matrix
C = [0 \ 0 \ 0 \ 1 \ 0; 1 \ 0 \ 0 \ -1 \ 0 \ 0; \ 0 \ 1 \ 0 \ 0 \ -1 \ 0]; \%  output matrix
car = NonLinearODE(6, 1, @car_dynamics, Tr, Tc, C);
ncs = NonlinearNNCS(controller, car); % system
```

```
Code 39: Results
ncs =
  NonlinearNNCS with properties:
            controller: [1x1 FFNNS]
                 plant: [1x1 NonLinearODE]
           feedbackMap: 0 % ** unused
                     nO: 3 % number of outputs
                     nI: 5 % number of inputs
                nI_ref: 2 % number of reference inputs
                 nI_fb: 3 % number of feedback outputs
                 ref_I: [] % reference input to controller
              init_set: [] % initial set of states of the plant
          reachSetTree: []
    totalNumOfReachSet: 0
             reachTime: 0
            controlSet: []
              simTrace: []
          controlTrace: []
```

IV.3.5 Construct an NNV discrete nonlinear NNCS

IV.3.5.1 Construct an FFNN controller object

This is construction of an FFNN object. Please refer to section III.2 for the detail.

IV.3.5.2 Construct a discrete nonlinear plant object

We use the *DNonLinearODE* class to construct a discrete nonlinear plant object. A discrete nonlinear plant is defined as:

$$x[k+1] = f(x[k], u[k]), y(k) = Cx(k).$$
 (IV.4)

where x[k] is the state vector, u[k] is the control input vector, y[k] is the output vector, and C is the output matrix.

The DNonLinearODE class takes the number of states, the number of control inputs, the dynamics function f(x[k],u[k]), and the sampling period T_s as inputs. The users also need to set the output_mat C defining the outputs that are feedback to the controller. In the following example, we construct a discrete nonlinear mountain car model with 2 states and 1 control input. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_dnonlinearODE.m.


```
Code 41: Results

Car =

DNonLinearODE with properties:

options: [1x1 struct]

dynamics_func: @discrete_car_dynamics

dim: 2 % number of states

nI: 1 % number of inputs

n0: 2 % number of outputs

C: [2x2 double] % output matrix

Ts: 0.5000 % sampling period

intermediate_reachSet: []
```

IV.3.5.3 Construct a discrete nonlinear NNCS object

After constructing an FFNN controller and a discrete nonlinear plant object, a discrete nonlinear NNCS object can be constructed by feeding the FFNN controller object and the plant object into the constructor of the *DNonlinearNNCS* class.

The following example constructs an NNV discrete nonlinear NNCS object. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_construct_dnonlinearNNCS.m.

Code 42: Construct a discrete nonlinar NNCS

```
/* An example of constructing a discrete nonlinear NNCS */
/* FFNN controller
load MountainCar_ReluController.mat;
W = nnetwork.W; % weight matrices
b = nnetwork.b; % bias vectors
n = length(W);
Layers = [];
for i=1:n-1
    L = LayerS(W{1, i}, b{1, i}, 'poslin');
    Layers = [Layers L];
end
L = LayerS(W{1, n}, b{1, n}, 'purelin');
Layers = [Layers L];
controller = FFNNS(Layers);
/* MountainCar
Ts = 0.5; % sampling time
C = [1 \ 0; \ 0 \ 1]; \%  output matrix
Car = DNonLinearODE(2, 1, @discrete_car_dynamics, Ts, C);
ncs = DNonlinearNNCS(controller, Car); % system
```

```
Code 43: Result
ncs =
  DNonlinearNNCS with properties:
            controller: [1x1 FFNNS]
                 plant: [1x1 DNonLinearODE]
           feedbackMap: 0 % **unused
                     nO: 2 % number of outputs
                    nI: 2 % number of inputs
                nI_ref: 0 % number of reference inputs
                 nI_fb: 2 % number of feedback outputs
                 ref_I: [] % reference input set
              init_set: [] % initial set of states of the plant
          reachSetTree: []
    totalNumOfReachSet: 0
             reachTime: 0
            controlSet: []
              simTrace: []
          controlTrace: []
```

IV.4 Specify a property of an NNCS

After constructing an NNCS, the users need to specify the property of the system that they want to verify. The property is a linear predicate over the states/outputs of the system, i.e., the states/outputs of the plant model which is defined in the form of $P \triangleq Gy \leq g$, where y is the output vector of the system. Let P be an unsafe region, if the reachable sets of the system reach the unsafe region, the system is unsafe, otherwise, it is safe. In NNV, we use a HalfSpace object to represent a property. An example of constructing a property for the car in section IV.3.2 is given as follows.

```
Code 44: Specify an NNCS property
/* An example of specifying an NNCS property */
t_{gap} = 1.4;
D_default = 10;
% safety specification:
            x_lead - x_ego > t_gap * v_ego + D_default
% unsafe region: x_lead - x_ego - t_gap * v_ego <= D_default</pre>
unsafe_mat = [1 \ 0 \ 0 \ -1 \ -t_gap \ 0];
unsafe_vec = [D_default];
U = HalfSpace(unsafe_mat, unsafe_vec); % unsafe property
Result
U =
  HalfSpace with properties:
      G: [1 0 0 -1 -1.4000 0] % unsafe matrix
      g: 10 % unsafe vector
    dim: 6 % dimension
```

IV.5 Choose a reachability method for an NNCS

For a continuous/discrete linear NNCS, NNV supports the "exact-star" and the "approx-star" reachability methods. The "exact-star" computes the exact reachable sets of the systems for a bounded time steps while the other computes an over-approximate reachable sets of the systems. For a continuous/discrete nonlinear NNCS, NNV supports the "approx-star" reachability method since we cannot compute the exact reachable set of a nonlinear plant model.

IV.6 Construct an initial set of states for an NNCS

The initial set of states of the plant of an NNCS needs to be a *star set*. The details about how to construct a star set is given in section III.5.1.

IV.7 Choose a number of cores for computation

For an NNCS, NNV computes the reachable sets of the controller, then these reachable sets are fed to the plant as input sets. The reachable sets of the plant are computed and then feed-backed to the controller. To reduce conservativeness in the reachable set computation, NNV always computes the exact reachable sets for the controller (assumed it has piecewise linear activation functions) even when users choose the "approx-star" method. Therefore, to speed up the computation, parallel computing are used in both reachability methods by setting the *number of cores* we want to use for the computation.

IV.8 Verify an NNCS

IV.8.1 Verify a continuous linear NNCS

Users can verify a continuous linear NNCS using the "verify" method in the *LinearNNCS* class. The verify method takes reachability parameters (reachPRM) and a (unsafe) property as inputs. The reachPRM is a struct containing 5 parameters including:

- 1. *init_set* is the initial set of states of the plant.
- 2. ref_input is the reference input to the controller (no reference input: $ref_input = []$).
- 3. *numSteps* is the number of steps we want to verify.
- 4. *reachMethod* is the reachability method used for verification.
- 5. *numCores* is the number of cores used for computation.

The *verify* method returns:

- 1. safe is the safety result which can be "SAFE", "UNSAFE" or "UNKNOWN".
- 2. counterExamples which may be an array of star set counterexamples or falsified input points.
- 3. *verifyTime* is the verification time.

In the following example, we verify safety of a continuous, linear neural network addaptive cruise control sytem. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_verify_linearNNCS.m.

Code 45: Verify a continuous linear NNCS

```
/* An example of verifying a continuous linear NNCS */
/* Controller
load controller_5_20.mat; weights = network.weights;
bias = network.bias; n = length(weights); Layers = [];
for i=1:n-1
    L = LayerS(weights{1, i}, bias{i, 1}, 'poslin');
    Layers = [Layers L];
end
L = LayerS(weights{1, n}, bias{n, 1}, 'purelin');
Layers = [Layers L];
Controller = FFNNS(Layers);
/* plant model
A = [0 \ 1 \ 0 \ 0 \ 0 \ 0; \ 0 \ 0 \ 1 \ 0 \ 0 \ 0; \ 0 \ 0 \ 0 \ 0 \ 0 \ 1; \dots]
    0 0 -2 0 0 0 0];
B = [0; 0; 0; 0; 0; 2; 0];
C = [1 \ 0 \ 0 \ -1 \ 0 \ 0 \ 0; \ 0 \ 1 \ 0 \ 0 \ -1 \ 0 \ 0; \ 0 \ 0 \ 0 \ 0 \ 1 \ 0 \ 0];
D = [0; 0; 0];
Tc = 0.1; % control period
Nr = 20; % number of reachability steps in 1 control period
plant = LinearODE(A, B, C, D, Tc, Nr); % continuous plant model
/* continuous linear NNCS
ncs = LinearNNCS(Controller, plant); % a continuous linear NNCS
```

Code 46: Verify a continuous linear NNCS(cont.) . . . /* ranges of initial set of states of the plant 1b = [90; 29; 0; 30; 30; 0; -10];ub = [92; 30; 0; 31; 30.5; 0; -10];/* reachability parameters reachPRM.init_set = Star(lb, ub); reachPRM.ref_input = [30; 1.4]; reachPRM.numSteps = 10; reachPRM.reachMethod = 'approx-star'; reachPRM.numCores = 4; /* usafe region: x1 - x4 <= 1.4 * v_ego + 10 unsafe_mat = [1 0 0 -1 -1.4 0 0]; unsafe_vec = 10; U = HalfSpace(unsafe_mat, unsafe_vec); /* verify the system [safe, counterExamples, verifyTime] = ncs.verify(reachPRM, U); Results safe = 'SAFE'; counterExamples = []; verifyTime = 3.6339;

IV.8.2 Verify a discrete linear NNCS

Users can verify a discrete linear NNCS using the "verify" method in the *DLinearNNCS* class. The verify method takes reachability parameters (reachPRM) and a (unsafe) property as inputs. The reachPRM is a struct containing 5 parameters including:

- 1. *init_set* is the initial set of states of the plant.
- 2. ref_input is the reference input to the controller (no reference input: $ref_input = [\]$).
- 3. *numSteps* is the number of steps we want to verify.
- 4. reachMethod is the reachability method used for verification.
- 5. *numCores* is the number of cores used for computation.

The *verify* method returns:

- 1. safe is the safety result which can be "SAFE", "UNSAFE" or "UNKNOWN".
- 2. counterExamples which may be an array of star set counterexamples or falsified input points.
- 3. *verifyTime* is the verification time.

In the following example, we verify safety of a discrete, linear neural network addaptive cruise control sytem. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_verify_dlinearNNCS.m.

Code 47: Verify a discrete linear NNCS

```
/* An example of verifying a discrete linear NNCS */
/* Controller
load controller_5_20.mat; weights = network.weights;
bias = network.bias; n = length(weights); Layers = [];
for i=1:n-1
    L = LayerS(weights{1, i}, bias{i, 1}, 'poslin');
    Layers = [Layers L];
end
L = LayerS(weights{1, n}, bias{n, 1}, 'purelin');
Layers = [Layers L];
Controller = FFNNS(Layers);
/* plant model
A = [0 \ 1 \ 0 \ 0 \ 0 \ 0; \ 0 \ 0 \ 1 \ 0 \ 0 \ 0; \ 0 \ 0 \ 0 \ 0 \ 0 \ 1; \dots]
    0 0 -2 0 0 0 0];
B = [0; 0; 0; 0; 0; 2; 0];
C = [1 \ 0 \ 0 \ -1 \ 0 \ 0 \ 0; \ 0 \ 1 \ 0 \ 0 \ -1 \ 0 \ 0; \ 0 \ 0 \ 0 \ 0 \ 1 \ 0 \ 0];
D = [0; 0; 0];
plant = LinearODE(A, B, C, D); % continuous plant model
plantd = plant.c2d(0.1); % discrete plant model
/* discrete linear NNCS
ncs = DLinearNNCS(Controller, plantd); % a discrete linear NNCS
```

Code 48: Verify a discrete linear NNCS (cont.) . . . /* ranges of initial set of states of the plant 1b = [90; 29; 0; 30; 30; 0; -10];ub = [92; 30; 0; 31; 30.5; 0; -10];/* reachability parameters reachPRM.init_set = Star(lb, ub); reachPRM.ref_input = [30; 1.4]; reachPRM.numSteps = 10; reachPRM.reachMethod = 'approx-star'; reachPRM.numCores = 4; /* usafe region: x1 - x4 <= 1.4 * v_ego + 10 unsafe_mat = [1 0 0 -1 -1.4 0 0]; unsafe_vec = 10; U = HalfSpace(unsafe_mat, unsafe_vec); /* verify the system [safe, counterExamples, verifyTime] = ncs.verify(reachPRM, U); Results safe = 'SAFE'; counterExamples = []; verifyTime = 1.8996;

IV.8.3 Verify a continuous nonlinear NNCS

Users can verify a continuous nonlinear NNCS using the "verify" method in the NonLinearNNCS class. The verify method takes reachability parameters (reachPRM) and a (unsafe) property as inputs. The reachPRM is a struct containing 5 parameters including:

- 1. *init_set* is the initial set of states of the plant.
- 2. ref_input is the reference input to the controller (no reference input: $ref_input = [\]$).
- 3. *numSteps* is the number of steps we want to verify.
- 4. *reachMethod* is the reachability method used for verification. Always need to be "approx-star".
- 5. *numCores* is the number of cores used for computation.

The verify method returns:

- 1. safe is the safety result which can be "SAFE", "UNSAFE" or "UNKNOWN".
- 2. counterExamples which may be an array of star set counterexamples or falsified input points.
- 3. *verifyTime* is the verification time.

In the following example, we verify safety of a continuous, nonlinear neural network adaptive cruise control sytem. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_verify_nonlinearNNCS.m.

Code 49: Verify a continuous nonlinear NNCS

```
/* An example of verifying a continuous nonlinear NNCS */
/* FFNN controller
load controller_5_20.mat;
weights = network.weights;
bias = network.bias;
n = length(weights);
Layers = [];
for i=1:n-1
    L = LayerS(weights{1, i}, bias{i, 1}, 'poslin');
    Layers = [Layers L];
end
L = LayerS(weights{1, n}, bias{n, 1}, 'purelin');
Layers = [Layers L];
controller = FFNNS(Layers);
/* car model
Tr = 0.01; % reachability time step for the plant
Tc = 0.1; % control period of the plant
% output matrix
C = [0 \ 0 \ 0 \ 0 \ 1 \ 0; 1 \ 0 \ 0 \ -1 \ 0 \ 0; 0 \ 1 \ 0 \ 0 \ -1 \ 0]; % output matrix
car = NonLinearODE(6, 1, @car_dynamics, Tr, Tc, C);
/* system
ncs = NonlinearNNCS(controller, car);
```

Code 50: Verify a continuous nonlinear NNCS (cont.) . . . /* ranges of initial set of states of the plant lb = [90; 29; 0; 30; 30; 0]; ub = [92; 30; 0; 31; 30.5; 0];/* reachability parameters reachPRM.init_set = Star(lb, ub); reachPRM.ref_input = [30; 1.4]; reachPRM.numSteps = 50; reachPRM.reachMethod = 'approx-star'; reachPRM.numCores = 4; /* usafe region: x1 - x4 <= 1.4 * v_ego + 10 unsafe_mat = [1 0 0 -1 -1.4 0]; unsafe_vec = 10; U = HalfSpace(unsafe_mat, unsafe_vec); /* verify the system [safe, counterExamples, verifyTime] = ncs.verify(reachPRM, U); Results safe = "UNSAFE"; counterExamples = 1000 counterExamples are found

verifyTime = 88.96

IV.8.4 Verify a discrete nonlinear NNCS

Users can verify a discrete nonlinear NNCS using the "verify" method in the *DNonLinearNNCS* class. The verify method takes reachability parameters (reachPRM) and a (unsafe) property as inputs. The reachPRM is a struct containing 5 parameters including:

- 1. *init_set* is the initial set of states of the plant.
- 2. ref_input is the reference input to the controller (no reference input: $ref_input = [\]$).
- 3. *numSteps* is the number of steps we want to verify.
- 4. *reachMethod* is the reachability method used for verification. Always need to be "approx-star".
- 5. *numCores* is the number of cores used for computation.

The verify method returns:

- 1. safe is the safety result which can be "SAFE", "UNSAFE" or "UNKNOWN".
- 2. counterExamples which may be an array of star set counterexamples or falsified input points.
- 3. *verifyTime* is the verification time.

In the following example, we verify safety of a discrete, nonlinear neural network mountain car sytem. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_verify_dnonlinearNNCS.m.

Code 51: Verify a discrete nonlinear NNCS

```
/* An example of constructing a discrete nonlinear NNCS */
/* FFNN controller
load MountainCar_ReluController.mat;
W = nnetwork.W; % weight matrices
b = nnetwork.b; % bias vectors
n = length(W);
Layers = [];
for i=1:n-1
    L = LayerS(W{1, i}, b{1, i}, 'poslin');
   Layers = [Layers L];
end
L = LayerS(W{1, n}, b{1, n}, 'purelin');
Layers = [Layers L];
controller = FFNNS(Layers);
/* MountainCar
Ts = 0.5; % sampling time
C = [1 0; 0 1]; % output matrix
Car = DNonLinearODE(2, 1, @discrete_car_dynamics, Ts, C);
ncs = DNonlinearNNCS(controller, Car); % system
```

Code 52: Verify a discrete nonlinear NNCS (cont.) b = [-0.41; 0];ub = [0.4; 0];reachPRM.init_set = Star(lb, ub); reachPRM.ref_input = []; reachPRM.numSteps = 10; reachPRM.reachMethod = 'approx-star'; reachPRM.numCores = 4; % unsafe region U = HalfSpace([-1 0], 0); % x1 > 0[safe, counterExamples, verifyTime] = ncs.verify(reachPRM, U); Results safe = "UNSAFE"; counterExamples = 485 counterExamples are found verifyTime = 4.2645

IV.9 Visualize results

For linear NNCS, user can visualize the reachable sets of the system using the "plotOutputReach-Sets" method in the LinearNNCS or DLinearNNCS class. This method plots the reachable set of the system in a specific direction defined by the mapping matrix G and the offset vector g. Mathematically, if the state vector of the system is x, the method plots $y = G \times x + g$. The users can also specify the color of the reachable sets they want to plot.

In the following example, we plot the reachable sets of the continuous linear neural network

addaptive cruise control systems in the example of section IV.8.1. The code for this example is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_visualize_linearNNCS.m.

```
Code 53: Visualizing reachable sets of linear NNCS
/* verify the system
[safe, counterExamples, verifyTime] = ncs.verify(reachPRM, U);
/* Plot output reach sets: actual distance vs. safe distance
% plot reachable set of the distance between two cars
figure;
map_mat = [1 0 0 -1 0 0 0];
map_vec = [];
ncs.plotOutputReachSets('blue', map_mat, map_vec);
hold on;
% plot safe distance between two cars:
% d_safe = D_default + t_gap * v_ego;
% D_default = 10; t_gap = 1.4, d_safe = 10 + 1.4 * x5;
map_mat = [0 0 0 0 1.4 0 0];
map\_vec = [10];
ncs.plotOutputReachSets('red', map_mat, map_vec);
title('Actual Distance versus. Safe Distance');
/* plot 2d output sets
figure;
map_mat = [1 0 0 -1 0 0 0; 0 0 0 0 1 0 0]; map_vec = [];
ncs.plotOutputReachSets('blue', map_mat, map_vec);
title('Actual Distance versus. Ego car speed');
```

Figures IV.2 and IV.3 illustrate the reachable sets of the system. One can observe that the actual distance > the safe distance, thus, the system is safe (in 10 control periods).




Figure IV.2: Reachable set of actual distance vs. the safe distance over time.

Similarly for the discrete linear neural network adaptive cruise control system verified in section IV.8.2, we can plot Figures IV.4 and IV.5 using the script that is available at https://github.com/verivital/nnv/code/example/Manual/example_nncs_visualize_dlinearNNCS.m.




Figure IV.3: Reachable set of actual distance and the velocity of the ego car.




Figure IV.4: Reachable set of actual distance vs. the safe distance over time.




Figure IV.5: Reachable set of actual distance and the velocity of the ego car.

BIBLIOGRAPHY

- Althoff, M. (2015). An introduction to cora 2015. In *Proc. of the Workshop on Applied Verification for Continuous and Hybrid Systems*.
- Bak, S., Bogomolov, S., and Johnson, T. T. (2015). Hyst: a source transformation and translation tool for hybrid automaton models. In *Proceedings of the 18th International Conference on Hybrid Systems: Computation and Control*, pages 128–133. ACM.
- Kvasnica, M., Grieder, P., Baotić, M., and Morari, M. (2004). Multi-parametric toolbox (mpt). In *International Workshop on Hybrid Systems: Computation and Control*, pages 448–462. Springer.