Let ϕ be the field

$$\phi(x, y, z, t) = p_x x + p_y y + p_z z - Et$$

where

$$E = \sqrt{p_x^2 c^2 + p_y^2 c^2 + p_z^2 c^2 + m^2 c^4}$$

The following solutions to the Dirac equation are used to model fermions.

$$\psi_{1} = \begin{pmatrix} E/c + mc \\ 0 \\ p_{z} \\ p_{x} + ip_{y} \end{pmatrix} \exp\left(\frac{i\phi}{\hbar}\right) \quad \psi_{2} = \begin{pmatrix} 0 \\ E/c + mc \\ p_{x} - ip_{y} \\ -p_{z} \end{pmatrix} \exp\left(\frac{i\phi}{\hbar}\right)$$
fermion spin up
fermion spin down

$$\psi_7 = \begin{pmatrix} p_z \\ p_x + ip_y \\ E/c + mc \\ 0 \end{pmatrix} \exp\left(-\frac{i\phi}{\hbar}\right) \quad \psi_8 = \begin{pmatrix} p_x - ip_y \\ -p_z \\ 0 \\ E/c + mc \end{pmatrix} \exp\left(-\frac{i\phi}{\hbar}\right)$$
anti-fermion spin up
$$\begin{pmatrix} E/c + mc \\ 0 \\ E/c + mc \end{pmatrix}$$
anti-fermion spin down

A spinor is the vector part of ψ . The following spinors are used for scattering calculations. Symbol u indicates a fermion and symbol v indicates an anti-fermion.

$$u_1 = \begin{pmatrix} E/c + mc \\ 0 \\ p_z \\ p_x + ip_y \end{pmatrix} \quad u_2 = \begin{pmatrix} 0 \\ E/c + mc \\ p_x - ip_y \\ -p_z \end{pmatrix} \quad v_1 = \begin{pmatrix} p_z \\ p_x + ip_y \\ E/c + mc \\ 0 \end{pmatrix} \quad v_2 = \begin{pmatrix} p_x - ip_y \\ -p_z \\ 0 \\ E/c + mc \end{pmatrix}$$
 fermion spin up fermion spin down anti-fermion spin up anti-fermion spin down

This is the corresponding space-time momentum vector.

$$p = \begin{pmatrix} E/c \\ p_x \\ p_y \\ p_z \end{pmatrix}$$

Spinors are solutions to the following momentum-space equations with $p = p \cdot (\gamma^0, \gamma^1, \gamma^2, \gamma^3)$.

$$pu = mcu$$
 $pv = -mcv$

Up and down spinors have the following "completeness property."

$$u_1\bar{u}_1 + u_2\bar{u}_2 = (E/c + mc)(\not p + mc)$$
 $v_1\bar{v}_1 + v_2\bar{v}_2 = (E/c + mc)(\not p - mc)$

The spinor adjoints are $\bar{u} = u^{\dagger} \gamma^0$ and $\bar{v} = v^{\dagger} \gamma^0$. The adjoint is a row vector hence $u\bar{u}$ and $v\bar{v}$ are outer products.