

EM: Natural Sources




Outline


- Background on natural source EM methods
- Magnetotellurics
- MT case history
- Z-axis tipper electromagnetics
- ZTEM case history

Motivation


Volcanoes




Base of salt




Geothermal




Tectonic settings of top few km



Mineral targets





Groundwater



Common challenge: getting enough energy into the ground


What is required to see deeper?

- Penetration depth depends upon system power
- Controlled source:
 - Using a small loop
 - Magnetic moment = $I * Area$
 - Total geometric decay = $\frac{1}{r^6}$
- Infinitely large loop source
 - Sheet currents generate plane waves



Natural EM sources


Sun and magnetosphere, solar storms



Lightning





Auroral electrojet; aurora



Earth as a waveguide

- EM waves bounce between earth surface and highly conductive ionosphere
- And travel as plane waves



- Dead band: difficult to collect frequencies in notch (~1 Hz)

Refraction of waves

- Snell's law

$$k_i \sin \theta_i = k_t \sin \theta_t$$

- k is complex wave number

$$k^2 = \omega^2 \mu \epsilon - i \omega \mu \sigma$$

- Quasi-static: $\frac{\omega \epsilon_0}{\sigma} \ll 1$

$$\sin \theta_t = \sqrt{2\omega\epsilon_0/\sigma} \sin \theta_i$$



- Angle of refraction is $\theta_t = 0^\circ$ in almost every instance

- Example for 10,000 Hz

- $\sigma = 10^{-3}$ S/m

- $\theta_i = 89^\circ$

- Then $\theta_R = 1.35^\circ$




Plane waves and skin depth

- Skin depth (meters)

$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = 503\sqrt{\frac{1}{\sigma f}}$$



- Low frequency waves propagate further

- Depth of propagation
 - A few skin depths
 - Only a portion of a wavelength



Control source vs Natural source

- Controlled source
 - Well-defined location, geometry, and amplitude
- Natural sources
 - Sources are random in space and time



MT Station

- Maxwell's equations:
 - Equations are linear in J_s
 - Both E and H are affected in the same way

$$\nabla \times \mathbf{E} + i\omega\mu\mathbf{H} = 0$$


$$\nabla \times \mathbf{H} - \sigma\mathbf{H} = \mathbf{J}_s$$

- Effects of unknown source removed by taking ratio
- Transfer function: relationship between fields.

$$\mathbf{E} = \mathbf{Z}\mathbf{H}$$

- \mathbf{Z} is the impedance (matrix)


$$\begin{pmatrix} E_x \\ E_y \end{pmatrix} = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix} \begin{pmatrix} H_x \\ H_y \end{pmatrix}$$





Impedance and resistivity

- Plane wave in homogenous media:
 - E and H fields are perpendicular

TE mode



TM mode



Homogeneous half space

Impedance


$$Z_{xy} = \frac{E_x}{H_y}$$

Resistivity

$$\rho = \frac{1}{\omega \mu} |Z_{xy}|^2$$

Phase

$$\Phi = \tan^{-1} \left(\frac{\text{Im}(Z_{xy})}{\text{Re}(Z_{xy})} \right) = -\frac{\pi}{4}$$



MT soundings in 1D

- In general:

$$Z = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix}$$

- Apparent resistivity:

$$\rho_a = \frac{1}{\omega \mu_0} |Z_{xy}|^2$$

- Phase:




$$\Phi = \tan^{-1} \left(\frac{\text{Im}(Z_{xy})}{\text{Re}(Z_{xy})} \right)$$

- In 1D:

$$Z = \begin{pmatrix} 0 & Z_{xy} \\ Z_{yx} & 0 \end{pmatrix}$$



$$Z_{xy} = \frac{E_x}{H_y}$$

$$Z_{xy} = -Z_{yx}$$



1D MT app

- Forward model MT data for layered Earth (1 to 3 layers)
- Choose physical properties for each layer
- Observe skin depth, apparent resistivity, phase



MT soundings in 2D

- In general:

$$Z = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix}$$


- In 2D:

$$Z = \begin{pmatrix} 0 & Z_{xy} \\ Z_{yx} & 0 \end{pmatrix}$$

$$Z_{xy} \neq Z_{yx}$$

- TE mode
 - E-field parallel to structure

$$Z_{yx} = \frac{E_y}{H_x}$$



MT soundings in 2D

- In general:

$$Z = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix}$$





- In 2D:

$$Z = \begin{pmatrix} 0 & Z_{xy} \\ Z_{yx} & 0 \end{pmatrix}$$

$$Z_{xy} \neq Z_{yx}$$

- TM mode
 - H-field parallel to structure
 - E_x discontinuous

$$Z_{xy} = \frac{E_x}{H_y}$$



MT soundings in 3D


- In general:

$$Z = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix}$$

- In 3D:


$$Z = \begin{pmatrix} Z_{xx} & Z_{xy} \\ Z_{yx} & Z_{yy} \end{pmatrix}$$

- No symmetry or special conditions




Measuring MT data

- Basic acquisition




- At each station, measure:
 E_x, E_y, B_x, B_y, B_z
- At remote reference, measure:
 B_x, B_y



Processing MT data

- Divide time series into time windows



- Apply Fourier transform
 - For each station:
 - For the remote reference:

$$\begin{aligned} e_x(t) &\rightarrow E_x(\omega) \\ h_y(t) &\rightarrow H_y(\omega) \end{aligned}$$

$$h_y^R(t) \rightarrow H_y^R(\omega)$$


- Form the impedance tensor:

$$Z_{xy}(\omega) = \frac{\langle E_x(\omega) H_y^{R*}(\omega) \rangle}{\langle H_y(\omega) H_y^{R*}(\omega) \rangle}$$

(*) complex conjugate
<> average over multiple samples

Inverting MT data

- Important: boundary conditions for modelling
- Mesh size:
 - MT: extended grid
 - L : a few skin depths from data area
- Challenge: Unknown boundary conditions
 - Possible channeled currents
 - Data can be affected by distant structures
- Otherwise, inversion of MT is essentially same as CSEM data



Outline

- Background on natural source EM methods
- Magnetotellurics
- Questions?
- MT case histories
- Z-axis tipper electromagnetics
- ZTEM case histories


MT case history

- Iceland





Hengill geothermal region: setup

- Iceland: geothermal hot spot
 - On the mid-Atlantic ridge
 - Hosts multiple high temperature geothermal systems
- Hengill geothermal area
 - Supplies majority of hot water in Reykjavik
 - Contributes ~450 Mwe to National power grid





Physical properties


- Relationships between alteration, resistivity, temperature, and conduction processes



Survey





- MT instrumentation
 - Phoenix MTU5's
- Survey
 - 133 stations used
 - Combination of 2E and 2E+3H setup
 - Frequencies: 300 – 0.001 Hz
- Remote reference
 - About 40 km away
- Raw data processing using Phoenix's SSMT2000 software









Data


Location 1



Location 3



Surface alteration,
hot water, fumaroles





Frequency (Hz)





Frequency (Hz)

3D inversion


- Off-diagonal impedance (Z_{xy} and Z_{yx}) used
- Combined multi-frequency inversion (300 Hz – 0.001 Hz)



Interpretation



Synthesis



- Conductive layer corresponds with formation temperature
 - Two main production fields: Hengill and Nesjavellir
 - Deep conductive heat source

Summary

- Background on natural source EM methods
- Magnetotellurics
- MT case history
- Z-axis tipper electromagnetics
- ZTEM case history

Tipper data (ZTEM)


- Transfer functions = relationship between two different fields.
- For MT relationship

$$E = ZH$$

- Relationships between magnetic fields

$$H_z = TH$$

- ZTEM: Z-axis tipper EM



ZTEM data

- H_z recorded over survey area
- H_x and H_y at a ground reference station
- Frequencies: 30-720 Hz
- Complex transfer functions


$$H_z(r) = T_{zx}H_x(r_0) + T_{zy}H_y(r_0)$$




$H_z(r)$




$H_x(r_0), H_y(r_0)$






Synthetic example


T_{zx}



Real




Imag




Conductor


T_{zy}



Real




Imag




ZTEM: some comments

- Can explore the “difficult to see” depth range 200-1000m
- Fast and economical
- Good geologic mapper
- Can be basis for follow-up ground survey




ZTEM case histories

- **Noranda district**
- Elevenmile Canyon geothermal area
- Balboa copper porphyry deposit



Noranda district, Canada


- Hosts many deposits:
 - 20 economic volcanogenic massive sulphide deposits (VMS)
 - 19 orogenic gold deposits
 - Several intrusion-hosted Cu-Mo deposits
- Physical properties
 - Synthetic example from geologic model
 - 38 geologic units converted into expected conductivities




Data

- Forward model data at 6 frequencies
 - 30, 45, 90, 180, 360, and 720 Hz

True model at 275m depth




Observed (90 Hz)



- Need to invert


Interpretation




- Geologic units are well mapped
- Some mineralized bodies are located

Synthesis

- Recovered model represents the regional geology




- Mineralized zones are recovered




Summary

- Background on natural source EM methods
- Magnetotellurics
- MT case history
- Z-axis tipper electromagnetics
- ZTEM case history



End of Natural Sources

- Introduction to EM
- DCR
- EM Fundamentals
- Inductive sources
 - Lunch: Play with apps



Next up →

- GPR
- Induced polarization
- The Future