



ElementOne

OpenAPI User's Guide

Version 1.31.2

July 2026

Contents

Chapter 1. Copyright.....	3
Chapter 2. Introduction.....	4
Chapter 3. Authentication.....	5
Creating an API bearer token.....	5
Authenticate using an API bearer token.....	7
Chapter 4. Getting Started.....	8
Chapter 5. Paging.....	9
Page Size.....	9
Example: Paging across multiple requests.....	9
Chapter 6. Error.....	14
Chapter 7. Contact Us.....	15

Chapter 1. Copyright

TXOne Networks Incorporated reserves the right to make changes to this document and to the product described herein without notice. Before installing and using the product, review the readme files, release notes, and/or the latest version of the applicable documentation, which are available at <https://help.txone.com/> and <https://my.txone.com/>.

TXOne Networks, TXOne Portable Inspector, TXOne Virtual Portable Inspector, TXOne ElementOne, and TXOne Safe Port are registered trademarks of TXOne Networks Incorporated. All other product names may be trademarks or registered trademarks of their owners.

Copyright ©2026 TXOne Networks Incorporated. All rights reserved. No part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted without the express prior written consent of TXOne Networks Incorporated.

Chapter 2. Introduction

The ElementOne OpenAPI is a developer-friendly REST API for interacting with the ElementOne platform. It is used to support automated data collection, reduce manual export tasks, and integrate scan data into your organization's internal platforms, enabling more efficient monitoring and centralized reporting.

The ElementOne OpenAPI is a Representational State Transfer (REST) API consisting of HTTP endpoints. The endpoints use Bearer Token authentication and are designed in a common pattern, primarily using JSON for both requests and responses.

Chapter 3. Authentication


To authenticate with the API, you must include an API token, commonly referred to as a **bearer token** in each API request. A bearer token is a string that grants access to a protected resource on behalf of the token's owner.

Include the token in the Authorization header using the **Bearer** authentication scheme, as shown below:

```
Authorization: Bearer <your token>
```

Creating an API bearer token

1. Log in to **ElementOne**.
2. Select **Administration > API Management**.
3. Click the **Create API key** button to create an API key.




4. In the **Create API Client** window, enter an API key name and a description, then click on **Generate**.




Note:

An API key name is required; a description is optional.



A dark-themed dialog box titled "Create API Client". It contains two input fields: "Name*" and "Description". At the bottom right, there are two buttons: "Generate" (yellow) and "Cancel" (gray).

5. After an API key is created successfully, on the **Copy your API Key** page, click on the **Copy** icon to copy the API key, save the API key in a secure location, then click **OK**.



A dark-themed dialog box titled "Copy Your API Key". It features a green checkmark icon and the text "API Client generated successfully. Click the Copy button, then save the generated API key in a secure location. You won't be able to view it again after closing this window." Below this, there is a table with the following data:


Name	test 1
Description	test 1
API Key	v1_d3fadac0f23e4454579133096cca58a6605e7a6ca ba2b37fbdfa536ff31572a7_3549781019

To the right of the API Key text is a copy icon (two overlapping sheets of paper) enclosed in a red square. At the bottom right, there is an "OK" button, also enclosed in a red rectangle.

**Note:**

Make sure to copy and save the generated API key in a secure location, you won't be able to view it again after closing the window.

You will see an error message if you skip clicking on the **Copy** icon to copy the API key.



6. See the generated API key on the **API management** page.

Authenticate using an API bearer token

To include a token in an API call, pass it in the **Authorization** header using the **Bearer** authentication scheme. For example:

```
curl -H "Content-Type=application/json" -H "Authorization: Bearer <your token>"https://<hostname>/openapi/sp/v1/logs/malware-scan"
```

Chapter 4. Getting Started

To make API calls, follow the steps below to proceed.

1. Find your host name

The hostname appears in all URLs when accessing ElementOne. You can find it by checking the URL in your browser's address bar while logged into the ElementOne platform. It looks like this:

```
https://<hostname>/
```

2. Get an authentication token

Follow the steps in **Chapter 2 Authentication (on page 5)** to get an authentication token.

3. Make a request

After getting your hostname and authentication token, you can use an API client to interact with the ElementOne API. All requests must use HTTPS and include the specific hostname.

For the supported APIs and their corresponding data schemas, please refer to the ***ElementOne OpenAPI Reference*** available on MyTXOne Portal.

Chapter 5. Paging

All endpoints that return multiple objects are paginated. This means you may need to make multiple requests to get all the objects you're interested in.

Responses from paginated endpoints include a `next_page_token` field. To access the next page, repeat the request and include a page token query parameter with the value from the `next_page_token` field.

If the response does not include a `next_page_token`, it indicates that you are on the last page.



Note:

The page token may or may not change between pages. Always use the `next_page_token` from the most recent response.

Page Size

By default, each API request returns **50 results per page** if the `page_size` query parameter is not specified.

You can control the number of results per page by setting the `page_size` parameter in your request. The valid range is **1 to 1000**. If you request a value greater than 1000, the page size will automatically be reduced to the maximum of 1000.

When there are more results available, the response includes a `next_page_token` field, which can be used to request the next page. If no further data is available, the `next_page_token` field will be **empty**.

As long as more data exists, each page will contain at least one result.

Example: Paging across multiple requests

The code snippets below demonstrate how to page through multiple results using the `page_size` and `page_token` parameters. The presence of the `next_page_token` field in the response indicates that more data is available. If no further data is available, the `next_page_token` field will be empty.

First Request

```
curl --location 'https://elementone.com/openapi/sp/v1/logs/media-check?page_size=1' \
--header 'Authorization: Bearer v1_d46019d09172d6af8f14867d7dd5ac0b21b43ea6f75a323ea91c1ba66e4cc838_3041876837' \
--header 'Content-Type: application/json' \
--data '{}'
```

Response

```
{
  "status": 0,
  "message": "Success",
  "data": {
    "logs": [
      {
        "media_check_id": "640f4484-a0ca-45aa-8ee2-e8a6b4f78af7",
        "visitor_mode": 1,
        "visitor": "0005726829",
        "start_time": "2025-04-11T07:38:08Z",
        "received_time": "2025-04-11T07:39:19Z",
        "media_status": 1,
        "storage_media_type": 1,
        "removable_media_sn": "USB\\VID_0781&PID_5588\\MSFT3012B45678C637",
        "removable_media_name": "SanDisk 3.2 Gen 1 SCSI Disk Device",
        "dev_id": "ES101-03560274-043C-05BA-0906-640700080009",
        "dev_name": "101 - Wifi - Safe Port",
        "storage_space_infos": [
          {
            "storage_media_type": 1,
            "size": 250123124736,
            "storage_space_infos": [
              {
                "storage_space_type": 1,
                "size": 10737418240,
                "start_address": 1048576,
                "drive_letter": "E",
                "volume_name": "WINPE",
                "file_system": "FAT32"
              },
              {
                "storage_space_type": 1,
                "size": 239383609344,
                "start_address": 10738466816,
                "drive_letter": "F",
                "volume_name": "Other",

```

```

        "file_system": "NTFS"
      }
    ]
  }
],
  "unallocated_space_size": 0
}
],
  "next_page_token": "v1_eyJpZCI6MSwicmVjZWl2ZV90aW1lIjoxNzQ0MzU3MTU5fQ=="
}
}

```

Second Request (Using `next_page_token`)

```

curl --location

'https://elementone.com/openapi/sp/v1/logs/media-check?page_size=1&page_token=v1_eyJpZCI6MSwicmVjZWl2ZV90aW1lIjoxNzQ0MzU3MTU5fQ%3D%3D' \

--header 'Authorization: Bearer v1_d46019d09172d6af8f14867d7dd5ac0b21b43ea6f75a323ea91c1ba66e4cc838_3041876837' \

--header 'Content-Type: application/json' \

--data '{}'
```

Response

```

{
  "status": 0,
  "message": "Success",
  "data": {
    "logs": [
      {
        "media_check_id": "05838972-6253-4927-bb6f-49ca51a7b51d",
        "visitor_mode": 1,
        "visitor": "0005726829",
        "start_time": "2025-04-11T07:39:46Z",
        "received_time": "2025-04-11T07:40:44Z",
        "media_status": 1,
        "storage_media_type": 1,
        "removable_media_sn": "USB\\VID_0781&PID_5588\\MSFT3012B45678C637",
        "removable_media_name": "SanDisk 3.2 Gen 1 SCSI Disk Device",
        "dev_id": "ES101-03560274-043C-05BA-0906-640700080009",

```

```

    "dev_name": "101 - Wifi - Safe Port",
    "storage_space_infos": [
      {
        "storage_media_type": 1,
        "size": 250123124736,
        "storage_space_infos": [
          {
            "storage_space_type": 1,
            "size": 10737418240,
            "start_address": 1048576,
            "drive_letter": "E",
            "volume_name": "WINPE",
            "file_system": "FAT32"
          },
          {
            "storage_space_type": 1,
            "size": 239383609344,
            "start_address": 10738466816,
            "drive_letter": "F",
            "volume_name": "Other",
            "file_system": "NTFS"
          }
        ]
      }
    ],
    "unallocated_space_size": 0
  }
],
  "next_page_token": "v1_eyJpZCI6MiwicmVjZWl2ZV90aw1lIjoxNzQ0MzU3MjQ0fQ=="
}

```

Final Page (No Further Results)

```

{
  "status": 0,
  "message": "Success",
  "data": {

```

```
"logs": [],  
  "next_page_token": ""  
}  
}
```

Chapter 6. Error

When making API requests, you may encounter errors. The following table shows the status codes, their meanings, and example scenarios that may trigger them.

Status Code	Description	Example Scenario
400	Bad Request. Request validation failed.	1. Example 1: Page size is set to 0 which is out of the valid range 1-1000. 2. Example 2: A required numeric field is given as a string.
401	Unauthorized. Authentication failed.	The authentication token is missing or incorrect.
500	Internal Server Error. Service failure.	The service encountered an unexpected condition. Try again or contact customer support.
503	Service Unavailable. Temporary issue.	Too many requests were sent in a short period. Wait and try again later.

Chapter 7. Contact Us

For support and additional information, visit the following websites:

- Worldwide support offices: <https://www.txone.com/contact/>
- TXOne Networks product documentation: <https://help.txone.com/docs>
- MyTXOne: <https://my.txone.com>