Modula-2 System for Z80 CP/M

bу

Hochstrasser Computing AG Leonhardshalde 21 CH-8001 Zuerich Switzerland

Manual Release 3-28-85/pwh

TABLE OF CONTENTS

1.	About	This Manual ourconscoursessessessessessessessesses	ST-1
	1.1.	Audience	ST-1
	1.2.	Marking and Typography	ST-1
	1.3.	Organization	ST-2
2.	System	в Description собысовання в проставляющий в придавания в пример в придавания в примента в примента в примента в	ST-5
	2.1.	System Requirements and accommon accomm	ST-5
	2,2,	System Features	ST-5
3.	Licens	ing, Updates, Liabilities and Support	ST-6
4.	Gettin	ရှိ သိန်ဆိုင်းလိုက်ပြီး လင္လေလသည်သည်။ သည်သော မေရာက္သော မေရာက္သည် မေရာက်သည်။ သိန်ဆိုင်းလိုက်ပြီး လင်လေလသည်။ မေရာက်သော မေရ	ST-7
	4.1.	Distribution Disks	ST-7
	4.2.	Making a Backup Copy	ST-9
	4.3.	System Configuration	ST-10
	4,4,	A Sample Compile and Run Session	ST-12

STARTUP GUIDE

Chapter 6. About This Manual

Section 1. Audience

This manual describes the Modula-2 implementation of Hochstrasser Computing AG for CP/M systems using a Z80 processor. It is neither a reference manual nor a course about programming in Modula-2.

From the user's part, basic CP/M familiarity is assumed. Should you be a newcomer to programming, it is indispensable for you to buy and thoroughly study a text book about Modula-2; also, the lecture of books dealing with programming in general is recommended. For Modula-2 text books, please consult the bibliography that is contained in this manual.

When learning Modula-2, familiarity with Pascal is useful, although not necessary. The error messages of the Modula-2 Compiler are in most cases more to the point than the ones a Pascal Compiler generates, thus, it can be even simpler to learn Modula-2 than it is to learn Pascal.

Section 2. Marking and Typography

Throughout the manual, several types of enhancements are used to mark some specific sections.

Enhancement Type		Meaning
boldfaced text	1075 2174	critical actions new notions document references
underscored text	South	user input in hands-on examples.
bold, underscored text	***	most important sections in boldfaced text.

Startup Guide About This Manual Page ST-2

To highlight important rules, they are set between horizontal lines.

Apart from these conventions, two other kinds of marking are used:

NOTE - Indented paragraphs starting with the word NOTE are used to mark paragraphs containing material being of special importance to the current topic of the text.

WARNING - Indented paragraphs beginning with the word **WARNING** contain information about dangers and often made mistakes related to the current topic.

Another often used abbreviation is <CR>. This means that the RETURN, ENTER, or NEWLINE key of the terminal is hit to announce the end of an input line to either the operating system or one of the programs.

Section 3. Organization

The manual is divided into different parts, each of them describing one particular topic.

Each of these parts begins with an overview describing the material covered in it in catchwords.

When you're just starting to use the system, it is recommended to search a specific topic by browsing through these catchwords to find the desired topic.

As an example, the catchwords of all of the manual's main parts are presented here in tabular form.

The main parts are:

Part	Topics covered
Startup Guide	 Manual usage (you're in it right now) System description licensing, updates, liabilities distribution disk contents backup and installation procedures sample compile and run procedure
Introduction to Modula-2	- Modula-2 Description - Modula-2 for Pascal Programmers
Implementation Guide	 System Parts, Program description How to compile and link System Restrictions Standard Library description Utility Library description
Advanced Programming Guide	 Chaining between programs Using shared data and heap Assembler Interfacing How to achieve better efficiency
Appendices	 Relocatible Format Description Reserved Words Standard Identifiers ASCII Character Set (Hex/Dec/Oct) Bibliograpy Error Messages Index

It is recommended to read the Startup Guide from cover to cover first.

WARNING - DO NOT UNSEAL THE DISKS BEFORE HAVING READ THE SYSTEM REQUIREMENTS, SYSTEM FEATURES AND THE LICENSING SECTIONS.

You can return the system and get your money back only as long as the seal isn't broken.

Startup Guide About This Manual Page ST-4

If you have never programmed in Modula-2 before, it is suggested to buy a good text book on it. A bibliography can be found in the appendices. There may be new good books around; choose one that appeals to you. In all cases, read the Introduction to Modula-2 carefully. After readying the system for use, have a look at the sample programs and at the library module sources.

A must for everybody is the Implementation Guide. It contains detailed descriptions of the programs belonging to the System, as well as the included libraries.

The Advanced Programming Guide concentrates on more elaborate programming techniques that make the code generator produce more efficient code, as well as assembly language interfacing, operating system service usage, etc.

Chapter 7. System Description

Section 1. System Requirements

To be able to run the Modula-2 System on your computer, it has to have the following characteristics:

- Z80 or official instruction set compatible processor (i.e. NEC 780, NSC 800. Sorry, no 8080, 8085).
- At least a 52k CP/M system. We only tested it under CP/M 2.2, but there seems to be no obstacle against earlier or later versions. The larger your system, the larger the programs the compiler can translate.
- The compiler itself uses about 170k Bytes of disk space; though it is desirable to have at least 2 drives holding 300kBytes each to work comfortably with the system.

Section 2. System Features

The Modula-2 System for the Z80 generates fast, ROM-able, reentrant Z80 native code. Assembly language integration is supported, as well as assembly language compiler output. The System also sports an auto-search mechanism in the compiler as well as the linker.

However, some minor omissions are present in this package: There are no priorities and therefore no monitors set up by the compiler. This omission was made because of the Z80's "flexible" interrupt structure: There are nearby as many different interrupt schemes as Z80 based computer brands. Version Control is currently disabled.

Startup Guide Licensing, Updates, Liabilities and Support Page ST-6

Chapter S. Licensing, Updates, Liabilities and Support

The license agreement (see separate sheet) allows for single CPU usage of the Modula-2 System for Z80 CP/M as well as for marketing your own programs, given you give credit to us and the Modula-2 System.

If you fill in, sign and return the license agreement to us, you are eligible for discounted updates to later versions of our product, provided you respected the license agreement's terms.

We feel that this license agreement is quite fair and wish to thank Leor Zolman of BDS, Inc. for allowing us to merely copy this text from his product, the BDS C System.

Please note that the standard disclaimer applies to this software. This means that we can't take any liabilities that you can accomplish a specific task using this Modula-2 System. However, because all the programs of the system as well as some commercial applications are written using this system itself, it has been proven that it really is usable and working.

Because we are a small company and have no branch offices, we cannot offer a dedicated telephone support line to our customers from overseas. Naturally, you can contact us with letters and even phone calls. Please note the time difference between Europe and other continents in the latter case. Switzerland, in particular, is in the GMT + 1 zone.

We are eager to get any and all bugs you may encounter out of our products as fast as possible, and count on your help in this respect.

Chapter 9. Getting Started

This section gives an overview of the components of the Modula-2 System, explains how to adapt it to your computer and features a sample compilation. Therefore, please read this section carefully.

Section 1. Distribution Disks

The distribution diskettes contain your Modula-2 System.

WARNING - Do not use these disks as your work disks. Please make at least one backup prior to any work with the system. That's in your very best interest.

The following files can be found on the distribution disks:

Group	File	Contents
Compiler	MC.COM MCP2.COM MCP2A.COM MCP3.COM MCP3A.COM MCP4.COM MCP4MAC.COM MCL.COM	Syntax check Imports & Initialisation Declaration Analysis Body Analysis; Type Check Symbol File Generation Code Generation, MRL output ", Assembler output Lister
Linker	ML.COM MLP2.COM	Pass 1 Pass 2
Ref-Listor	MX.COM	Reference Lister

Group	File	Contents
Converter	MR _* COM	REL to MRL converter
Installation	MP.COM	System Configuration Program
Library	MODLIB.MRL	Runtime Library
Utilities	CMDLIN.* CONVERSI.* CONVERTR.* INOUT.* REALINOU.* MOVES.* OPSYS.* SEQIO.* FILESYS.* FILES.* TERMINAL.* TERM1.*	Command Line Scanner Conversions (numbers <-> strings) Conversions (REAL numbers <-> strings) Standard I/O Standard I/O for REALs fast moves operating system access Sequential File I/O Sequential File I/O Random File I/O CRT I/O (sample programs)
Test Programs	ACKER.MOD ERATOS.MOD QUEENS.MOD	Ackermann function Sieve of Erathostenes (BYTE) Eight Queens Problem

These files will be present in any case; there might be others as well.

Section 2. Making a Backup Copy

Your first step is now to make a copy of the distribution disks. This copy will serve as your Copy Master thereafter.

To generate a copy, follow these steps:

- prepare enough diskettes to hold the system. This means about 450 kBytes of diskette storage. Each of these diskettes should be formatted, SYSGENized and hold a copy of PIP, CP, or your favourite copy program. It is desirable to have also a text editor as WordStar, Mince, PolyVue or ED and SUBMIT on these disks.
- Copy all files from the distribution disks to your prepared disks.
 Use these as your copy masters from now on, i.e. all copies of the system to generate a new work disk will be taken from these disks.
- Perform a configuration. See the following section for this.
- make a SUBMIT-file, which permits you, to copy automatically all necessary files to make a work disk on a new disk. Such a file might look like:

PIP \$1:=MC*.*[v] <CR>
PIP \$1:=ML*.*[v] <CR>
PIP \$1:=MODLIB.MRL[v] <CR>
PIP \$1:=MX.COM[v] <CR>
PIP \$1:=TERMINAL.*[v] <CR>
PIP \$1:=SEQIO.*[v] <CR>
ERA \$1:TERMINAL.MOD <CR>
ERA \$1:SEQIO.MOD <CR>

Let's call this file "MODULA2.SUB". Now insert your master disk containing this file into drive A: and the work disk-to-be into drive B:. The correct usage of the SUBMIT file would be:

A>SUBMIT MODULA2 B <CR>

By executing these steps, you created your master diskettes. From these, you can create all of your work disks. The components that are necessary to create a working system are: The compiler (MC*.*), the linker (ML*.*), as well as the runtime library (MODLIB,MRL). If you want to create listings without a compilation but with

Startup Guide Getting Started Page ST-10

numbered lines and reference tables, you need also MX.COM. All other modules mentioned in the SUMBIT file can be replaced by modules developed by yourself.

WARNING - Hochstrasser Computing AG and its distributors do not provide replacements for intentionally or carelessly damaged distribution disks. Therefore, do **NO**T use the distribution disks as your master disks or even worse - as your work disks. Keep them "off premises" in a safe or some other secure place. Make copies of them only if necessary, i.e. if the other masters are unusable!

Section 3. System Configuration

The Modula-2 System features an Auto-Search-Mechanism. This allows the compiler to search for files which cannot be found on a particular drive, on other drives. The system distinguishes between two so called **search paths**: one for Data-Files (input files) and one for its own program parts. With the aid of MP.COM, these two paths can be installed into the system.

For the installation, the following files have to be present on your disk:

MP.COM - The installation program

MC.COM - The compiler base ML.COM - The linker base

Now invoke MP as follows:

Α>

NOTE - user input is -according to the typographic conventions- underlined.

A>MP <CR> MODULA-2 Patcher for Z80 CP/M Version 15-03-1985 Processing Compiler enter data search path (Default @AB): <DataPath> <CR> enter program search path (Default @AB): <ProgPath> <CR> Processing Linker enter data search path (Default @AB): <DataPath> <CR> enter program search path (Default @AB): <ProgPath> <CR> Installation Complete

DataPath indicates where the programs shall get their input files from.

ProgPath tells the programs where to search their parts. You can spread, for instance, the compiler's parts among seven drives, if you like to do so (the compiler consists of seven files). All of the programs make internal version controls, so any mismatching (old) versions are detected. Any operation is aborted immediately in this case.

<DataPath> as well as <ProgPath> both consist of one to six letters. These letters can be either "@" (the at-sign) or "A" up to and including "P". The at-sign denotes the so called default drive, the other letters correspond to the respective drives allowed under CP/M.

The default drive is the one whose letter is used in CP/M's prompt: If the prompt is A>, then the A: drive is the current default drive, if it is F>, then F: is the one. If you do not indicate where CP/M shall get a file or program from, it takes it from the default drive. This drive is often referred to as the currently logged drive.

NOTE - There is no way to direct the intermediate files of the compiler to another than the default drive.

Startup Guide Getting Started Page ST-12

On a standard dual disk drive system, assuming that your copy master disk is in drive A:, MP would receive the following answers:

Compiler DatSearch Path: @ Compiler Program Search Path: @AB

Linker Data Linker Program Search Path: @

Linker Program Search Path: @AB

This directs the programs to search their input on the default drive only, and their program parts first on the default drive and then on the A: drive, and finally on the B: drive.

If you have, say a North Star Advantage with only a 320 kBytes per disk capacity, it might be reasonable to place all of the program parts on the B: drive, including the runtime library, while your programs would be placed on drive A:. In this case, your answers change to:

Compiler Data Search Path: @BA Compiler Program Search Path: B@

Linker Data

Search Path: @BA

Linker Program Se

Search Path: B@

So, the linker will search for the runtime library first on the default drive (usually A:) and then on B:. The 'A' in the DataPath is included to allow compilations on B: that require files from A: to be successful.

NOTE - The installation program checks for multiple usage of the same drive and flags it as an error.

Section 4. A Sample Compile and Run Session

If you aren't that much curious to see "how it runs", you can skip this section and switch to the introduction to Modula-2.

On the distribution disks, you find some example programs, which are ready to compile. One of them is "ERATOS.MOD", a Sieve of Erathostenes benchmark. By following the steps explained below, you can do a sample compilation. Please do not forget to install the compiler before using it.

- On your work disk, there should be the following files:

ERATOS.MOD
TERM1.MSY
TERM1.MRL
TERM1.MRL
TERM1.MRL
TOTAL
TERM1.MRL
TERM1.MODLIB.MRL
THE relocatible file of Term1.
The Modula-2 runtime library.
The installed compiler.
The installed linker.

- Start the compilation as follows:

NOTE - The dates in the above example do not necessarily coincide with what you get from your distribution disks. Also, the number of dots output by the linker can change.

There were 1899 primes.

Startup Guide Getting Started Page ST-14

Further information about the programs, their operation and usage is covered by the Implementation Guide.