
Windows MySQL 搭建

版本 mysql community 8.0.17。

将 mysql-8.0.17-winx64.zip 解压到需要安装的目录下(我的是 D:\\MySQL), 并新建 mv.ini 文件,目录接口如下



打开 my.ini, 编辑内容如下:

注意:此处 basedir 和 datadir 的路径是解压后的安装路径,需将地址换成自己的路径。

[mysqld] basedir=D:\\MySQL\\mysql-8.0.17-winx64

datadir=D:\\MySQL\\mysql-8.0.17-winx64\\data

port=3306

以管理员身份启动 cmd,进入 MySQL 安装目录的 bin 目录

- 安装 MySQL 服务: 执行 mysqld –install 命令。(移除是 mysqld -remove) 如果出现 Service successfully installed.说明注册成功了。
- 初始化 MySQL:执行 mysqld --initialize --console 命令。 表示初始化 MySQL,生成 data 文件夹中的文件。如果没有报错,就表示初始化完成。 执行完后, 会输出 root 用户的初始默认密码(需要记住)。
- 3) 启动 MySQL 服务: net start mysql 命令启动服务器。 停止 MySQL 服务: net stop mysql。
- 登录:mysql –u root –p,然后按提示输入密码即可登录。
 - 提示我们输入密码, 这个密码是 MySQL 自动生成的初始密码, 在 data 文件夹中找 到以.err 结尾的文件打开,然后 Ctrl+F 搜索 password, 可以看到如下的搜索出来

的初始密码(前面没有记住密码时使用)。

```
D:\MySQL>cd mysql-8.0.17-winx64/bin
D:\MySQL\mysql-8.0.17-winx64\bin>mysqld -install
Service successfully installed.
D:\MySQL\mysql-8.0.17-winx64\bin>mysqld --initialize --console
2019-10-08T05:05:14.310814Z 0 [System] [MY-013169] [Server] D:\MySQL\mysql-8.0.1
7-winx64\bin\mysqld.exe (mysqld 8.0.17) initializing of server in progress as pr
ocess 36040
2019-10-08T05:05:43.476814Z 5 [Note] [MV-010454] [Server] A temporary password
s generated for root@localhos<mark>:</mark>: I9ywxfbajP.l
2019–10–08T05:05:58.849814Z 0 tsystem; tmy-bisi70] [Server] D:\MySQL\mysql-8.0.1
7-winx64\bin\mysqld.exe (mysqld 8.0.17) initializing of server has completed
D: MySQL\mysql-8.0.17-winx64\bin>net start mysql
MySQL 服务正在启动 ..
MySQL 服务已经启动成功。
D:\MySQL\mysql-8.0.17-winx64\bin>net start mysql
D:\MySQL\mysql-8.0.17-winx64\bin>mysql -u root -p
Enter password: *********
Welcome to the MySQL monitor. Commands end with ; or ackslash g .
```

看到上图,说明 MySQL 已经配置成功了。

5) 修改初始密码

mysql> ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY 'gisnci';

```
mysql> ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY 'g
isnci';
Query OK, 0 rows affected (0.04 sec)
```

设置好后退出重新登录验证密码。

然后要输入 flush privileges;刷新数据库, 否则会保留在缓存中。

6) 退出:\quit 或者\q。

注意重新修改密码加密规则,否则 Navicat 不能连上数据库。

端口 3306; 密码: gisnci;

- 4. 用户 root 登录开启远程访问权限
- 1) 登录 mysal 终端
- 2) 执行命令:

use mysql

select host, user from user;

如上图所示,发现 root 用户的访问权限是 localhost, 需要修改 host 为%。

3) 执行如下命令:

update user set host='%' where user='root'; flush privileges;

再次查询,结果如下:

Linux MySQL 搭建

安装过程适用于 centos7.2 (麒麟 3.10.0-327.eI7.x86 64), 以下操作在 root 权限下执行

- -rpm 版 mysql-8.0.17-1.el7.x86_64.rpm-bundle.tar
- 1. 下载安装包并解压缩

```
-rw-r--r-- 1 root root 663142400 Oct 12 19:11 mysql-8.0.17-1.el7.x86_64.rpm-bundle.tar
-rw-r--r-- 1 7155 31415 33978208 Jun 27 18:49 mysql-community-client-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 602852 Jun 27 18:49 mysql-community-common-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 5794588 Jun 27 18:49 mysql-community-devel-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 24493280 Jun 27 18:49 mysql-community-embedded-compat-8.0.17-1.el7.x86_6
-rw-r--r-- 1 7155 31415 3173088 Jun 27 18:49 mysql-community-libs-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 2177520 Jun 27 18:49 mysql-community-libs-compat-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 435206404 Jun 27 18:50 mysql-community-server-8.0.17-1.el7.x86_64.rpm
-rw-r--r-- 1 7155 31415 157704760 Jun 27 18:51 mysql-community-test-8.0.17-1.el7.x86_64.rpm
```

2. 删除 mariadb, (不删除会有冲突导致装不成功)

```
[root@elk-es235 bin]# rpm -qa|grep mariadb
mariadb-libs-5.5.41-2.el7_0.x86_64
[root@elk-es235 bin]# rpm -e mariadb-libs-5.5.41-2.el7_0.x86_64 --nodeps
```

- 3. 依次安装 common, libs, libs-compact, devel, embedded-compat, client, server。 安装命令如 rpm –ivh xxx.rpm
- 4. 初始化

命令行执行 mysqld –initialize; 执行完没报错默认为成功

- 5. 更改权限并启动 命令行执行 chown -R mysql:mysql /var/lib/mysql 然后启动 systemctl start mysqld
- 6. 查看默认密码,启动,并修改密码 查看密码 cat /var/log/mysqld.log |grep password 获得密码后登陆 mysgl –u root –p ,输出刚刚查看到的密码

登陆后修改密码 ALTER USER 'root'@'localhost' identified by 'gisnci'; 刷新 flush privileges;

-绿色版:mysql-8.0.17-el7-x86_64.tar.gz

- 1. 解压缩得到 mysql-8.0.17-linux-glibc2.12-x86_64
- 2. 将解压后的包放入目标目录 (可自己设定, 此目录需与后续配置文件对应上), 本示例放入/usr/local/mysql 中,

mv mysql-8.0.17-linux-glibc2.12-x86_64 /usr/local/mysql

3. 创建数据存储目录(可自己设定,此目录需与后续配置文件对应上),本示例放入 /usr/local/mysql/data 中

mkdir/usr/local/mysql/data

4. 创建组 mysql,以及修改根目录权限

groupadd mysgl

useradd -r -g mysql mysql

5. 拷贝运行程序并修改

cp /usr/local/mysql/support-files/mysql.server /etc/init.d/mysql.server vi /etc/init.d/mysql.server, 修改

basedir=/usr/local/mysql

datadir=/usr/local/mysql/data

6. 修改配置文件

备份, cp /etc/my.cnf /etc/my.cnf_bk vi /etc/my.cnf, 修改

[clinet]

port = 3306

socket = /tmp/mysql.sock

[mysqld]

user = mysql

server-id = 1

port = 3306

basedir = /usr/local/mysql

datadir=/usr/local/mysgl/data

pid-file = /usr/local/mysql/log/mysql.pid

tmpdir = /tmp

socket=/tmp/mysql.sock

max_connections = 400

max_connect_errors = 1000

max_allowed_packet = 128M

interactive_timeout = 1800

tmp_table_size = 134217728

max_heap_table_size = 134217728

Disabling symbolic-links is recommended to prevent assorted security risks #symbolic-links=0

Settings user and group are ignored when systemd is used.

If you need to run mysqld under a different user or group,

customize your systemd unit file for mariadb according to the

instructions in http://fedoraproject.org/wiki/Systemd

[mysqld_safe]

log-error=/usr/local/mysql/log/error.log

slow_query_log = 1

slow_query_log_file = /usr/local/mysql/log/slow.log

log_queries_not_using_indexes = 1

log_throttle_queries_not_using_indexes = 5

log_slow_slave_statements = 1

long_query_time = 8

min_examined_row_limit = 100

expire_logs_days = 5

7. 初始化,记录产生的临时密码

/usr/local/mysql/bin/mysqld –initialize –user=mysql –basedir=/usr/local/mysql – datadir=/usr/local/mysql/data

8. 创建相关日志文件

mkdir /usr/local/mysql/log

touch /usr/local/mysql/log/error.log

touch /usr/local/mysql/log/slow.log

touch /usr/local/mysql/log/mysql.pid

chown -R mysql:mysql/logl/usr/local/mysql/log

9. 启动服务

service mysql.server start

10. 登录 mysql –u root -p