

## planetmath.org

Math for the people, by the people.

## rectifiable set

Canonical name RectifiableSet

Date of creation 2013-03-22 14:28:12 Last modified on 2013-03-22 14:28:12

Owner paolini (1187) Last modified by paolini (1187)

Numerical id 11

Author paolini (1187)
Entry type Definition
Classification msc 49Q15
Defines density

Defines tangent vector

Defines approximate tangent plane

Let us denote with  $\mathcal{H}^m$  the m-dimensional Hausdorff measure in  $\mathbb{R}^n$ .

A set  $S \subset \mathbb{R}^n$  is said to be *countably m-rectifiable* if there exists a countable sequence of Lipschitz continuous functions  $f_k \colon \mathbb{R}^m \to \mathbb{R}^n$  such that

$$S \subset \bigcup_{k} f_k(\mathbb{R}^m).$$

A set  $S \subset \mathbb{R}^n$  is said to be *countably*  $(\mathcal{H}^m, m)$ -rectifiable if there exists a set S' which is countable m-rectifiable and such that  $\mathcal{H}^m(S \setminus S') = 0$ .

A set  $S \subset \mathbb{R}^n$  is said to be  $(\mathcal{H}^m, m)$ -rectifiable or simply m-rectifiable if it is  $(\mathcal{H}^m, m)$ -rectifiable and  $\mathcal{H}^m(S) < +\infty$ .

If S is any Borel subset of  $\mathbb{R}^n$  and  $x \in \mathbb{R}^n$  is given, one can define the density of S in x as

$$\Theta^{m}(S, x) = \lim_{\rho \to 0} \frac{\mathcal{H}^{m}(S \cap B_{\rho}(x))}{\omega_{m} \rho^{m}}$$

where  $\omega_m$  is the Lebesgue measure of the unit ball in  $\mathbb{R}^m$ . Notice that an m-dimensional plane  $\Pi$  has density 1 in all points  $x \in \Pi$  and density 0 in all points  $x \notin \Pi$ .

It turns out that if S is rectifiable, then in  $\mathcal{H}^m$ -a.e. point  $x \in S$  the density  $\Theta^m(S,x)$  exists and is equal to 1. Moreover in  $\mathcal{H}^m$ -a.e. point  $x \in S$  there exists an approximate tangent plane to S as defined below.

Given a point  $x \in S \subset \mathbb{R}^n$  and a vector  $v \in \mathbb{R}^n$  we say that v is tangent to S in x if there exists a sequence of points  $x_k \in S$ ,  $x_k \to x$  and a sequence of positive numbers  $\lambda_k$  such that

$$\lim_{k \to \infty} \lambda_k(x_k - x) = v.$$

If S is an m-dimensional manifold, then the set of tangent vectors to a point  $x \in S$  is nothing else than the usual tangent plane to S in x.

We say that a vector v is approximately tangent to S in x if it is a tangent vector to every subset S' of S such that  $\Theta^m(S \setminus S', x) = 0$ . Notice that every tangent vector is also an approximately tangent vector while the converse is not always true, as it is shown in an example below. The point, here, is that being the set S defined  $\mathcal{H}^m$ -almost everywhere, we need a stronger definition for tangent vectors.

The approximate tangent cone to S in x is the set of all approximately tangent vectors to S in x (notice that if v is a tangent vector then  $\lambda v$  is

also a tangent vector, for all  $\lambda > 0$ ). If the approximate tangent cone is an m-dimensional vector subspace of  $\mathbb{R}^n$ , it is called the *approximate tangent plane*.

Notice that if  $S \subset \mathbb{R}^n$  is any m-dimensional regular surface, and Q is the set of all points of  $\mathbb{R}^n$  with rational coordinates, then the set  $S \cup Q$  is an m-rectifiable set since  $\mathcal{H}^1(Q) = 0$ . Notice, however, that  $\overline{S \cup Q} = \mathbb{R}^n$  and consequently every vector v is tangent to  $S \cup Q$  in every point  $x \in S \cup Q$ . On the other hand the approximately tangent vectors to  $S \cup Q$  are only the tangent vectors to S, because the set Q has density 0 everywhere.

## References

[1] Frank Morgan: Geometric Measure Theory: A Beginner's Guide.