NAME

append_rec, create_file, create_id, create_rec, create_rec_id, destroy_file, destroy_rec, lfid_of_lrid, truncate_rec, update_rec, update_rec_hdr - Class ss_m Methods for File/Record Operations

SYNOPSIS

#include <sm_vas.h> // which includes sm.h

```
static rc_t create_f
const lvid_t& lvid,
serial t& lfid,
                 create_file(
                   property);
store_property_t
static rc_t
const lvid_t&
                 destroy_file(
                  lvid,
const serial_t&
                    lfid);
const Ivia_t&
const serial_t&
const vec_t&
                     lfid,
                    hdr,
                    len_hint,
smsize_t
const vec_t&
serial_t&
                     data,
                     lrid);
int
                     id_count,
                     id_start);
serial_t&
const vec_t&
smsize_t
                    hdr,
                   len_hint,
smsize_t
const vec_t&
                    data,
const serial_t&
                lrid);
static rc_t destroy_rec(
const lvid_t&
                   lvid,
const serial_t&
                     lrid);
static rc_t
                 update_rec(
const lvid_t&
                   lvid,
const serial_t&
                    lrid,
smsize_t
                    start,
const vec_t& data);
static rc_t
                 update_rec_hdr(
const lvid_t& lvid, const serial_t& lrid,
smsize_t
                    start,
const vec_t&
                     hdr);
```

```
static rc_t
                     append_rec(
const lvid_t&
                        lvid,
const serial_t&
                        lrid,
const vec t&
                        data);
static rc t
                     truncate rec(
const lvid_t&
                        lvid,
const serial_t&
                        lrid,
                        amount);
smsize t
// lfid_of_lrid converts a logical record ID into a logical file ID
static rc_t
                    lfid of lrid(
const lvid_t&
                       lvid,
const serial_t&
                        lrid,
serial t&
                        lfid);
```

DESCRIPTION

The above class ss_m methods all deal with manipulating files and records.

Common Parameters

There are a number of common parameters for these methods:

lvid Logical volume ID of volume containing a file/record.

lfid Logical file ID, the serial number of a file.

lrid Logical record ID, the serial number of a record.

data A vector pointing to data used to fill/overwrite the body of a record.

hdr A vector pointing to data used to fill/overwrite the header of a record.

create_file(lvid, lfid, property)

The **create_file** method creates a new file on the volume *lvid*, and returns its serial number in *lfid*. The *property* parameter specifies whether the file is temporary or not. See **enum(ssm)** for more information on file properties.

See the "ROOT INDEX METHODS" section of **volume(ssm)** for information on how to keep track of the files on a volume.

destroy file(lvid, lfid)

The **destroy_file** method destroys all records in the file and deallocates space used by a file. The space used by the file is not available for reuse until the transaction destroying the file commits.

create_rec(lvid, lfid, hdr, len_hint, data, lrid)

The **create_rec** method creates a record in a file. The ID of the new record is returned in the *lrid* parameter. The *len_hint* parameter is a "hint" about the final length of the record. If the creation will be followed by appends, *len_hint* should ideally be set to the final length of the record. This will allow the SM to place the record in a location with sufficient contiguous space for the record. A value of 0 should be used if the final length is unknown. No order is defined on the records in a file: when a new record is created, the I/O subsystem may place the record anywhere in the file.

create_id(lvid, id_count, id_start)

The **create_id** method generates id_count new IDs that can be used later by **create_rec_id** to associate a records with the IDs. The first ID is returned in id_start . The other IDs should be obtained by calling **id_start::increment(1)** id_count -1 times.

create_rec_id(lvid, lfid, hdr, len_hint, data, lrid)

The **create_rec_id** method is identical to **create_rec** except that the record ID is specified by the caller with the *lrid* parameter rather than being generated and returned in *lrid* as is done in **create_rec.**

destroy_rec(lvid, lrid)

The **destroy_rec** method destroys the specified record.

update rec(lvid, lrid, start, data)

The **update_rec** method updates a range of bytes in the body of the record specified by *lvid*, *lrid*. The byte offset, from the beginning of the record body, for the beginning of the range is specified by the *start* parameter. The length of the range is the length of the *data* vector. The range is replaced by the bytes pointed to by the *data* parameter. Note that **update_rec** cannot be used to change the size of the record. It is an error to specify a starting location and vector length that imply updating beyond the end of the record.

update_rec_hdr(lvid, lrid, start, hdr)

The **update_rec_hdr** method updates a range of bytes in the header of the record specified by *lvid*, *lrid*. The byte offset, from the beginning of the header, for the beginning of the range is specified by the *start* parameter. The length of the range is the length of the *hdr* vector. The range is replaced by the bytes pointed to by the *hdr* parameter.

Note: There are no methods for appending to a record header or truncating a record header (as there are for a record body). If these methods would be useful for you, please contact the Shore developers.

append_rec(lvid, lrid, data)

The **append_rec** method appends the bytes pointed to by *data* to the end of the record body.

truncate_rec(lvid, lrid, amount)

The **truncate_rec** method removes *amount* bytes from the end of a record body.

lfid_of_lrid(lvid, lrid, lfid)

The **lfid_of_lrid** method returns, in *lfid*, the ID of file containing the record, *lrid*.

UNINITIALIZED DATA

The functions **create_rec**, **append_rec**, and **update_rec** can be used to write blocks of data that are all zeroes, with minimal logging. This is useful, for example, when a value-added server creates a record of a known size but with uninitialized data. To make use of this feature, these functions are called with data vectors of a specialized type, *zvec_t*, whose constructor takes only a size:

ERRORS

All of the above methods return a **w_rc_t** error code. If an error occurs during a method that is updating persistent data (the create, update, append, and truncate methods will update data) then the record/file could be in an inconsistent state. The caller then has the choice of aborting the transaction or rolling back to the nearest save-point (see **transaction(ssm)**).

See **errors**(ssm) for more information on error handling.

EXAMPLES

To Do.

VERSION

This manual page applies to Version 1.1 of the Shore software.

SPONSORSHIP

The Shore project is sponsored by the Advanced Research Project Agency, ARPA order number 018 (formerly 8230), monitored by the U.S. Army Research Laboratory under contract DAAB07-91-C-Q518.

COPYRIGHT

Copyright © 1994, 1995, 1996, 1997, Computer Sciences Department, University of WisconsinMadison. All Rights Reserved.

SEE ALSO

vec_t(common), pin_i(ssm), scan_file_i(ssm), intro(ssm),