

03 — Fund Flows

This document traces money for each operation: where value enters, where it sits, who signs, and where it exits. The **local fiat (TZS/M-Pesa) leg is always executed by the licensed on/off-ramp partner**; OlomiPay holds value as USDC on Stellar.

Legend: **User wallet** = the user's Stellar USDC account · **Platform wallets** = gas / fee / savings-vault / treasury accounts controlled by OlomiPay · **Partner** = licensed on/off-ramp (Yellow Card).

1. Add money (deposit) — TZS → USD balance

User (M-Pesa, TZS)

- 1. user requests deposit of X TZS in app



Partner (Yellow Card) – collects TZS via M-Pesa, converts to USDC

- 2. partner pays out USDC (net of partner fee)



User wallet (USDC on Stellar) – balance shown to user as USD

- OlomiPay never touches TZS; the partner performs collection + conversion under its licence and confirms via webhook.
- Idempotency: each deposit has an internal reference; the partner order is keyed to it.

2. Send money (P2P) — user → user

Sender wallet (USDC)

- 1. sender authorises with PIN (signs transfer)
- 2. AML screen (riskGate) + tier-limit check



Platform fee wallet ← ~1% platform fee

+

Recipient wallet (USDC) ← net amount

- On-chain transfer on Stellar; gas paid by the platform gas wallet (fee-bump), so the user needs no native asset.
- Recipient sees an instant USD credit + notification.

3. Withdraw — USD balance → TZS (M-Pesa)

User wallet (USDC)

- 1. user authorises with PIN
- 2. tier-limit + AML checks



Platform (debits user's USDC)

- 3. instruct partner to pay out



Partner (Yellow Card) – converts USDC → TZS, pays user's M-Pesa



User (M-Pesa, TZS)

4. Cross-border send (remittance)

Sender wallet (USDC) → platform debits → Partner converts USDC → local currency
→ recipient's mobile money (other country)

- Same control set as withdrawal (PIN, tier limits incl. a remittance feature gate, AML screen). Real payout requires the partner's production corridors.

5. Savings / Goals

User wallet (USDC)

- 1. user authorises deposit with PIN



Savings vault (platform-controlled wallet) – accrues interest

- 2. on withdrawal, platform signs payout



User wallet (USDC)

- While saved, funds sit in a **platform-controlled vault** → this portion is explicitly **custodial** (see Doc 04). Withdrawals are platform-signed.

6. Cash agents (cash-in / cash-out)

Cash-in : customer gives agent physical cash → agent wallet → customer wallet (USDC)

Cash-out : customer authorises (PIN) → customer wallet → agent wallet → agent gives cash

- Agents are KYC-verified, limit-capped, and monitored for velocity/abandonment (see Doc 05). Cash-out uses short-lived confirmation codes.

7. Fee handling & treasury

- The ~1% platform fee accrues in a **dedicated fee wallet** (separate from gas).
- Fees can be swept to top up the gas wallet (operational sustainability).
- Platform reserves vs. user liabilities are **reconciled automatically** every cycle (alerts if platform USDC < user liabilities). See Doc 05/06.

8. Settlement & reconciliation summary

Operation	Fiat leg (partner)	On-chain leg (OlomiPay)	Signer
Deposit	TZS→USDC	USDC credited to user	Partner
Send	—	USDC user→user (+fee)	User (PIN)
Withdraw	USDC→TZS	USDC debited from user	User (PIN) + platform

Remittance	USDC→local	USDC debited from user	User (PIN) + platform
Savings in/out	—	user↔vault	User (PIN) in; platform out
Agent cash-in/out	—	agent↔user	Agent / user (PIN)