

Notes on Transport Phenomena in Materials

Gandham Phanikumar

Professor, Department of Metallurgical and Materials Engineering

Indian Institute of Technology Madras

Chennai 600036 INDIA

e-mail: gphani@iitm.ac.in

url: <http://gphanikumar.github.io>

Course website: <https://github.com/gphanikumar/tpnotes>

October 25, 2025

Contents

List of Symbols	15
1 Introduction to the course	16
1.1 Description	16
1.2 Aim of the course	17
1.3 Learning objectives and Bloom's Taxonomy	17
1.4 Prelude	19
1.5 Online videos	19
2 Subscript notation	24
2.1 Concept map	24
2.2 Rules of subscript notation	24
2.3 Nabla	28
2.4 Kronecker Delta	29
2.5 Levi-Civita Symbol	30
2.6 Summary	32
3 Application of subscript notation	33
3.1 Relation between Kronecker delta and Levi-Civita symbol	33
3.2 Vector identities	33
3.3 Summary	43
4 Coordinate transformations	44
4.1 Rotation of coordinate axes	44
4.2 Scaffold to determine transformation matrix	53
4.3 Rodrigues rotation formula	54
4.4 Summary	55
5 Introduction to Cartesian Tensors	56
5.1 Cartesian Tensors	56

5.1.1	Scalar	56
5.1.2	Vector	56
5.1.3	Bisor	57
5.1.4	Trisor	57
5.1.5	Tetror	57
5.1.6	Tensor	57
5.2	Operations on tensors	58
5.3	Types of tensors	58
5.3.1	Symmetric Tensor	58
5.3.2	Anti-symmetric Tensor	59
5.4	Summary	63
6	Symmetry of Property Tensors	64
6.1	Tensor quantities	64
6.2	Tensors that represent physical properties	64
6.3	Isotropic tensors	68
6.4	Symmetry elements of crystal classes	69
6.5	Scaffold to reduce components by symmetry operations	71
6.6	Components of a symmetric tensor property	72
6.7	Summary	73
7	Continuity Equation	74
7.1	Learning objectives	74
7.2	Concept map	74
7.3	Type of specifications	75
7.4	Time derivative	76
7.5	Flux of mass	77
7.6	Mass balance	79
7.7	Continuity equation	79
7.8	Strain rate tensor	80
7.9	Rate of dilation	81
7.10	Other forms of continuity equation	81
7.11	Applications of continuity equation	84
7.11.1	Unidirectional velocities	84
7.11.2	Interpretation of continuity equation	85
7.12	Exercises	85
7.13	Further study	86

7.14 Summary	86
8 Planar flows	87
8.1 Learning objectives	87
8.2 Reducing the number of unknown velocity components	87
8.3 Stream function	88
8.3.1 Rectangular	89
8.3.2 Cylindrical	89
8.3.3 Spherical	89
8.4 Vorticity	92
8.5 Velocity potential	93
8.6 Potential flow	93
8.7 Elementary planar flows	94
8.7.1 Uniform flow	94
8.7.2 Stagnation flow	94
8.7.3 Sink flow	94
8.7.4 Source flow	95
8.7.5 Doublet	96
8.7.6 Vortex	97
8.7.7 Combinations of elementary planar flows	97
8.8 Summary	98
8.9 Further study	98
9 Navier-Stokes Equations - Part 1	100
9.1 Learning objectives	100
9.2 Concept map	100
9.3 Forces	100
9.4 Equation of motion	101
9.5 Stress tensor	102
9.6 Strain rate tensor	103
9.7 Relation between stress and strain-rate	104
9.8 Navier-Stokes equations	106
10 Navier-Stokes Equations - Part 2	109
10.1 Significance of the linear relation and Viscosity	109
10.2 Reynold's number	110
10.3 Equations in cylindrical co-ordinate system	112

10.3.1	Continuity equation	112
10.3.2	Other operators	112
10.3.3	Stress components	113
10.3.4	Navier-Stokes equations in cylindrical co-ordinate system	113
11	Specific cases of fluid flow - Planar	114
11.1	Learning objectives	114
11.2	Boundary Conditions and Problem Definitions	114
11.3	Trivial case reproducing Newton's Law	116
11.4	Film flow	118
11.5	Flow between two plates	120
12	Specific cases of fluid flow - Cylindrical	124
12.1	Flow through a pipe	124
13	Creeping flow	133
13.1	Learning objectives	133
13.2	Concept map	133
13.3	N-S equations using stream function	133
13.4	The E^2 operator	135
13.5	Creeping flow over a sphere	136
13.5.1	Pressure	139
13.5.2	Drag forces	140
13.5.3	Terminal velocity	141
13.6	Summary	141
13.7	Exercises	141
13.8	Creeping flow through a porous medium	143
13.9	Exercises	145
14	Correlations for turbulent regime	146
14.1	Learning objectives	146
14.2	Concept map	146
14.3	Friction factor	146
14.4	Flow through tube	147
14.5	Flow across a sphere	148
14.6	Flow through a porous medium	149
14.7	Flow through a packed bed of spheres	150

14.8 Summary	150
14.9 Exercises	150
15 Energy Transport	156
15.1 Learning objectives	156
15.2 Introduction	156
15.3 Thermal equilibrium	156
15.4 Balance of Enthalpy	157
15.5 Fourier's first law	159
15.6 Fourier's second law	160
15.7 Boundary conditions	161
15.8 Summary	162
16 Steady state heat transfer in solids	163
16.1 Concept map	163
16.2 Steady state 1D heat transfer	163
16.2.1 Across a rectangular slab	163
16.2.2 Across a cylindrical wall	164
16.2.3 Across a spherical shell	166
16.2.4 Point effect of diffusion	166
16.2.5 Across a planar composite wall	167
16.2.6 Across a cylindrical composite wall	168
16.3 Summary	169
16.4 Exercises	169
17 Transient heat transfer in solids	171
17.0.1 Introduction	171
17.0.2 Interface dominated	171
17.0.3 Conduction dominated	172
17.1 Moving boundary condition	174
17.1.1 Solidification: mould and solid conductivity controlled	175
17.2 Exercises	178
18 Heat tranfer with advection term	179
18.1 Steady state heat transfer	179
18.1.1 Heat transfer normal to plug flow	179
18.1.2 Heat transfer along plug flow	180

18.2 Exercises	180
18.3 Heat transfer in a smooth pipe	181
18.3.1 Bulk temperature	184
18.4 Constant Surface Temperature solution	185
18.5 Definitions of some non-dimensional numbers	185
18.6 Forced convection correlations	186
18.7 Exercises	188
18.8 Summary	188
19 Mass Transfer	190
19.1 Introduction	190
19.2 Organization of topics	190
19.3 Chemical equilibrium	191
19.4 Reaction Equilibrium	192
19.4.1 Objectives	192
19.4.2 Example system	192
19.4.3 Gibbs energy minimization method	193
19.4.4 Entropy maximization method	195
19.4.5 Ellingham Diagram	197
19.4.6 References	198
19.5 Species balance equation	199
19.5.1 Continuity Equation	201
19.5.2 Diffusional flux	201
19.5.3 Ficks Law	202
19.5.4 Diffusion equation	203
19.5.5 Diffusivity	203
20 Solute diffusion in solids	205
20.1 Solid state diffusion	205
20.1.1 Steady state diffusion profiles	205
20.1.2 Fixed boundary compositions	205
20.1.3 Fixed total solute content	205
20.1.4 Fourier series solution	206
20.1.5 Diffusion during growth of precipitate	206
20.1.6 Solute profile during directional solidification	206
20.1.7 Solute profile during eutectic solidification	207
20.2 Diffusion with two species considered	207

20.2.1 Interdiffusion coefficient	207
20.2.2 Stagnant layer approach	207
20.3 Boundary conditions	209
20.3.1 Solubility limits	209
20.3.2 Reaction mass transfer	209
20.3.3 Sieverts Law	210
21 Convective mass transfer	211
21.1 Mass transfer with advection	211
21.2 Mass transfer with advection	211
21.2.1 Mass transfer coefficient	212
21.2.2 Film Theory	213
21.2.3 Penetration Theory	214
21.2.4 Surface Renewal Theory	214
21.2.5 Sherwood number	215
21.3 Exercises	216
22 Similarity across transport phenomena	218
22.1 Learning objectives	218
22.2 Reynold's analogy	218
22.3 Chilton-Colburn analogy	218
22.4 Summary	221
22.5 Exercises	221
A Derivations	224
A.1 The quotient rule	224
A.2 Symmetric tensors are diagonalisable	225
A.3 Levi-Civita tensor is isotropic	227
A.4 General form of isotropic tensor of order four	228
A.5 Simplification of tensor properties for crystals	230
A.6 Change of variable with multiple integrals	231
A.7 Dilation	232
A.8 Reynold's transport theorem	233
A.9 RTT and Continuity Equation	234
A.10 Cauchy's stress principle	235
A.11 Stress is a tensor	236
A.12 Stress tensor is symmetric	237

A.13 Meaning of terms in strain rate tensor	238
A.14 Strain rate tensor	240

List of Figures

2.1	Concept map on the use of subscript notation in introducing tensors.	24
4.1	Orthogonal axes	44
4.2	Illustration of simple rotation of coordinate system	45
4.3	Simple rotation about $\hat{x}_3$ axis	46
4.4	New unit vector $\hat{x}_1$ in terms of old ones after coordinate rotation	47
4.5	New unit vector $\hat{x}_2$ in terms of old ones after coordinate rotation	48
4.6	Old unit vector $\hat{x}_1$ in terms of new ones after coordinate rotation	49
4.7	Old unit vector $\hat{x}_2$ in terms of new ones after coordinate rotation	50
4.8	Components of a vector across coordinate rotation	50
6.1	Examples of tensor quantities	67
7.1	Concept map to arrive at continuity equation	74
7.2	An image generated by chatgpt to show Euler as traffic police and Lagrange as a driver. Helps c	
7.3	Motion of a volume element in a fluid	75
7.4	Convention for flux of material	77
7.5	Schematic for divergence theorem	78
7.6	Motion of a control volume due to unidirectional flow along $\hat{x}_1$	80
7.7	Motion of a control volume due to unidirectional flow along $\hat{x}_2$	81
7.8	Motion of a control volume due to unidirectional flow	82
7.9	Motion of a control volume due to flow with velocity gradient	83
7.10	Rate of dilation	83
8.1	Sign convention for stream function	90
8.2	Convention for flow direction using contours of stream function	91
8.3	Uniform flow using potential function	94
8.4	Stagnation flow using potential function	95
8.5	Sink flow using potential function	95
8.6	Source flow using potential function	96

8.7	Doublet flow using potential function	96
8.8	Vortex flow using potential function	97
8.9	Source + Uniform flow using potential function	97
8.10	Source + Vortex flow using potential function	98
8.11	Doublet + Uniform flow using potential function	98
8.12	Doublet + Vortex + Uniform flow using potential function	99
9.1	Concept map of derivation of Navier-Stokes equation	101
9.2	Concept map of how the constitutive relation is being proposed between deviatoric stress and ve	
10.1	Types of fluids	110
11.1	Problem domain to recover Newton's Law	116
11.2	Velocity and Stress distribution in the Newton's Law problem	117
11.3	Schematic of a film flow problem	118
11.4	Velocity and Stress distribution in a film flow problem	120
11.5	Flow in a channel	120
11.6	Flow in a channel	121
11.7	Schematic of a film mixing problem	122
11.8	Squeegee device	123
12.1	Pipe Flow	124
12.2	Solution to Pipe Flow	126
12.3	Axial film flow	126
12.4	Leaking Tank	127
12.5	Cubic network of pipes	127
12.6	Channel flow between porous walls	130
13.1	Concept map for Stokes law derivation	134
13.2	Creeping flow around a sphere	137
13.3	Porous medium and its approximation as a bundle of tubes	143
14.1	Concept map on how one usually goes about problem solution using friction factors	147
16.1	Concept map on heat transfer solutions	163
16.2	Heat flow across a slab	164
16.3	Heat flow across a cylindrical wall	165
16.4	Point effect of diffusion	167
16.5	Box type multi-walled furnace schematic created using Gemini 2.0 Flash.	167

16.6	Schematic thermal profile across a composite wall of a furnace. The image of the furnace was cr	
17.1	Regimes of domination of convective and conduction heat transfer	173
17.2	Temperature profile during solidification	174
17.3	Temperature profile during solidification	176
18.1	1D Profiles of thermal conduction problems	189
19.1	Schematic showing changes in reaction constant	195
20.1	Fixed Compositions	206
20.2	Stagnant layer approach	207
21.1	Surface Renewal Approach	212
21.2	Film Theory	213
21.3	Schematic of penetration theory. Here, $t_2 > t_1$	214
21.4	Schematic of surface renewal theory.	215
A.1	Analysis of deformation of a fluid element	238

List of Tables

- 1.1 List of online videos and content description 23
- 6.1 Examples of common physical phenomena, adapted from [Perelomova and Tagieva, 1983]. 65
- 6.2 Symmetry elements in some crystal systems 70

List of Learning Objectives

2.1	Apply (Tensors)	25
2.2	Understand (Tensors)	28
2.3	Apply (Preliminaries)	29
2.4	Apply (Preliminaries)	30
2.5	Apply (Preliminaries)	31
3.1	Apply (Vector Identities)	33
4.1	Apply (Coordinate transforms)	44
4.2	Apply (Coordinate transforms)	54
5.1	Remember (Tensor introduction)	56
5.2	Understand (Tensor Introduction)	57
5.3	Understand (Tensor introduction)	59
5.4	Understand (Tensor components)	63
5.5	Understand (Tensor components)	63
6.1	Apply (Tensors)	68
6.2	Apply (Tensors)	69
6.3	Apply (Tensors)	70
7.1	Apply (Fluid Flow)	74
7.2	Apply (Fluid Flow)	84
7.3	Apply (Fluid Flow)	85
8.1	Apply (Fluid Flow)	88
8.2	Apply (Fluid Flow)	92
8.3	Apply (Fluid Flow)	93
8.4	Apply (Fluid Flow)	94
9.1	Understand (Fluid Flow)	100
9.2	Apply (Fluid Flow)	101

10.1 Understand (Fluid Flow)	109
--	-----

List of Symbols

u velocity
 μ viscosity

Chapter 1

Introduction to the course

1.1 Description

MM2041 Transport Phenomena in Materials

Credits: 3 0 0 3

- Fundamentals of heat conduction, convection, radiation and their combined effect; steady and unsteady heat transfer in metallurgical processes, e.g. continuous casting, spray forming, solidification, extrusion etc.
- Diffusion and its application in solid state materials processing, convective mass transfer in extraction processes, unsteady diffusion in finite and infinite bodies, diffusion and chemical reaction in porous and nonporous solid.
- Newton's law of viscosity, laminar flow problems related to metallurgy, general equation of continuity and motion, application of Bernoulli's equation in flow measuring devices and flow from ladles.

References:

1. Transport Phenomenon in Metallurgy
G.H. Geiger and D.R. Poirier
Addison Wesley, 1973
2. Transport Phenomenon
R.B. Bird, W.E. Stewart and E.N. Lightfoot
John Wiley and Sons, 1994
3. Transport Phenomena and Materials Processing
Sindo Kou
John Wiley and Sons. Inc., 1996
4. Transport Phenomena in Materials Processing
D.R. Poirer and G.H. Geiger
TMS, Warrendale, PA, 1998

MT538 Transport Phenomena in Metallurgical Processes

Credits: 3 0 0 3

- Types of reactors like plug flow, fluidised bed and their applications. Transport of heat and mass in sinter beds, fluidised beds, plug flow reactions as applied to metallurgical processes.
- Convective and diffusion controlled mass transport.
- Modelling of metallurgical reactions, slag-metal reactions, heat treatment processes, sponge iron making, hydro metallurgical and pyro metallurgical processes in non-ferrous extraction

References:

1. Transport Phenomenon in Metallurgy
G.H. Geiger and D.R. Poirier
Addison Wesley, 1973
2. An Introduction to Transport Phenomena in Materials Engineering
David R. Gaskell
Macmillan, New York (1992)
3. Transport Phenomena and Materials Processing
Sindo Kou
John Wiley and Sons. Inc., 1996
4. Transport Phenomena in Materials Processing
D.R. Poirer and G.H. Geiger
TMS, Warrendale, PA, 1998
5. Rate phenomena in process metallurgy
Julian Szekely and Nickolas J. Themells
John Wiley and sons, New York (1971)

1.2 Aim of the course

Introduce transport of heat, momentum and mass - in materials of our interest

Physics behind the transport phenomena

Range of applicability of the equations, initial and boundary conditions, solution methods

Similarity and relations between the three transport phenomena

1.3 Learning objectives and Bloom's Taxonomy

In this book, we use the revised Bloom's taxonomy as given by Anderson and co-workers [Anderson and Kra
The learning objectives will appear with the following tags. The action verbs and their definitions as in [Anderson and Krathwohl, 2001] are given below. An attempt is made to either use

the action verb in the question or map each question in the book to the corresponding learning objective.

C1 : Remember

- Recognize / Identify : being able to correctly relate to knowledge in long term memory
- Recall / Retrieve : being able to extract knowledge from long term memory

C2 : Understand

- Classify / Categorize / Subsume : Determining that something belongs to a category
- Summarize / Abstract / Generalize : being able to express the take away
- Interpret / Clarify / Paraphrase / Represent / Translate : changing from one form of representation to another
- Exemplify / Illustrate / Instantiate : Finding a specific example or illustration of a principle or concept
- Infer / Conclude / Extrapolate / Interpolate / Predict : being able to draw a logical conclusion
- Explain / Construct : arrive at the cause and effect relationship
- Compare / Contrast / Map / Match : being able to relate two (sets) of concepts, objects, ideas etc.

C3A : Apply

- Execute / carry out : apply a sequence of steps to a related and familiar task
- Implement / Use : apply a sequence of steps to an unfamiliar task

C3B : Analyze

- Differentiate / Discriminate / Distinguish / Focus / Select : being able to pick the desirable or relevant portions from the rest
- Organize / Find / Integrate / Outline / Parse / Structure : being able to determine how different pieces fit with each other in a coherent structure of knowledge
- Attribute / Deconstruct : being able to identify the underlying intent / point of view / value / bias

C3C : Evaluate

- Check / Coordinate / Detect / Monitor / Test : detecting inconsistencies in a process, determining effectiveness of a procedure or its implementation
- Critique / Judge : detect inconsistencies against a criterion of evaluation, determine suitability of a procedure

C3D : Create

- Generate / Hypothesize : being able to come up with an alternative hypothesis based on a criterion
- Plan / Design : Devise a procedure to accomplish a task
- Produce / Construct : Invent a product

1.4 Prelude

In the course, we will use multiple notations to write down the equations. Consider the following alternate forms of the equation that states divergence of a vector u is zero.

$$\vec{u} = u_1\hat{x}_1 + u_2\hat{x}_2 + u_3\hat{x}_3$$

$$\vec{\nabla} = \hat{x}_1\frac{\partial}{\partial x_1} + \hat{x}_2\frac{\partial}{\partial x_2} + \hat{x}_3\frac{\partial}{\partial x_3}$$

$$\frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = 0 \quad (1.1)$$

$$\vec{\nabla} \cdot \vec{u} = 0 \quad (1.2)$$

$$\nabla_i u_i = 0 \quad (1.3)$$

$$u_{i,i} = 0 \quad (1.4)$$

Continuum hypothesis: The material is continuous in structure such that the physical quantities associated with the material within a given small volume are regarded as spread over uniformly over that volume.

The hypothesis is valid for most of the situations. In situations such as when the length scales are nanometric and the time scales are picometric, the hypothesis breaks down.

1.5 Online videos

Videos of lectures based on this course are freely available on youtube. The links for the videos and the mapping of the content are given below.

The youtube links can be accessed by prepending the string with <https://youtu.be/>.

Lec	Topics	Link	Mapping
01	Subscript Notation - Part 1: Subscript notation, Einstein summation convention, use of comma for differentiation, inner and outer products, Kronecker delta, Trace of Matrix, use of Kronecker delta to replace free indices.	7xNUBQax8Hk	Chapter 2

02	Subscript Notation - Part 2 : Levi-Civita symbol / Permutation matrix, curl, cross product, determinant, double cross products and use of Kronecker delta to simplify products of Levi-Civita symbols, proving vector identities using subscript notation	43_Z57_1zRY	Chapter 3
03	Coordinate Rotation : Orthogonal coordinate system, handedness, transformation matrix for coordinate rotation and its properties, definition of tensors of different order.	CaZTftBJD6I	Chapter 4
04	Introduction to Tensors : Tensor quantities of different order, forms of isotropic tensors of different order, algebraic operations on tensors, symmetric and anti-symmetric tensors, inner and outer product of tensors, contraction theorem, quotient theorem.	FbnS5qsRkSg	Chapter 5
05	Symmetry of Properties : Constitutive relationships with examples illustrating tensors of different order, Curie principle, Neumann principle, imposing symmetry of crystal on a tensor property and evaluating components, Diagonalization of symmetric tensors.	UjhI0PwkSko	Chapter 6
06	Material Derivative : Eulerian specification, material derivative, control volume approach, convention for flux, divergence theorem, velocity gradients and strain rate tensor, rate of dilation, definition of incompressible fluid, balance of mass and continuity equation in rectangular, cylindrical and spherical coordinate systems, application of continuity equation to determine missing components of incompressible fluid flow in rectangular coordinate system.	we01LUmy0oY	Chapter 7
07	Planar Flows : Stream function in rectangular, cylindrical and spherical coordinate systems, vorticity, definition of irrotational flow, velocity potential, potential flows, elementary planar flows and their combinations, application to metallurgical problems.	Q1daoew7-3Q	Chapter 8
08	Reynolds Transport Theorem : Concept map of derivation of Reynolds transport theorem, Deformation of fluid element due to velocity gradients, convected coordinates, Jacobian of transformation, rate of dilation in terms of Jacobian of transformation, material derivative of integral over control volume, Reynolds transport theorem, application to continuity equation and momentum.	V-0oTDBNZK4	Appendixes A.6, A.7, A.8, A.9

09	Derivation of Navier-Stokes equation - Part 1 : Concept map of derivation of Navier-Stokes equation, Newtons second law of balance of linear momentum to control volume approach, body forces, stress tensor and its symmetry, deviatoric stress, definition of pressure in terms of trace of stress tensor, velocity gradients and its components representing dilational strain rate, shear strain rate and rotational strain rate, linear constitutive relation between velocity gradient and deviatoric stress, definition of Newtonian fluid, Stokes assumption, Equation of motion, Navier-Stokes equation.	Y3lcc5rCJ8E	Chapter 9
10	Navier Stokes equations - Part 2 : Types of fluids based on relation between strain rate and shear stress, expressions for shear stress in rectangular and cylindrical coordinate systems, designation of different terms in Navier-Stokes equation, scaling of Navier-Stokes equation, Reynolds number, Navier-Stokes equations in 2D using stream function, Jacobian determinant, Special cases of Navier-Stokes equations under limiting conditions.	e1G1VXdLK00	Chapter 10
11	Flow problem statements: Assumptions used in flow problem definitions, Newtonian fluid, Incompressible fluid, constant properties, laminar regime, problem domain and boundaries, steady state, unidirectional flow, fully developed flow, boundary conditions, no slip condition, validity of analytical solutions.	Z0ahHJOZUeE	Chapter 11
12	Simple cases in fluid flow : rectangular coordinate system : Convention for sign of shear stress, distribution of velocity and shear stress across domain for simple problems: film flow on an inclined plane, planar Couette flow, average flow rate, volume flow rate and mass flow rate, residence time and exposure time.	nZgfz1CAm1E	Chapter 11
13	Simple cases in fluid flow : cylindrical coordinate system : Pressure variation due to velocity components, unidirectional radial flow in cylindrical coordinate system, Poiseuille flow, average flow rate through a pipe, Hagen-Poiseuille equation, Axial flow through annular region, Couette flow, limiting case enabling planar flow assumption.	pdI1ZvocUbI	Chapter 12

14	Pipe flow and porous medium: Electrical analogue to pipe flow, definition of hydraulic radius, concept of superficial velocity through a porous medium, modeling porous medium as a bundle of tubes, Blake-Kozeny equation, Darcy's law, definition of Reynold's number for porous media, bed of spheres as a porous medium.	qEYDWzyPyqo	Chapter 13
15	Simple cases in fluid flow : spherical coordinate system: Concept map of derivation of Stokes equation, creeping flow over a sphere, Stokes equation, stream function solution, friction drag and form drag, Stokes law for terminal velocity.	yFiZ2aGQi1k	Chapter 13
16	Friction factors and correlations : Definition of friction factor for internal and external flow, friction factor expressions from exact analytical solutions to Navier-Stokes equations, empirical correlations for simple cases in turbulent regime.	tFk7ulqJxTE	Chapter 14
17	Energy Transport: Enthalpy change without phase change, spontaneity of thermal equilibration using total entropy change, Fourier law for heat conduction, derivation of governing equation for heat conduction, boundary conditions for heat transfer, heat transfer coefficient.	RY-JNULWk3g	Chapter 15
18	Conduction cases - steady state : Steady state heat conduction across rectangular slab, cylindrical wall and spherical shell, point effect of diffusion, thermal resistances, electrical analogue to heat conduction, limiting case to approximate cylindrical and spherical cases to rectangular equivalents, steady state heat conduction across a composite wall.	yS0tVTsFGI4	Chapter 16
19	Conduction cases - transient state : Transient heat conduction in 1D, interface limited and diffusion limited heat transfer, Biot number, Fourier number, Lumped heat capacitance method, error function solution, application of error function to determine interface temperature in metallurgical problems such as casting, Chvorinov's rule.	XB4wVJT0yd4	Chapter 17

20	Convective heat transfer : Effect of advection on heat transfer / convective heat transfer, Peclet number, limiting cases for use of upstream temperature / up-wind scheme, heat transfer in a pipe with Poiseuille flow, Bulk temperature, Nusselt number, empirical correlations of Nusselt number for simple cases.	49zn_rY5HEQ	Chapter 18
21	Mass Transfer overview	azXGH2kcDJU	
22	Chemical equilibrium	c5T6bttIWSQ	
23	Reaction equilibrium	1LvAAmpr7fA	
24	Species Balance equation	TuiURnxQ6h0	
25	Solute transfer modelling - Part 1	BxGh2taiYXQ	
26	Solute transfer modelling - Part 2	EBmByHHc6rA	
27	Solute segregation profile - Part 1	tBMw6-C4Hx4	
28	Solute segregation profile - Part 2	1429Vw7yk1c	
29	Problem statements	JWemMy2w1Gw	
30	Diffusion in solid state	NTXrsUwMgtA	
31	Transient diffusion in solid state	mYuLNGQROFI	
32	Mass transfer in fluids	KfcZQmCT1k4	
33	Similarity Analysis	940uYw5DIBg	

Table 1.1: List of online videos and content description

Chapter 2

Subscript notation

2.1 Concept map

Most of the discussion in the notes will assume a cartesian co-ordinate system unless otherwise mentioned. You can read further about introduction to tensors in one of the following resources:

- Chapter 26 titled Tensors in [Riley et al., 2006].
- The whole of [Bourne and Kendall, 1992].

A concept map of how subscript notation will be used in this chapter is given in figure 2.1.




Figure 2.1: Concept map on the use of subscript notation in introducing tensors.

2.2 Rules of subscript notation

2.1 Apply (Tensors). *Analyse free and dummy indices in an expression and determine number of components*

Subscript notation was introduced by G. Ricci and popularised by Einstein. Each subscript (or index) runs from 1 to the dimension of the space in consideration. Since most of the time a 3D space is referred to, the subscripts run from 1 to 3. Following rules apply to the notation:

1. Cartesian Summation Convention: Subscripts that are repeated are called dummy subscripts and should be summed over the range that the subscript can take. Dummy index should not appear more than twice in a term.
2. Subscripts that are not repeated are called free subscripts.
3. Subscripts can come anywhere in an expression.
4. Subscripts after a comma indicate differentiation.
5. Free subscripts on either sides of the '=' sign should match.

Subscript notation is useful to represent three and higher dimensional entities. It simplifies expressions.

Examples

- Vector

$$u_i = (u_1 \ u_2 \ u_3) = \vec{u} = u_1\hat{x}_1 + u_2\hat{x}_2 + u_3\hat{x}_3$$

- Matrices and Tensors

$$a_{ij} = \begin{pmatrix} a_{11} & a_{12} & a_{13} \\ a_{21} & a_{22} & a_{23} \\ a_{31} & a_{32} & a_{33} \end{pmatrix}$$

- Nabla or Del or Grad:

$$\vec{\nabla} = \frac{\partial}{\partial x_1}\hat{x}_1 + \frac{\partial}{\partial x_2}\hat{x}_2 + \frac{\partial}{\partial x_3}\hat{x}_3 = \nabla_i$$

- Gradient:

$$\vec{\nabla}\phi = \frac{\partial\phi}{\partial x_1}\hat{x}_1 + \frac{\partial\phi}{\partial x_2}\hat{x}_2 + \frac{\partial\phi}{\partial x_3}\hat{x}_3 = \frac{\partial\phi}{\partial x_i} = \nabla_i\phi = \phi_{,i}$$

- Divergence:

$$\vec{\nabla} \cdot \vec{u} = \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3}$$
$$\text{Div}(u) = \frac{\partial u_i}{\partial x_i} = u_{i,i}$$

- Inner product is an operation where there is a contraction of the number of subscripts. For two vectors, it is also called as dot product.

$$a_ib_i = a_1b_1 + a_2b_2 + a_3b_3$$

$$a_i a_i = a_1^2 + a_2^2 + a_3^2$$

$$\begin{aligned} c_j &= a_{ij} b_i \\ c_1 &= a_{11} b_1 + a_{21} b_2 + a_{31} b_3 \\ &\vdots \end{aligned}$$

- Outer product is an operation where there is an expansion of the number of subscripts.

$$a_i b_j = \begin{pmatrix} a_1 b_1 & a_1 b_2 & a_1 b_3 \\ a_2 b_1 & a_2 b_2 & a_2 b_3 \\ a_3 b_1 & a_3 b_2 & a_3 b_3 \end{pmatrix}$$

Exercise 2.2.1

Subscripts that are not repeated are called free subscripts. Each subscript (or index) runs from 1 to the dimension of the space (3, by default). Fill the number of components for each of the following quantities.

1. u_i
2. σ_{ij}
3. ϵ_{ijk}
4. μ_{ijkl}

Think of these entities as those physical parameters that can be represented by a bunch of numbers in any given coordinate system. These numbers can be arranged as matrices for convenience.

Solution 2.2.1

1. $u_i : 3^1 = 3$
2. $\sigma_{ij} : 3^2 = 9$
3. $\epsilon_{ijk} : 3^3 = 27$
4. $\mu_{ijkl} : 3^4 = 81$

Exercise 2.2.2

Cartesian summation convention: Subscripts that are repeated are called dummy subscripts and should be summed over the range that the subscript can take. The rest of the subscripts are free subscripts. Fill the number of components for each of the following quantities.

1. $u_i v_i$
2. $a_{ij} b_{ij}$
3. $d_{ijk} E_k$
4. $\epsilon_{ijk} \sigma_{ij}$

5. $S_{ijkl}\sigma_{kl}$
6. $\frac{1}{2}C_{ijkl}e_{ij}e_{kl}$
7. $\chi_{ijkl}E_jE_kE_l$

Solution 2.2.2

1. $u_iv_i : 3^0 = 1$
2. $a_{ij}b_{ij} : 3^0 = 1$
3. $d_{ijk}E_k : 3^2 = 9$
4. $\epsilon_{ijk}\sigma_{ij} : 3^1 = 3$
5. $S_{ijkl}\sigma_{kl} : 3^2 = 9$
6. $\frac{1}{2}C_{ijkl}e_{ij}e_{kl} : 3^0 = 1$
7. $\chi_{ijkl}E_jE_kE_l : 3^1 = 3$

Exercise 2.2.3

Subscripts can come anywhere in an expression. Fill the number of components for each of the following quantities.

1. $\frac{\partial u_i}{\partial x_i}$
2. $\frac{\partial \sigma_{ij}}{\partial x_j}$
3. $\frac{\partial u_i}{\partial x_j}$
4. $\rho_{mn}J_n + \alpha_{mn}\frac{\partial T}{\partial Z_n}$

Solution 2.2.3

1. $\frac{\partial u_i}{\partial x_i} : 3^0 = 1$
2. $\frac{\partial \sigma_{ij}}{\partial x_j} : 3^1 = 3$
3. $\frac{\partial u_i}{\partial x_j} : 3^2 = 9$
4. $\rho_{mn}J_n + \alpha_{mn}\frac{\partial T}{\partial Z_n} : 3^1 = 3$

Exercise 2.2.4

Subscripts after a comma indicate differentiation.

$$u_{i,i} = \frac{\partial u_i}{\partial x_i} = \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3}$$

1. $\sigma_{ij,j}$

2. $u_{i,j}$

Solution 2.2.4

1. $\sigma_{ij,j} : \frac{\partial \sigma_{i1}}{\partial x_1} + \frac{\partial \sigma_{i2}}{\partial x_2} + \frac{\partial \sigma_{i3}}{\partial x_3}$
2. $u_{i,j} : \text{A matrix of 9 elements}$

2.2 Understand (Tensors). *Validate an expression to be conforming to the rules of subscript notation*

Exercise 2.2.5

Free subscripts on either sides of the '=' sign should match. In an expression, each term shall have the same free subscript. Identify the errors in the following expressions. [LO 2.2]

1. $a_i = \frac{\partial u_i}{\partial x_i} + b_j$
2. $J_i = -k_{ij} \frac{\partial T}{\partial x_j} + q_j$
3. $\frac{\partial u_i}{\partial t} + u_j \frac{\partial u_i}{\partial x_j} = -\frac{\partial p}{\partial x_i} + F_j$

Solution 2.2.5

Corrected expressions are given as follows:

1. $a_{ij} = \frac{\partial u_i}{\partial x_j} + b_{ij}$
2. $J_i = -k_{ij} \frac{\partial T}{\partial x_j} + q_i$
3. $\frac{\partial u_i}{\partial t} + u_j \frac{\partial u_i}{\partial x_j} = -\frac{\partial p}{\partial x_i} + F_i$

2.3 Nabla

Nabla or Del or Grad

$$\vec{\nabla} = \frac{\partial}{\partial x_1} \hat{x}_1 + \frac{\partial}{\partial x_2} \hat{x}_2 + \frac{\partial}{\partial x_3} \hat{x}_3 = \nabla_i$$

Exercise 2.3.6

Write the following using the above convention.

1. Gradient of a scalar function ϕ
2. Divergence of a vector $\vec{u}$

Solution 2.3.6

1. Gradient of a scalar function ϕ is $\nabla_i \phi$
2. Divergence of a vector $\vec{u}$ is $\nabla_i u_i \delta_{ij} = \nabla_i u_i$

2.4 Kronecker Delta

2.3 Apply (Preliminaries). *Apply the definition of Kronecker delta to simplify expressions in subscript notation*

Definition of Kronecker delta which is used to represent an isotropic tensor of order 2 is :

$$\delta_{ij} = \begin{cases} 1 & \text{if } i = j \\ 0 & \text{if } i \neq j \end{cases}$$

$$\delta_{ij} = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{pmatrix}$$

- Trace of a matrix a

$$\text{Tr}(a) = a_{ij} \delta_{ij} = a_{ii} = a_{11} + a_{22} + a_{33}$$

$$\boxed{\text{Tr}(a) = a_{ii}}$$

- Trace of δ_{ij} is $\delta_{ii} = 3$.
- δ_{ij} is used to simplify expressions involving dummy indices. Consider $b_{ik} = a_{ij} \delta_{jk}$ Expand the expression for a given i, k and convince yourself that

$$\boxed{a_{ik} \delta_{ij} = a_{jk}}$$

$$p_i \delta_{ij} = p_j$$

Exercise 2.4.7

Evaluate the following and comment.

1. $a_i b_j \delta_{ij}$
2. $a_i b_i$
3. $c_{ij} \delta_{ij}$
4. $\delta_{ij} \delta_{ij}$

Solution 2.4.7

1. $a_i b_j \delta_{ij} = a_1 b_1 + a_2 b_2 + a_3 b_3$
2. $a_i b_i = a_1 b_1 + a_2 b_2 + a_3 b_3$
3. $c_{ij} \delta_{ij} = c_{11} + c_{22} + c_{33}$
4. $\delta_{ij} \delta_{ij} = 3$

Exercise 2.4.8

From the above expressions, can you discover what the Kronecker delta would do to one of the matching indices?

Solution 2.4.8

Identify a term that is summed with Kronecker delta over one of the indices. Replace that index in the term with the free index of Kronecker delta. See for example:

$$a_{ik} \delta_{ij} = a_{jk}$$

2.4 Apply (Preliminaries). *Apply the definition of Levi-Civita symbol to simplify expressions in subscript notation*

2.5 Levi-Civita Symbol

Levi-Civita symbol is also called as permutation matrix or alternator.

Definition:

$$\epsilon_{ijk} = \begin{cases} 1 & \text{if } i, j, k \text{ appear cyclic} \\ -1 & \text{if } i, j, k \text{ do not appear cyclic} \\ 0 & \text{if } i = j \text{ or } j = k \text{ or } k = i \end{cases}$$

$$\begin{aligned} \epsilon_{123} &= \epsilon_{231} = \epsilon_{312} = 1 \\ \epsilon_{132} &= \epsilon_{213} = \epsilon_{321} = -1 \\ \epsilon_{111} &= \epsilon_{112} = \epsilon_{211} = \epsilon_{121} = \epsilon_{113} = \epsilon_{311} = \epsilon_{131} = 0 \\ \epsilon_{222} &= \epsilon_{221} = \epsilon_{122} = \epsilon_{212} = \epsilon_{223} = \epsilon_{322} = \epsilon_{232} = 0 \\ \epsilon_{333} &= \epsilon_{331} = \epsilon_{133} = \epsilon_{313} = \epsilon_{332} = \epsilon_{233} = \epsilon_{323} = 0 \end{aligned}$$

One can also write the permutation matrix as follows:

$$\epsilon_{ijk} = \frac{(i-j)(j-k)(k-i)}{2}$$

Permutation matrix will help in writing expressions involving a cross product in a simplified manner.

One can write ϵ_{ijk} also in terms of a triple product as follows:

$$\epsilon_{ijk} = [\hat{x}_i, \hat{x}_j, \hat{x}_k]$$

Exercise 2.5.9

What is the value of $\epsilon_{ijk}\epsilon_{ijk}$?

Solution 2.5.9

6

Exercise 2.5.10

Expand the following expressions separately and indicate the number of components and comment on the quantity. (1) $\epsilon_{ijk}u_jv_k$ (2) $\epsilon_{ijk}u_{k,j}$ (3) $\epsilon_{ijk}a_{1i}a_{2j}a_{3k}$

Solution 2.5.10

(1) 1 free index, 3 components, vector, the quantity is cross product of $\vec{u}$ and $\vec{v}$ (2) 1 free index, 3 components, vector, the quantity is curl of $\vec{u}$ (3) 0 free index, 1 component, scalar, the quantity is determinant of matrix $[a]$

2.5 Apply (Preliminaries). *Convert an expression in vectorial notation to subscript notation*

Utility of permutation matrix:

Exercise 2.5.11

If you have discovered the utility of ϵ_{ijk} to write cross products, then write the following expressions in their equivalent subscript notation. (1) $\vec{c} = \vec{a} \times \vec{b}$ (2) $\vec{c} = \vec{\nabla} \times \vec{a}$ (3) $\vec{c} \cdot (\vec{\nabla} \times \vec{a})$ (4) $\vec{c} \times (\vec{\nabla} \times \vec{a})$

Solution 2.5.11

(1) Choose i as free index and write the expression as $c_i = \epsilon_{ijk}a_jb_k$ (2) Similar to above, $c_i = \epsilon_{ijk}\nabla_ja_k$ (3) $c_i\epsilon_{ijk}\nabla_ja_k$ (4) Choose the $ijklm$ the two sets of indices in cyclic manner. $\epsilon_{lmi}c_m\epsilon_{ijk}\nabla_ja_k$

Discuss with your neighbour and answer the following.

1. In what kind of vectorial expressions do you need to know how to simplify terms where the permutation matrix appears twice.
2. Within a term written using subscript notation, is the sequence of the terms important? If no - why? If yes - in what situations.

- Curl :

$$\vec{p} = \vec{\nabla} \times \vec{u}$$

$$p_i = \epsilon_{ijk}\nabla_ju_k = \epsilon_{ijk}u_{k,j} = \epsilon_{ijk}\frac{\partial u_k}{\partial x_j}$$

$$\boxed{\text{Curl}(u) = \epsilon_{ijk}\frac{\partial u_k}{\partial x_j}}$$

- Cross Product :

$$\vec{p} = \vec{u} \times \vec{v}$$

$$p_i = \epsilon_{ijk} u_j v_k$$

- Condition for coplanarity of three vectors a_i , b_j and c_k is:

$$\epsilon_{ijk} a_i b_j c_k = 0$$

- Determinant of a matrix a :

$$\text{Det}(a) = \|a_{ij}\|$$

$$\text{Det}(a) = \epsilon_{ijk} a_{1i} a_{2j} a_{3k}$$

2.6 Summary

1. Kronecker delta δ_{ij} and its application to dot product.
2. Levi-Civita symbol ϵ_{ijk} and its application to cross product.

Chapter 3

Application of subscript notation

3.1 Relation between Kronecker delta and Levi-Civita symbol

Exercise 3.1.12

Convince yourself about the relation between δ_{ij} and ϵ_{ijk} :

$$\epsilon_{ijk}\epsilon_{klm} = \delta_{il}\delta_{jm} - \delta_{im}\delta_{jl}$$

Solution 3.1.12

The values of RHS are

$$\begin{aligned} &+1 \text{ if } i = l \text{ and } j = m \text{ and } i \neq j \\ &-1 \text{ if } i = m \text{ and } j = l \text{ and } i \neq j \\ &0 \text{ for any other combination} \end{aligned} \tag{3.1}$$

For the first case, it turns out that $\epsilon_{ijk} = \epsilon_{lmk} = \epsilon_{klm}$ and the indices are non-repeating. Thus, whether they are cyclic or not, LHS is ϵ_{klm}^2 and is +1. For the second case, $\epsilon_{ijk} = \epsilon_{mlk} = -\epsilon_{klm}$ and the indices are non-repeating. Thus, LHS is $-\epsilon_{klm}^2$ and is -1.

As a continuation of this, one can also write:

$$\epsilon_{ijk}\epsilon_{ijm} = 2\delta_{km}$$

Based on the relations given above, the following vector identities can be derived using subscript notation.

3.2 Vector identities

3.1 Apply (Vector Identities). *Prove vector identities using subscript notation*

Exercise 3.2.13

Prove the following vector identity.

$$\vec{\nabla} \cdot (\vec{\nabla} \phi) = \nabla^2 \phi \quad (3.2)$$

Solution 3.2.13

$$\vec{\nabla} \cdot (\vec{\nabla} \phi) = \frac{\partial}{\partial x_i} \frac{\partial}{\partial x_i} \phi = \frac{\partial^2 \phi}{\partial x_i^2} = \nabla^2 \phi$$

Exercise 3.2.14

Prove the following vector identity.

$$\vec{\nabla} \times (\vec{\nabla} \phi) = 0 \quad (3.3)$$

Solution 3.2.14

$$p_i = \vec{\nabla} \times (\vec{\nabla} \phi) = \epsilon_{ijk} \frac{\partial}{\partial x_j} \frac{\partial \phi}{\partial x_k} = \epsilon_{ijk} \frac{\partial^2 \phi}{\partial x_j \partial x_k}$$

For each term with the index i , there are two non zero terms on the RHS to be summed up. While the order of differentiation is immaterial, ϵ_{ijk} is asymmetric about the indices j, k . Hence the RHS will vanish.

Take for example,

$$p_1 = \epsilon_{1jk} \frac{\partial^2 \phi}{\partial x_j \partial x_k} = \epsilon_{123} \frac{\partial^2 \phi}{\partial x_2 \partial x_3} + \epsilon_{132} \frac{\partial^2 \phi}{\partial x_3 \partial x_2} = (\epsilon_{123} + \epsilon_{132}) \frac{\partial^2 \phi}{\partial x_2 \partial x_3} = 0$$

Similarly the other terms will also vanish.

Exercise 3.2.15

(Exercise 2.23.1 of [Aris, 1962]) Show how to find the vector which lies in the intersection of the plane of $\vec{a}$ and $\vec{b}$ with the plane of $\vec{c}$ and $\vec{d}$.

Solution 3.2.15

Look at the solution for 2.23.1 of Aris here.

Exercise 3.2.16

Convince yourself that the following relations are valid. Condition for coplanarity of three vectors a_i , b_j and c_k is:

$$\epsilon_{ijk} a_i b_j c_k = 0$$

Solution 3.2.16

The term given is the determinant of a square matrix where each row contains the elements of each of the three vectors. However, the condition for coplanarity of three vectors is that one of them is a linear combination of the other two. But we know that when one row of a square matrix is a linear combination of the other two then the determinant is zero. Hence proved.

The following involve only gradient and inner product operations.

Exercise 3.2.17

Prove the following using subscript notation.

$$\vec{\nabla}(\phi\psi) = \phi\vec{\nabla}\psi + \psi\vec{\nabla}\phi$$

Solution 3.2.17

$$\vec{\nabla}(\phi\psi) = \phi\vec{\nabla}\psi + \psi\vec{\nabla}\phi$$

$$\vec{\nabla}(\phi\psi) = \frac{\partial}{\partial x_i}(\phi\psi)$$

Differentiate by parts

$$= \psi \frac{\partial}{\partial x_i} \phi + \phi \frac{\partial}{\partial x_i} \psi$$

$$= \psi \vec{\nabla} \phi + \phi \vec{\nabla} \psi$$

Exercise 3.2.18

Prove the following using subscript notation.

$$\vec{\nabla} \cdot (\vec{\nabla} \phi) = \nabla^2 \phi$$

Solution 3.2.18

$$\vec{\nabla} \cdot (\vec{\nabla} \phi) = \nabla^2 \phi$$

$$\vec{\nabla} \cdot (\vec{\nabla} \phi) = \frac{\partial}{\partial x_i} \frac{\partial}{\partial x_i} \phi = \frac{\partial^2 \phi}{\partial x_i^2} = \nabla^2 \phi$$

Exercise 3.2.19

Prove the following using subscript notation.

$$\vec{\nabla} \cdot (\phi \vec{f}) = \phi(\nabla \cdot \vec{f}) + \vec{f} \cdot (\vec{\nabla} \phi)$$

Solution 3.2.19

$$\vec{\nabla} \cdot (\phi \vec{f}) = \frac{\partial}{\partial x_i} (\phi f_i)$$

Differentiate by parts, element by element

$$\begin{aligned} &= \phi \frac{\partial}{\partial x_i} f_i + f_i \frac{\partial}{\partial x_i} \phi \\ &= \phi (\vec{\nabla} \cdot \vec{f}) + \vec{f} \cdot (\vec{\nabla} \phi) \end{aligned}$$

The following identity introduces the curl operation.

Exercise 3.2.20

Prove the following using subscript notation

$$\vec{\nabla} \times (\phi \vec{f}) = \nabla \phi \times \vec{f} + \phi (\nabla \times \vec{f})$$

Solution 3.2.20

$$\vec{\nabla} \times (\phi \vec{f}) = \nabla \phi \times \vec{f} + \phi (\nabla \times \vec{f})$$

$$\vec{\nabla} \times (\phi \vec{f}) = \epsilon_{ijk} \frac{\partial}{\partial x_j} \phi f_k$$

Differentiate by parts

$$\begin{aligned} &= \epsilon_{ijk} \left[f_k \frac{\partial}{\partial x_j} \phi + \phi \frac{\partial}{\partial x_j} f_k \right] \\ &= \epsilon_{ijk} \frac{\partial \phi}{\partial x_j} f_k + \phi \epsilon_{ijk} \frac{\partial f_k}{\partial x_j} \\ &= \vec{\nabla} \phi \times \vec{f} + \phi \vec{\nabla} \times \vec{f} \end{aligned}$$

Exercise 3.2.21

Prove the following using subscript notation

$$\vec{\nabla} \cdot (\vec{\nabla} \times \vec{f}) = 0$$

Solution 3.2.21

$$\begin{aligned} \vec{\nabla} \cdot \vec{\nabla} \times \vec{f} &= \frac{\partial}{\partial x_i} \epsilon_{ijk} \frac{\partial}{\partial x_j} f_k \\ &= \epsilon_{ijk} \frac{\partial}{\partial x_i} \frac{\partial}{\partial x_j} f_k \end{aligned}$$

In this expression, ϵ_{ijk} is not symmetric over the indices i and j .

But $\frac{\partial}{\partial x_i} \frac{\partial}{\partial x_j}$ is symmetric over the indices i and j since the order of differentiation should not matter for well behaved functions. Thus, when summed over these indices, the result must be zero.

The following identity involves cross product and needs switching indexes to reduce index expressions to more intuitive form.

Exercise 3.2.22

Prove the following using subscript notation.

$$\nabla \cdot (\vec{f} \times \vec{g}) = \vec{g} \cdot (\nabla \times \vec{f}) - \vec{f} \cdot (\nabla \times \vec{g})$$

Solution 3.2.22

$$\vec{\nabla} \cdot (\vec{f} \times \vec{g}) = \frac{\partial}{\partial x_i} \epsilon_{ijk} f_j g_k = \epsilon_{ijk} \frac{\partial}{\partial x_i} (f_j g_k)$$

Differentiate by parts

$$\begin{aligned} &= \epsilon_{ijk} \left[f_j \frac{\partial g_k}{\partial x_i} + g_k \frac{\partial f_j}{\partial x_i} \right] = f_j \epsilon_{ijk} \frac{\partial g_k}{\partial x_i} + g_k \epsilon_{ijk} \frac{\partial f_j}{\partial x_i} \\ &= f_j \epsilon_{jki} \frac{\partial}{\partial x_i} g_k + g_k \epsilon_{kij} \frac{\partial}{\partial x_i} f_j \\ &= -f_j \epsilon_{jik} \frac{\partial}{\partial x_i} g_k + g_k \epsilon_{kij} \frac{\partial f_j}{\partial x_i} \\ &= -\vec{f} \cdot (\nabla \times \vec{g}) + \vec{g} \cdot (\nabla \times \vec{f}) \end{aligned}$$

The following identity involves the cross product twice. Use the identity in the question 12 to convert two Levi-Civita tensors into Kronecker delta terms.

Exercise 3.2.23

Prove the following using subscript notation

$$\vec{\nabla}(\vec{\nabla} \cdot \vec{f}) = \vec{\nabla} \times (\vec{\nabla} \times \vec{f}) + \nabla^2 \vec{f}$$

Solution 3.2.23

We start with R.H.S.

$$\begin{aligned} \vec{\nabla} \times \vec{f} &= \epsilon_{ijk} \frac{\partial}{\partial x_j} f_k \\ \vec{\nabla} \times (\vec{\nabla} \times \vec{f}) &= \epsilon_{lmi} \frac{\partial}{\partial x_m} \epsilon_{ijk} \frac{\partial}{\partial x_j} f_k \\ &= \epsilon_{ijk} \epsilon_{lmi} \frac{\partial^2 f_k}{\partial x_m \partial x_j} \\ &= [\delta_{lj} \delta_{mk} - \delta_{lk} \delta_{mj}] \frac{\partial^2 f_k}{\partial x_m \partial x_j} \end{aligned}$$

$$\begin{aligned}
 &= [\delta_{lj}\delta_{mk} - \delta_{lk}\delta_{mj}] \frac{\partial^2 f_k}{\partial x_m \partial x_j} \\
 &= \delta_{lj}\delta_{mk} \frac{\partial^2 f_k}{\partial x_m \partial x_j} - \delta_{lk}\delta_{mj} \frac{\partial^2 f_k}{\partial x_m \partial x_j} \\
 &= \delta_{lj} \frac{\partial^2 f_m}{\partial x_m \partial x_j} - \delta_{mj} \frac{\partial^2 f_l}{\partial x_m \partial x_j} \\
 &= \frac{\partial^2 f_m}{\partial x_m \partial x_l} - \frac{\partial^2 f_l}{\partial x_m \partial x_m} = \frac{\partial}{\partial x_l} \frac{\partial f_m}{\partial x_m} - \frac{\partial^2 f_l}{\partial x_m \partial x_m} \\
 &= \vec{\nabla} \left(\vec{\nabla} \cdot \vec{f} \right) - \vec{\nabla}^2 \vec{f}
 \end{aligned}$$

Rearrange the terms to see that the identity has been proved.

Exercise 3.2.24

$$\nabla \times (\vec{f} \times \vec{g}) = \vec{f}(\nabla \cdot \vec{g}) - \vec{g}(\nabla \cdot \vec{f}) + (\vec{g} \cdot \nabla) \vec{f} - (\vec{f} \cdot \nabla) \vec{g}$$

Solution 3.2.24

$$\begin{aligned}
 \vec{f} \times \vec{g} &= \epsilon_{ijk} f_j g_k \\
 \vec{\nabla} \times (\vec{f} \times \vec{g}) &= \epsilon_{lmi} \frac{\partial}{\partial x_m} \epsilon_{ijk} f_j g_k \\
 &= \epsilon_{ijk} \epsilon_{lmi} \frac{\partial}{\partial x_m} (f_j g_k) \\
 &= [\delta_{lj}\delta_{mk} - \delta_{lk}\delta_{mj}] \left[f_j \frac{\partial g_k}{\partial x_m} + g_k \frac{\partial f_j}{\partial x_m} \right] \\
 &= [\delta_{lj}\delta_{mk} - \delta_{lk}\delta_{mj}] \left[f_j \frac{\partial g_k}{\partial x_m} + g_k \frac{\partial f_j}{\partial x_m} \right] \\
 &= \delta_{lj}\delta_{mk} f_j \frac{\partial g_k}{\partial x_m} - \delta_{lk}\delta_{mj} f_j \frac{\partial g_k}{\partial x_m} + \delta_{lj}\delta_{mk} g_k \frac{\partial f_j}{\partial x_m} - \delta_{lk}\delta_{mj} g_k \frac{\partial f_j}{\partial x_m} \\
 &= \delta_{mk} f_l \frac{\partial g_k}{\partial x_m} - \delta_{lk} f_m \frac{\partial g_k}{\partial x_m} + \delta_{mk} g_k \frac{\partial f_l}{\partial x_m} - \delta_{lk} g_k \frac{\partial f_m}{\partial x_m} \\
 &= f_l \frac{\partial g_m}{\partial x_m} - f_m \frac{\partial g_l}{\partial x_m} + g_m \frac{\partial f_l}{\partial x_m} - g_l \frac{\partial f_m}{\partial x_m} \\
 &= \vec{f} (\vec{\nabla} \cdot \vec{g}) - (\vec{f} \cdot \vec{\nabla}) \vec{g} + (\vec{g} \cdot \vec{\nabla}) \vec{f} - \vec{g} (\vec{\nabla} \cdot \vec{f})
 \end{aligned}$$

Exercise 3.2.25

$$\vec{\nabla} (\vec{f} \cdot \vec{g}) = \vec{f} \times (\vec{\nabla} \times \vec{g}) + \vec{g} \times (\vec{\nabla} \times \vec{f}) + (\vec{f} \cdot \vec{\nabla}) \vec{g} + (\vec{g} \cdot \vec{\nabla}) \vec{f}$$

Solution 3.2.25

We start from the R.H.S.

$$\vec{f} \times (\vec{\nabla} \times \vec{g}) = \epsilon_{lmi} f_m \epsilon_{ijk} \frac{\partial g_k}{\partial x_j}$$

$$\vec{g} \times (\vec{\nabla} \times \vec{f}) = \epsilon_{lmi} g_m \epsilon_{ijk} \frac{\partial f_k}{\partial x_j}$$

Thus,

$$\begin{aligned} \vec{f} \times (\vec{\nabla} \times \vec{g}) + \vec{g} \times (\vec{\nabla} \times \vec{f}) &= \epsilon_{lmi} f_m \epsilon_{ijk} \frac{\partial g_k}{\partial x_j} + \epsilon_{lmi} g_m \epsilon_{ijk} \frac{\partial f_k}{\partial x_j} \\ &= \epsilon_{ijk} \epsilon_{lmi} \left[f_m \frac{\partial g_k}{\partial x_j} + g_m \frac{\partial f_k}{\partial x_j} \right] \\ &= [\delta_{lj} \delta_{mk} - \delta_{lk} \delta_{mj}] \left[f_m \frac{\partial g_k}{\partial x_j} + g_m \frac{\partial f_k}{\partial x_j} \right] \\ &= \delta_{lj} \delta_{mk} f_m \frac{\partial g_k}{\partial x_j} - \delta_{lk} \delta_{mj} f_m \frac{\partial g_k}{\partial x_j} + \delta_{lj} \delta_{mk} g_m \frac{\partial f_k}{\partial x_j} - \delta_{lk} \delta_{mj} g_m \frac{\partial f_k}{\partial x_j} \\ &= f_k \frac{\partial g_k}{\partial x_l} - f_j \frac{\partial g_l}{\partial x_j} + g_k \frac{\partial f_k}{\partial x_l} - g_j \frac{\partial f_l}{\partial x_j} \\ &= f_k \frac{\partial g_k}{\partial x_l} + g_k \frac{\partial f_k}{\partial x_l} - f_j \frac{\partial g_l}{\partial x_j} - g_j \frac{\partial f_l}{\partial x_j} \\ &= \frac{\partial}{\partial x_l} (f_k g_k) - \left(f_j \frac{\partial}{\partial x_j} \right) g_l - \left(g_j \frac{\partial}{\partial x_j} \right) f_l \\ &= \vec{\nabla} (\vec{f} \cdot \vec{g}) - (\vec{f} \cdot \vec{\nabla}) \vec{g} - (\vec{g} \cdot \vec{\nabla}) \vec{f} \end{aligned}$$

Rearrange the terms to see that the identity has been proved.

Exercise 3.2.26

Prove the identity.

$$\frac{1}{2} \vec{\nabla} (\vec{f} \cdot \vec{f}) = \vec{f} \times \vec{\nabla} \times \vec{f} + (\vec{f} \cdot \vec{\nabla}) \vec{f}$$

Solution 3.2.26

Use the identity for $\nabla(\vec{f} \cdot \vec{g})$ and put $\vec{f} = \vec{g}$.

Exercise 3.2.27

$$(\vec{f} \times \vec{g}) \times \vec{h} = (\vec{f} \cdot \vec{h})\vec{g} - (\vec{g} \cdot \vec{h})\vec{f}$$

Solution 3.2.27

Using i as the free index:

$$\vec{f} \times \vec{g} = \epsilon_{ijk} f_j g_k$$

Using l as the free index:

$$(\vec{f} \times \vec{g}) \times \vec{h} = \epsilon_{lim} [\epsilon_{ijk} f_j g_k] h_m$$

Cycle the indexes and gather the permutation matrices:

$$= \epsilon_{ijk} \epsilon_{iml} f_j g_k h_m$$

$$= [\delta_{mj} \delta_{lk} - \delta_{mk} \delta_{jl}] f_j g_k h_m$$

$$= \delta_{mj} \delta_{lk} f_j g_k h_m - \delta_{mk} \delta_{jl} f_j g_k h_m$$

$$= f_j g_l h_j - f_l g_m h_m$$

$$= (\vec{f} \cdot \vec{h}) \vec{g} - (\vec{g} \cdot \vec{h}) \vec{f}$$

These identities involve two cross products involving vector fields.

Exercise 3.2.28

$$\vec{f} \times (\vec{g} \times \vec{h}) = (\vec{f} \cdot \vec{h}) \vec{g} - (\vec{f} \cdot \vec{g}) \vec{h}$$

Solution 3.2.28

Using i as the free index:

$$\vec{g} \times \vec{h} = \epsilon_{ijk} g_j h_k$$

Using l as the free index:

$$(\vec{f} \times \vec{g}) \times \vec{h} = \epsilon_{lmi} f_m [\epsilon_{ijk} g_j h_k]$$

Cycle the indices and gather the permutation matrices:

$$= \epsilon_{ijk} \epsilon_{ilm} f_m g_j h_k$$

$$\begin{aligned}
 &= [\delta_{jl}\delta_{mk} - \delta_{mj}\delta_{lk}] f_m g_j h_k \\
 &= \delta_{jl}\delta_{mk} f_m g_j h_k - \delta_{mj}\delta_{lk} f_m g_j h_k \\
 &= f_k g_l h_k - f_j g_j h_l \\
 &= (\vec{f} \cdot \vec{h}) \vec{g} - (\vec{f} \cdot \vec{g}) \vec{h}
 \end{aligned}$$

Exercise 3.2.29

$$\vec{f} \times (\vec{g} \times \vec{h}) + \vec{g} \times (\vec{h} \times \vec{f}) + \vec{h} \times (\vec{f} \times \vec{g}) = 0$$

Solution 3.2.29

Cycle the vectors in the above identity and prove.

These identities involve a number of terms to be consolidated.

Exercise 3.2.30

$$(\vec{f} \times \vec{g}) \cdot (\vec{f} \times \vec{g}) = |\vec{f}|^2 |\vec{g}|^2 - (\vec{f} \cdot \vec{g})^2$$

Solution 3.2.30

Choose i as the free index for each of the two terms.

Write first term using:

$$\vec{f} \times \vec{g} = \epsilon_{ijk} f_j g_k$$

Write second term using:

$$\vec{f} \times \vec{g} = \epsilon_{ilm} f_l g_m$$

Dot the two quantities over the index i to give:

$$\begin{aligned}
 (\vec{f} \times \vec{g}) \cdot (\vec{f} \times \vec{g}) &= \epsilon_{ijk} f_j g_k \epsilon_{ilm} f_l g_m \\
 &= \epsilon_{ijk} \epsilon_{ilm} f_j g_k f_l g_m \\
 &= (\delta_{jl}\delta_{km} - \delta_{jm}\delta_{kl}) f_j g_k f_l g_m \\
 &= \delta_{jl}\delta_{km} f_j g_k f_l g_m - \delta_{jm}\delta_{kl} f_j g_k f_l g_m \\
 &= f_l f_l g_m g_m - f_m g_m f_l g_l
 \end{aligned}$$

$$= (\vec{f} \cdot \vec{f}) (\vec{g} \cdot \vec{g}) - (\vec{f} \cdot \vec{g})^2$$

Exercise 3.2.31

$$\vec{a} \times (\vec{b} \times \vec{c}) = \beta \vec{b} + \gamma \vec{c}$$

Solution 3.2.31

$$\vec{b} \times \vec{c} = \epsilon_{ijk} b_j c_k$$

Choose the cyclic indices as $ijklm$ to give two pairs of such indices namely ijk and lmi .

$$\vec{a} \times (\vec{b} \times \vec{c}) = \epsilon_{lmi} a_m \epsilon_{ijk} b_j c_k$$

The free index of each term in the above expression is l . Simplify further as follows:

$$= \epsilon_{lmi} \epsilon_{ijk} a_m b_j c_k$$

$$= (\delta_{lj} \delta_{mk} - \delta_{lk} \delta_{jm}) a_m b_j c_k$$

$$= \delta_{lj} \delta_{mk} a_m b_j c_k - \delta_{lk} \delta_{jm} a_m b_j c_k$$

$$= a_k b_l c_k - a_j b_j c_l$$

$$= \beta b_l + \gamma c_l$$

Where $\beta = \vec{a} \cdot \vec{c}$ and $\gamma = -\vec{b} \cdot \vec{a}$. This shows that the cross product $\vec{a} \times (\vec{b} \times \vec{c})$ lies in the plane containing the vectors $\vec{b}$ and $\vec{a}$.

Exercise 3.2.32

For any vector $\vec{a}$ and a unit vector $\vec{e}$, show the following:

$$\vec{a} = (\vec{a} \cdot \vec{e}) \vec{e} + \vec{e} \times (\vec{a} \times \vec{e})$$

Solution 3.2.32

$$\vec{e} \times (\vec{a} \times \vec{e}) = \epsilon_{lmi} e_m \epsilon_{ijk} a_j e_k$$

$$= (\delta_{lj} \delta_{mk} - \delta_{lk} \delta_{jm}) e_m a_j e_k$$

$$= \delta_{lj} \delta_{mk} e_m a_j e_k - \delta_{lk} \delta_{jm} e_m a_j e_k$$

$$= e_m a_l e_m - a_m e_l e_m$$

$$= \vec{a} (\vec{e} \cdot \vec{e}) - \vec{e} (\vec{a} \cdot \vec{e})$$

Since $\vec{e}$ is a unit vector, $\vec{e} \cdot \vec{e} = 1$.

This shows that any vector can be split in to two components, one along a unit vector and another perpendicular to that unit vector.

3.3 Summary

1. Kronecker delta can be used for inner (dot) products and to replace indices
2. Levi-Civita symbol can be used for cross products and to evaluate determinants

Chapter 4

Coordinate transformations

4.1 Apply (Coordinate transforms). *Determine components of a vector in a new coordinate system given the transformation matrix*

4.1 Rotation of coordinate axes




Figure 4.1: Orthogonal axes

Right-handed system:

$$\hat{x}_1 \cdot (\hat{x}_2 \times \hat{x}_3) = 1$$

$$\hat{x}_1 \cdot \hat{x}_1 = \hat{x}_2 \cdot \hat{x}_2 = \hat{x}_3 \cdot \hat{x}_3 = 1$$

$$\hat{x}_1 \cdot \hat{x}_2 = \hat{x}_1 \cdot \hat{x}_3 = \hat{x}_2 \cdot \hat{x}_3 = 0$$

If a coordinate system is rotated, how are the unit vectors of the two systems related?

An example of coordinate transformation

Consider rotating the coordinate system about $\hat{x}_3$ by an arbitrary angle θ .

New unit vectors in terms of old ones




Figure 4.2: Illustration of simple rotation of coordinate system

$$\begin{aligned}\hat{x}_1^* &= \cos \theta \hat{x}_1 + \sin \theta \hat{x}_2 + 0 \hat{x}_3 \\ \hat{x}_2^* &= -\sin \theta \hat{x}_1 + \cos \theta \hat{x}_2 + 0 \hat{x}_3 \\ \hat{x}_3^* &= 0 \hat{x}_1 + 0 \hat{x}_2 + \hat{x}_3\end{aligned}$$

or

$$\begin{bmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{bmatrix} = \begin{bmatrix} \cos \theta & \sin \theta & 0 \\ -\sin \theta & \cos \theta & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{bmatrix}$$

$$\begin{bmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{bmatrix} = \begin{bmatrix} T_{11} & T_{12} & T_{13} \\ T_{21} & T_{22} & T_{23} \\ T_{31} & T_{32} & T_{33} \end{bmatrix} \begin{bmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{bmatrix}$$

Where


$$T = \begin{bmatrix} \cos \theta & \sin \theta & 0 \\ -\sin \theta & \cos \theta & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

Using subscript notation,

$$\hat{x}_p^* = T_{pi} \hat{x}_i$$

Old unit vectors in terms of new ones

$$\begin{aligned}\hat{x}_1 &= \cos \theta \hat{x}_1^* + -\sin \theta \hat{x}_2^* + 0 \hat{x}_3^* \\ \hat{x}_2 &= \sin \theta \hat{x}_1^* + \cos \theta \hat{x}_2^* + 0 \hat{x}_3^* \\ \hat{x}_3 &= 0 \hat{x}_1^* + 0 \hat{x}_2^* + \hat{x}_3^*\end{aligned}$$


 Figure 4.3: Simple rotation about $\hat{x}_3$ axis

or

$$\begin{bmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{bmatrix} = \begin{bmatrix} \cos \theta & -\sin \theta & 0 \\ \sin \theta & \cos \theta & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{bmatrix}$$

Using subscript notation,

$$\hat{x}_i = T_{pi} \hat{x}_p^*$$

Watch out the sequence of indices

Transformation of old to new coordinate system:

$$\begin{aligned} \hat{x}_p^* &= T_{pi} \hat{x}_i \\ \begin{bmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{bmatrix} &= \begin{bmatrix} T_{11} & T_{12} & T_{13} \\ T_{21} & T_{22} & T_{23} \\ T_{31} & T_{32} & T_{33} \end{bmatrix} \begin{bmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{bmatrix} \end{aligned}$$

Transformation of new back to old coordinate system:

$$\begin{aligned} \hat{x}_i &= T_{pi} \hat{x}_p^* \\ \begin{bmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{bmatrix} &= \begin{bmatrix} T_{11} & T_{12} & T_{13} \\ T_{21} & T_{22} & T_{23} \\ T_{31} & T_{32} & T_{33} \end{bmatrix} \begin{bmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{bmatrix} \end{aligned}$$

Watch out the sequence of indices !

For old to new coordinate system, the convention is:

$$\hat{x}_p^* = T_{pi} \hat{x}_i$$




Figure 4.4: New unit vector $\hat{x}_1$ in terms of old ones after coordinate rotation

Where, p is the index for new- and i is the index for old- coordinate systems.

Alternate definition of T_{pi}

Consider the transformation from old to new coordinate system:

$$\hat{x}_p^* = T_{pi} \hat{x}_i$$

Expand for $p = 1$:

$$\hat{x}_1^* = T_{1i} \hat{x}_i = T_{11} \hat{x}_1 + T_{12} \hat{x}_2 + T_{13} \hat{x}_3$$

This means one can also write the elements of T_{pi} as

$$T_{11} = \frac{\partial \hat{x}_1^*}{\partial \hat{x}_1}$$

$$T_{12} = \frac{\partial \hat{x}_1^*}{\partial \hat{x}_2}$$

$$T_{13} = \frac{\partial \hat{x}_1^*}{\partial \hat{x}_3}$$

$$T_{pi} = \frac{\partial \hat{x}_p^*}{\partial \hat{x}_i}$$

Consider the transformation from new to old coordinate system:

$$\hat{x}_i = T_{pi} \hat{x}_p^*$$

Expand for $i = 1$:

$$\hat{x}_1 = T_{p1} \hat{x}_p^* = T_{11} \hat{x}_1^* + T_{21} \hat{x}_2^* + T_{31} \hat{x}_3^*$$

Write the elements of T_{pi} as

$$T_{11} = \frac{\partial \hat{x}_1}{\partial \hat{x}_1^*}$$




Figure 4.5: New unit vector $\hat{x}_2$ in terms of old ones after coordinate rotation

$$T_{21} = \frac{\partial \hat{x}_1}{\partial \hat{x}_2^*}$$

$$T_{31} = \frac{\partial \hat{x}_1}{\partial \hat{x}_3^*}$$

$$T_{pi} = \frac{\partial \hat{x}_i}{\partial \hat{x}_p^*}$$

$$T_{pi} = \frac{\partial \hat{x}_p^*}{\partial \hat{x}_i} = \frac{\partial \hat{x}_i}{\partial \hat{x}_p^*}$$

Yet another definition of T_{pi}

Consider the transformation from old to new coordinate system:

$$\hat{x}_p^* = T_{pi} \hat{x}_i$$

Expand for $p = 1$:

$$\hat{x}_1^* = T_{1i} \hat{x}_i = T_{11} \hat{x}_1 + T_{12} \hat{x}_2 + T_{13} \hat{x}_3$$

This means one can also write the elements of T_{pi} as

$$\hat{x}_1^* \cdot \hat{x}_1 = T_{11}$$

$$\hat{x}_1^* \cdot \hat{x}_2 = T_{12}$$

$$\hat{x}_1^* \cdot \hat{x}_3 = T_{13}$$

$$T_{pi} = \hat{x}_p^* \cdot \hat{x}_i$$

Properties of T_{pi} using orthogonality

$$\hat{x}_1^* \cdot \hat{x}_1^* = 1$$




Figure 4.6: Old unit vector $\hat{x}_1$ in terms of new ones after coordinate rotation

$$\begin{aligned}\hat{x}_1^* &= T_{1i}\hat{x}_i \\ T_{1i}T_{1i} &= 1 = \delta_{11}\end{aligned}$$

$$\begin{aligned}\hat{x}_1^* \cdot \hat{x}_2^* &= 0 \\ \hat{x}_1^* &= T_{1i}\hat{x}_i \\ \hat{x}_2^* &= T_{2i}\hat{x}_i \\ T_{1i}T_{2i} &= 0 = \delta_{12}\end{aligned}$$

$$\begin{aligned}\hat{x}_1^* \cdot \hat{x}_3^* &= 0 \\ \hat{x}_1^* &= T_{1i}\hat{x}_i \\ \hat{x}_3^* &= T_{3i}\hat{x}_i \\ T_{1i}T_{3i} &= 0 = \delta_{13}\end{aligned}$$

Generalizing,

$$T_{mi}T_{ni} = \delta_{mn}$$

Similarly, using the orthogonality of the old coordinate system, we can get

$$T_{im}T_{in} = \delta_{mn}$$

Properties of transformation matrix

- T_{pi} is determined by the rotation of the coordinate system
- Determinant of T_{pi} is 1




Figure 4.7: Old unit vector $\hat{x}_2$ in terms of new ones after coordinate rotation

- Inverse of T_{pi} is its transpose, namely T_{ip}
- Orthogonality leads to $T_{mi}T_{ni} = \delta_{mn}$ and $T_{im}T_{in} = \delta_{mn}$

Components of a vector across coordinate rotation




Figure 4.8: Components of a vector across coordinate rotation

Components of a vector across coordinate rotation

$$\begin{aligned}
 \vec{u} &= u_1 x_1 + u_2 x_2 + u_3 x_3 \\
 &= u_1 (\cos \theta \hat{x}_1^* + \sin \theta \hat{x}_2^* + 0 \hat{x}_3^*) + \\
 &+ u_2 (-\sin \theta \hat{x}_1^* + \cos \theta \hat{x}_2^* + 0 \hat{x}_3^*) +
 \end{aligned}$$

$$\begin{aligned}
& +u_3 (0 \hat{x}_1^* + 0 \hat{x}_2^* + \hat{x}_3^*) \\
& = (u_1 \cos \theta + u_2 \sin \theta) \hat{x}_2^* + (-u_1 \sin \theta + u_2 \cos \theta) \hat{x}_2^* + u_3 \hat{x}_3^* \\
& = u_1^* \hat{x}_1^* + u_2^* \hat{x}_2^* + u_3^* \hat{x}_3^*
\end{aligned}$$

Components of a vector across coordinate rotation

$$\begin{bmatrix} u_1^* \\ u_2^* \\ u_3^* \end{bmatrix} = \begin{bmatrix} \cos \theta & \sin \theta & 0 \\ -\sin \theta & \cos \theta & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} u_1 \\ u_2 \\ u_3 \end{bmatrix}$$

or

$$u_p^* = T_{pi} u_i$$

This equation preserves the nature of $\vec{u}$ across coordinate transforms and is thus a way to **define** a vector.

Definition of a vector

A bunch of three numbers u_i that follow the following relation across a coordinate transformation are components of a vector $\vec{u}$

Definition

$$u_p^* = T_{pi} u_i$$

A vector field is a vector that is a function of a location.

Examples Velocity field $u(x, y, z)$, Gradient of thermal field $\vec{\nabla} T(r, \theta, z)$, Gradient of composition $\vec{\nabla} C_A(x, y, z)$, Electric field $E(x, y, z,)$ etc.,

Definition of a scalar

Scalar is a quantity which is invariant (does not change) across a coordinate transformation.

Examples Temperature T , Energy G , density ρ etc.,

A scalar field is a scalar that is a function of location.

Examples Thermal field $T(x, y, z)$, Density field $\rho(r, \theta, z)$, Phase field $\phi(x, y, z,)$ etc.,

Value of a scalar field at a location should not change if the coordinates chosen to represent the location change.

Cartesian co-ordinate system $\hat{x}_i$ is used. Consider the following co-ordinate transformation where the xy plane is rotated about z-axis clockwise by an angle θ .

The new axes (starred) are given in terms of the old axes (unstarred) by the following relations:

$$\begin{aligned}
\hat{x}_1^* &= \hat{x}_1 \cos \theta + \hat{x}_2 \sin \theta \\
\hat{x}_2^* &= -\hat{x}_1 \sin \theta + \hat{x}_2 \cos \theta \\
\hat{x}_3^* &= \hat{x}_3
\end{aligned} \tag{4.1}$$

or

$$\begin{aligned}\hat{x}_1^* &= T_{11}\hat{x}_1 + T_{12}\hat{x}_2 + T_{13}\hat{x}_3 \\ \hat{x}_2^* &= T_{21}\hat{x}_1 + T_{22}\hat{x}_2 + T_{23}\hat{x}_3 \\ \hat{x}_3^* &= T_{31}\hat{x}_1 + T_{32}\hat{x}_2 + T_{33}\hat{x}_3\end{aligned}\quad (4.2)$$

$$\begin{pmatrix} \hat{x}_1^* \\ \hat{x}_2^* \\ \hat{x}_3^* \end{pmatrix} = \begin{pmatrix} \cos\theta & \sin\theta & 0 \\ -\sin\theta & \cos\theta & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} \hat{x}_1 \\ \hat{x}_2 \\ \hat{x}_3 \end{pmatrix}\quad (4.3)$$

or

$$\boxed{\hat{x}_p^* = T_{pi}\hat{x}_i}\quad (4.4)$$

The transformation matrix T_{pi} used in the above expression is by the convention that first index represents the row and the second index, the column. In one of the reference texts, viz., Aris' book [Aris, 1962], equation (2.11.1) shows that this convention is reversed. As a result the indices appear swapped in the definitions. This use of different convention is clear also from equation (A.6.4) in the same book.

When we express x_i^* in terms of x_i , the **transformation matrix** can be written as:

$$T_{pi} = \frac{\partial \hat{x}_p^*}{\partial \hat{x}_i} = \begin{pmatrix} \frac{\partial \hat{x}_1^*}{\partial \hat{x}_1} & \frac{\partial \hat{x}_1^*}{\partial \hat{x}_2} & \frac{\partial \hat{x}_1^*}{\partial \hat{x}_3} \\ \frac{\partial \hat{x}_2^*}{\partial \hat{x}_1} & \frac{\partial \hat{x}_2^*}{\partial \hat{x}_2} & \frac{\partial \hat{x}_2^*}{\partial \hat{x}_3} \\ \frac{\partial \hat{x}_3^*}{\partial \hat{x}_1} & \frac{\partial \hat{x}_3^*}{\partial \hat{x}_2} & \frac{\partial \hat{x}_3^*}{\partial \hat{x}_3} \end{pmatrix}\quad (4.5)$$

We have chosen cartesian co-ordinate systems which have the following properties of *orthogonality* :

$$\begin{aligned}\hat{x}_1^* \cdot \hat{x}_1^* &= 1 & \hat{x}_2^* \cdot \hat{x}_3^* &= 0 & \hat{x}_3^* \cdot \hat{x}_2^* &= 0 \\ \hat{x}_2^* \cdot \hat{x}_2^* &= 1 & \hat{x}_3^* \cdot \hat{x}_1^* &= 0 & \hat{x}_1^* \cdot \hat{x}_3^* &= 0 \\ \hat{x}_3^* \cdot \hat{x}_3^* &= 1 & \hat{x}_1^* \cdot \hat{x}_2^* &= 0 & \hat{x}_3^* \cdot \hat{x}_1^* &= 0\end{aligned}\quad (4.6)$$

Expressing $\hat{x}^*$ in terms of $\hat{x}$ and using equations 4.2 and 4.6, we get:

$$\begin{aligned}T_{11}T_{12} + T_{21}T_{22} + T_{31}T_{32} &= 0 \\ T_{12}T_{13} + T_{22}T_{23} + T_{32}T_{33} &= 0 \\ T_{13}T_{11} + T_{23}T_{21} + T_{33}T_{31} &= 0 \\ T_{11}T_{11} + T_{12}T_{12} + T_{13}T_{13} &= 1 \\ T_{21}T_{21} + T_{22}T_{22} + T_{23}T_{23} &= 1 \\ T_{31}T_{31} + T_{32}T_{32} + T_{33}T_{33} &= 1\end{aligned}\quad (4.7)$$

or

$$\boxed{T_{ij}T_{ik} = \delta_{jk}}\quad (4.8)$$

Rotating the co-ordinate system back...

Similarly, we can express $\hat{x}$ in terms of $\hat{x}^*$. Inverse transformation relation is given using the transpose of the transformation matrix as follows. Transpose of a matrix is nothing but the

same matrix with the indices swapped around.

$$\hat{x}_i = D_{ip}\hat{x}_p^*$$

The co-ordinate transformation matrix D for new to old system is related to the matrix for old to new the following manner.

$$D_{ip} = T_{ip}^{-1} = T_{ip}^T = T_{pi}$$

$$\hat{x}_i = D_{ip}\hat{x}_p^* = T_{pi}\hat{x}_p^*$$

$$\boxed{\hat{x}_i = T_{pi}\hat{x}_p^*} \quad (4.9)$$

Note: Compare equations 4.4 and 4.9 and notice which of the indices is being repeated in the RHS.

Exploiting the orthogonality of the old co-ordinate system:

$$\begin{aligned} \hat{x}_1 \cdot \hat{x}_1 &= 1 & \hat{x}_2 \cdot \hat{x}_3 &= 0 & \hat{x}_3 \cdot \hat{x}_2 &= 0 \\ \hat{x}_2 \cdot \hat{x}_2 &= 1 & \hat{x}_3 \cdot \hat{x}_1 &= 0 & \hat{x}_1 \cdot \hat{x}_3 &= 0 \\ \hat{x}_3 \cdot \hat{x}_3 &= 1 & \hat{x}_1 \cdot \hat{x}_2 &= 0 & \hat{x}_2 \cdot \hat{x}_3 &= 0 \end{aligned} \quad (4.10)$$

$$\boxed{T_{ji}T_{ki} = \delta_{jk}} \quad (4.11)$$

4.2 Scaffold to determine transformation matrix

1. For a rotation of a coordinate system about $\hat{x}_3$ by 90 degrees, anti-clockwise, express the unit vectors of the new coordinate system in terms of those of the old coordinate system. Write down how the transformation matrix would look like.
2. For a rotation of a coordinate system about $\hat{x}_3$ by 90 degrees, clockwise, write down how the transformation matrix would look like.
3. Write the unit vectors of the new coordinate system $\hat{x}_i^*$ in terms of T_{ij} and unit vectors of the old coordinate system $\hat{x}_i$. Use the orthogonality properties of the unit vectors in the new coordinate system and determine what values the expression $T_{ij}T_{ik}$ would take.
4. If the transformation matrix for coordinate system rotation from $\hat{x}_i$ (old) to $\hat{x}_p^*$ (new) is T_{pi} then convince yourself that the transformation matrix for rotating the new coordinate system back to the old one is the transpose of T_{pi} .
5. Write the unit vectors of the old coordinate system $\hat{x}_i$ in terms of T_{ij} and unit vectors of the new coordinate system $\hat{x}_p^*$. Use the orthogonality properties of the unit vectors in the new coordinate system and determine what values the expression such as $T_{ji}T_{ki}$ would take.
6. Based on the answers to the above questions, generalize a rule when two terms of

type T_{ij} were to come together in an expression that involves summation over any index.

4.3 Rodrigues rotation formula

4.2 Apply (Coordinate transforms). *Determine components of a transformation matrix given the axis and angle of rotation of a rectangular coordinate system*

The transformation matrix for rotation of a coordinate system about an arbitrary axis given by the unit vector $\hat{n}$ by an arbitrary angle θ is given by:

$$R_{ij} = \cos \theta \delta_{ij} + (1 - \cos \theta) n_i n_j - \sin \theta \epsilon_{ijk} n_k \quad (4.12)$$

$$\hat{n} = n_i \hat{i} + n_j \hat{j} + n_k \hat{k} \quad (4.13)$$

$$n_i^2 + n_j^2 + n_k^2 = 1 \quad (4.14)$$

The transformation matrix when expanded looks like the following.

$$R_{ij} = \begin{bmatrix} \cos \theta + n_1^2 (1 - \cos \theta) & n_1 n_2 (1 - \cos \theta) - n_3 \sin \theta & n_1 n_3 (1 - \cos \theta) + n_2 \sin \theta \\ n_1 n_2 (1 - \cos \theta) + n_3 \sin \theta & \cos \theta + n_2^2 (1 - \cos \theta) & n_2 n_3 (1 - \cos \theta) - n_1 \sin \theta \\ n_1 n_3 (1 - \cos \theta) - n_2 \sin \theta & n_2 n_3 (1 - \cos \theta) + n_1 \sin \theta & \cos \theta + n_3^2 (1 - \cos \theta) \end{bmatrix} \quad (4.15)$$

One can substitute the values of n_i for the unit vector $\hat{n}$ about which a rotation is being made, along with the value for θ for the angle of rotation and obtain the components of the transformation matrix R_{ij} readily.

Exercise 4.3.33

Show that the following matrix is a possible transformation matrix for coordinate rotation about a fixed point.

$$T_{ij} = \begin{bmatrix} \sin \theta \cos \phi & \sin \theta \sin \phi & \cos \theta \\ \cos \theta \cos \phi & \cos \theta \sin \phi & -\sin \theta \\ -\sin \phi & \cos \phi & 0 \end{bmatrix} \quad (4.16)$$

Solution 4.3.33

Show that the determinant is unity and that the orthogonality relations apply.

Exercise 4.3.34

If T_{ij} is a transformation matrix, show that the following relations apply.

$$T_{11} = T_{22}T_{33} - T_{23}T_{32}$$

$$T_{12} = T_{23}T_{31} - T_{21}T_{33}$$

$$T_{13} = T_{21}T_{32} - T_{22}T_{31}$$

Solution 4.3.34

Consider the terms in T_{ij} as direction cosines and compare the terms using the expression for determinant $\text{Det}(T_{ij}) = 1$

4.4 Summary

1. Orthogonality relations can be used to simplify terms while determining isotropy of a tensor

Chapter 5

Introduction to Cartesian Tensors

5.1 Cartesian Tensors

5.1 Remember (Tensor introduction). *Recall the definitions of tensors and their order.*

Many entities, such as those that have a physical meaning, are independent of the co-ordinate system we choose to represent them. If n is the dimension of the space we are concerned, the entities can be classified - according to the number of components (n^i) they would have - as **tensors** of order i .

In this notes, when we say tensor, we imply Cartesian tensor. We don't want to get into covariant, contravariant and such things at this stage.

5.1.1 Scalar

Scalar is a tensor of order zero. Only one value would suffice to describe it at any location. Scalars are invariant under co-ordinate transformations.

Definition: Scalar is an entity that remains invariant under all co-ordinate transformations.

Eg: Temperature T , Composition of - say - A species C_A , Pressure in a fluid p , Density ρ , etc.,

5.1.2 Vector

Vector is a tensor of order one. It requires as many values / components as the dimension of the space (which is three for most of us) ie., a set of three components in a 3D space.

Definition: Vector is an entity that transforms the following way under a co-ordinate transformation:

$$a_p^* = T_{pi} a_i \quad (5.1)$$

Eg: Velocity of fluid $\vec{u} = u_i$, Temperature gradient $\frac{\partial T}{\partial x_i}$, Composition gradient $\frac{\partial C_A}{\partial x_i}$, Displacement u_i , Electric Potential difference P , Electric Current J_i etc.,

5.1.3 Bisor

Bisor is a tensor of order two. All tensors of order 2 or more are called as just **tensors**. Specific names for tensors of order 2 and above are often considered old fashioned. A tensor of order 2 requires 9 components to describe it in general in 3D.

Definition: Tensor of order two is an entity that transforms the following way under a co-ordinate transformation:

$$a_{pq}^* = T_{pi}T_{qj}a_{ij} \quad (5.2)$$

Eg: Stress σ_{ij} , Strain e_{ij} , Electrical Conductivity σ_{ij} , Electrical Resistivity ρ_{ij} , Diffusivity D_{ij} , Thermal Conductivity k_{ij} , Magnetic Permeability μ_{ij} , Dielectric Permittivity ϵ_{ij} , Thermal Expansion Coefficient α_{ij} , Gyration Tensor g_{ij}

5.1.4 Trisor

Trisor is a tensor of order three. 27 components!

Definition: Tensor of order three is an entity that transforms the following way under a co-ordinate transformation:

$$a_{pqr}^* = T_{pi}T_{qj}T_{rk}a_{ijk} \quad (5.3)$$

Eg: Piezoelectric coefficient e_{ijk} ,

5.1.5 Tetrar

Tetrar is a tensor of order four. 81 components!

$$a_{pqrs}^* = T_{pi}T_{qj}T_{rk}T_{sl}a_{ijkl} \quad (5.4)$$

Eg: Elastic Modulus c_{ijkl}

5.1.6 Tensor

In general, a tensor is an entity that follows the following generalised rule for any co-ordinate transformation. The number of indices of a indicate the order of the tensor which is the same as the number of times T occurs in the expression.

$$a_{pqrst\dots}^* = T_{pi}T_{qj}T_{rk}T_{sl}T_{tm}\dots a_{ijklm\dots} \quad (5.5)$$

5.2 Understand (Tensor Introduction). *Validate a tensorial expression and identify the tensorial order of a parameter*

Here we must bring in some examples.

5.2 Operations on tensors

- Sum and difference of two tensors (of same order) is also a tensor. In the following example, if b_{ij} and c_{ij} are tensors, then a_{ij} and d_{ij} are also tensors.

$$a_{ij} = b_{ij} + c_{ij}$$

$$d_{ij} = b_{ij} - c_{ij}$$

- An outer product of a tensor of order m with a tensor of order n will give a tensor of order $m + n$. Outer product is also referred to as dyadic product.

$$a_{ijk} = b_{ij}c_k$$

- An inner product of a tensor of order m with a tensor of order n will give a tensor of order $|m - n|$.

$$a_i = b_{ijk}c_{jk}$$

- **Contraction theorem** : If $a_{ijkl..}$ is a tensor of order m , then the entity obtained by repeating any two subscripts is a tensor of order $m - 2$. Eg., if d_{ijkl} is a tensor of order 4, then by repeating two of its indices (say, third and fourth), the entity obtained a_{ij} is a tensor of order $4 - 2 = 2$.

$$a_{ij} = d_{ijkk}$$

A corollary to the above theorem is obtained when we take a tensor of order two and repeat the indices. i.e., Trace of a second order tensor a_{ii} is tensor of order zero or scalar or invariant across co-ordinate transformations.

- **Quotient law of tensors** : If there is an entity representable by (subscript notation as) a_{ij} relative to any cartesian co-ordinate system and if $a_{ij}b_i$ is a *vector* where b_i is *any arbitrary vector* then a_{ij} is a *tensor* of order two. Proof is given in section A.1.

Combining with the theorem on outer product, quotient law can be extended to tensors of higher order.

5.3 Types of tensors

5.3.1 Symmetric Tensor

a is a *symmetric* tensor if $a_{ij} = a_{ji}$

Theorem: For every second order symmetric tensor, there exists a co-ordinate system relative to which, the matrix of the components of the tensor is diagonal ¹. Proof is given in section A.2.

¹This theorem has important implications when applied to the stress tensor in the mechanical behaviour of materials. The diagonal terms are called principal stresses.

5.3.2 Anti-symmetric Tensor

a is a *skew-symmetric* or *anti-symmetric* tensor if $a_{ij} = -a_{ji}$

The vector formed by the components of an anti-symmetric tensor:

$$\omega_k = \begin{pmatrix} \omega_1 \\ \omega_2 \\ \omega_3 \end{pmatrix}$$

$$\Omega_{ij} = \begin{pmatrix} 0 & \omega_3 & -\omega_2 \\ -\omega_3 & 0 & \omega_1 \\ \omega_2 & -\omega_1 & 0 \end{pmatrix}$$

$$\omega_k = \frac{1}{2} \epsilon_{kij} \Omega_{ij}$$

Also,

$$\Omega_{ij} = \epsilon_{ijk} \omega_k$$

The two tensors ω_k and Ω_{ij} are called dual tensors.

Theorem: Every second order tensor is expressible as a sum of a symmetric tensor and an anti-symmetric tensor.

$$a_{ij} = \frac{1}{2} (a_{ij} + a_{ji}) + \frac{1}{2} (a_{ij} - a_{ji}) \quad (5.6)$$

5.3 Understand (Tensor introduction). *Prove an expression to be a tensor of appropriate order using the definition of a tensor*

Exercise 5.3.35

Prove that gradient of a continuous scalar function is a vector.

$$a_i = \nabla_i \phi = \frac{\partial \phi}{\partial x_i} \quad (5.7)$$

Solution 5.3.35

Exercise 5.3.36

Prove that the magnitude of a vector is invariant under co-ordinate transformations.

Solution 5.3.36

Exercise 5.3.37

Prove that δ_{ij} is (an isotropic) tensor of order two.

Solution 5.3.37

Exercise 5.3.38

Prove that if u_i and v_j are vectors, then the dyad $a_{ij} = u_i v_j$ is a tensor of order two.

Solution 5.3.38

Exercise 5.3.39

(Exercise 2.42.1 of [Aris, 1962]) Prove that for any vector $\vec{a}$, $\epsilon_{ijk} a_k$ are the components of a second order tensor.

Solution 5.3.39

Exercise 5.3.40

(Exercise 2.42.3 and 2.44.2 of [Aris, 1962]) If $r^2 = x_k x_k$ and $f(r)$ is any twice differentiable function, show that the following nine derivatives are components of a tensor.

$$\left[f''(r) - \frac{f'(r)}{r} \right] \frac{x_i x_j}{r^2} + \frac{f'(r)}{r} \delta_{ij}$$

. Show also that the trace of that tensor is the following.

$$\frac{1}{r^2} \frac{d}{dr} \left(r^2 \frac{df}{dr} \right)$$

Solution 5.3.40

Exercise 5.3.41

Prove that strain rate or velocity gradient is a tensor of order two.

$$e_{ij} = \frac{\partial u_i}{\partial x_j}$$

Solution 5.3.41

Exercise 5.3.42

If σ_{ij} is a tensor, prove that σ_{ii} , the trace of the matrix of σ_{ij} is invariant under co-ordinate transformations. ^a

^aThis quantity has a special meaning in mechanical behaviour of materials.

Solution 5.3.42**Exercise 5.3.43**

Prove that ϵ_{ijk} is a tensor of order three. Clue: Use the subscript notation for determinant of the transformation matrix. When two rows of a matrix are same, the determinant vanishes.

Solution 5.3.43**Exercise 5.3.44**

Prove that the dyad $\delta_{ij}\delta_{kl}$ is (an isotropic) tensor of order four. Considering that δ_{ij} is an isotropic and hence a symmetric tensors, how many combinations of the four indices can you get so that you can arrive at possible isotropic tensors of order four.

Solution 5.3.44**Exercise 5.3.45**

If a_{ij} and b_{kl} are tensors of order two, prove that the dyad $a_{ij}b_{kl}$ is a tensor of order four. Prove that $a_{ij}b_{jk}$ is a tensor of order two. Also, that $a : b = a_{ij}b_{ji}$ is a scalar.

Solution 5.3.45**Exercise 5.3.46**

Use the Neumann's principle to prove that the number of components necessary to describe the thermal conductivity of a tetragonal crystal is two. You can assume that the thermal conductivity is a symmetric tensor to start with, thanks to Onsager's theory [Onsager, 1931a, Onsager, 1931b].

Solution 5.3.46

Tensor Properties

Exercise 5.3.47

If a_{ij} and b_{ij} are two tensors of order 2, then write the order / rank and list the free indices for each of the following quantities.

- (1) $a_{ij}b_{jk}$ (2) $a_{ij}b_{ik}$ (3) $a_{ij}b_{kj}$ (4) $a_{ij}b_{ij}$ (5) $a_{ij}b_{ji}$ (6) $a_{ji}b_{ij}$ (7) $a_{ij}b_{ki}$ (8) $a_{ij}b_{kl}$

Solution 5.3.47

The order of tensor and free indices are as follows: (1) 2, i, k (2) 2, j, k (3) 2, i, k (4) 0, no free indices (5) 0, no free indices (6) 0, no free indices (7) 2, j, k (8) 4, i, j, k, l

Exercise 5.3.48

In the above list of expressions, which of the above qualifies as a matrix multiplication the way you knew it?

Solution 5.3.48

(1) $a_{ij}b_{jk}$ is matrix multiplication. The summation is over the second index j of first matrix a and first index j of second matrix b . The output is a matrix of size given by first index i of first matrix and second index k of second matrix.

- 1.
2. Consider the above expressions are contraction operations on d_{ijkl} where $d_{ijkl} = a_{ij}b_{kl}$. List which expression is a contraction operation over which of the indices of d .
3. In the above list of expressions, are all the second order tensorial quantities identical?
4. The elements of a vector $\vec{a}$ in the new coordinate system after rotation from an old coordinate system are given as follows. Here, T_{pi} indicates the transformation matrix corresponding to the rotation of axes.

$$a_p^* = T_{pi} a_i$$

Show that the components of this vector $\vec{a}$ in the old coordinate system in terms of the new coordinate system can be given by the following equation.

$$a_i = T_{pi} a_p^*$$

5. If b_i is any vector and a_{ij} is a matrix of nine numbers and if a relation could be found such that $a_{ij}b_i = c_j$ is always a vector, then show that a_{ij} is a tensor.
Hint: Start with definition of b_i and c_j being vectors. Apply the relation connecting them across a coordinate transformation. The result you obtain is called as the Quotient Rule.
6. Show that δ_{ij} is an isotropic tensor of order 2. That is, the elements of δ_{ij} do not change for **any** arbitrary rotation of the coordinate system.
Hint: Use the subscript replacement ability of Kronecker delta and the orthogonality condition for a transformation matrix.
7. Show that ϵ_{ijk} is an isotropic tensor of order 3.
Hint: Use the formula for determinant of a matrix using the permutation symbol.
8. Show that $\delta_{ij}\delta_{kl}$ is an isotropic tensor of order 4. Show that the other two combination of indices will also give the same conclusion. Show that a linear combination of these three fourth order isotropic tensors is also an isotropic tensor of order four.

To ponder / home work

1. What can you recall about eigenvectors and eigenvalues for a 3×3 matrix?
2. If A is a 3×3 matrix and δ_{ij} is the identity matrix, write down the determinant of the matrix $|A - \lambda\delta_{ij}|$. The cubic polynomial in λ you obtain is called the characteristic polynomial and the equation that equals this polynomial to zero is called **secular** equation or characteristic equation of a tensor of order two.
3. Collate the coefficients of λ^3 , λ^2 and λ in the above expression.
4. Write each of these coefficient expressions in subscript notation.
5. Is it right to say that each of these coefficients are invariant under rotation of coordinate system?

$$|\sigma_{ij} - \lambda\delta_{ij}| = -\lambda^3 + I_1\lambda^2 - I_2\lambda + I_3 = 0 \quad (5.8)$$

Here the invariants are as follows:

$$I_1 = \sigma_{kk} = \sigma_{11} + \sigma_{22} + \sigma_{33}$$

$$I_2 = \frac{1}{2}(\sigma_{ii}\sigma_{jj} - \sigma_{ij}\sigma_{ji}) = \sigma_{11}\sigma_{22} + \sigma_{22}\sigma_{33} + \sigma_{11}\sigma_{33} - \sigma_{12}^2 - \sigma_{23}^2 - \sigma_{31}^2$$

$$I_3 = \det(\sigma_{ij}) = \sigma_{11}\sigma_{22}\sigma_{33} + 2\sigma_{12}\sigma_{23}\sigma_{31} - \sigma_{12}^2\sigma_{33} - \sigma_{23}^2\sigma_{11} - \sigma_{31}^2\sigma_{22}$$

5.4 Understand (Tensor components). *Determine the components of a second order tensor after rotation of coordinate systems given the transformation matrix*

Give some examples here

5.5 Understand (Tensor components). *Determine unknown components of a tensor of second order by using the invariants*

Give some examples here

5.4 Summary

1. Tensors are defined by the way their elements are to change upon a coordinate rotation.
2. Theorems on tensors allow us to interpret if a particular quantity in an expression is a tensor or not.
3. Isotropic tensor is one whose elements do not change upon any arbitrary coordinate rotation.

Chapter 6

Symmetry of Property Tensors

6.1 Tensor quantities

- **Polar tensors** do not change sign when the handedness of the coordinate system changes

$$a_{pqrs...} = T_{pi}T_{qj}T_{rk}T_{sl}...a_{ijkl...}$$

- **Axial / Pseudo tensors** change sign when the handedness of the coordinate system changes

$$a_{pqrs...} = |a| T_{pi}T_{qj}T_{rk}T_{sl}...a_{ijkl...}$$

Here, $|a|$ is the determinant of the direction cosine matrix.

6.2 Tensors that represent physical properties

- **Constitutive relations** are those that describe a physical phenomenon by connecting the cause with the effect through a material property.

In a constitutive relation, the entity that connects a tensor of order m with a tensor of order n is of the order $m + n$ by the quotient law of tensors.

- **Neumann's principle** : The symmetry group of any physical property of a crystal comprises the point symmetry group of the crystal.

A tensor that represents a physical property of a material should have at least the symmetry of the material.

- **Pierre Curie symmetry principle** (1894) : Effect is at least as symmetric as the cause. The symmetry of a crystal of known symmetry in the presence of external fields is given by the intersection of the symmetries of the crystal and the fields.

Using the Neumann's principle, the tensor representing a property of a material should have the same symmetry as that of the material itself.

Liquids and glasses are isotropic ie., they have infinite symmetry ¹. The stuff remains the same in all the directions. So the physical property should also remain the same in all directions.

¹Only on a long range. They do have a short range order allegedly close to icosahedral in case of liquid metals

Property	Equation	Quantities
Pyroelectric effect	$\Delta P_i = \gamma_i \Delta T$	electric polarisation, pyroelectric coefficient and change in temperature
Thermal conduction	$q_i = -k_{ij} \frac{dT}{dx_j}$	heat flux, thermal conductivity and temperature gradient
Electrical conduction	$J_i = \sigma_{ij} E_j$	electric current, electrical conductivity and electrical field
Thermal expansion	$e_{ij} = \alpha_{ij} \Delta T$	thermal strain, thermal expansion coefficient and change in temperature
Direct piezoelectric effect	$P_i = d_{ijk} \sigma_{jk}$	electric polarization, piezoelectric coefficient and stress tensor
Inverse piezoelectric effect	$e_{jk} = l_{ijk} E_i$	strain, inverse piezoelectric coefficient and electric field
Linear electrooptical effect	$\Delta \eta_{ij} = r_{ijk} E_k$	polarization constants, tensor of linear electrooptical effect and electric field
Elasticity	$e_{ij} = c_{ijkl} \sigma_{kl}$	strain, elastic compliance and stress

Table 6.1: Examples of common physical phenomena, adapted from [Perelomova and Tagieva, 1983].

So, the tensor representing the physical property of this stuff should be isotropic. That is, any arbitrary transformation of the co-ordinate system should leave the matrix containing the values of physical property unchanged. It is possible only if the property is representable by an isotropic tensor of corresponding order. Thus, for second order tensors such as thermal conductivity, diffusivity etc., of liquids only one value is necessary.

$$a_{ij} = a\delta_{ij}$$

Polycrystalline materials have crystals in all possible directions and as a bulk they behave as if the material is isotropic. Most of the engineering materials of interest are polycrystalline. Exceptions are highly textured materials (eg. after rolling) and single crystals (for turbine blades or semiconductor industry).

Take, for example, the second order tensor representing the thermal conductivity of a crystal. It should in general have 6 components (9 components become 6 thanks to the tensor being symmetric). Using the Curie principle, it can be shown as in section A.5 that for cubic crystals one needs to specify only one value for thermal conductivity.

Examples of Tensor quantities

Order	Polar	Axial
0	Specific heat	Rotary Power
1	Pyroelectricity	Pyromagnetism
2	Thermal expansion	Magnetoelectricity
3	Piezoelectricity	Piezomagnetism
4	Elastic compliance	Piezogyrotropy

Quotient theorem

- If u_i and v_j are tensors of order one and are related in every coordinate system as $u_i = b_{ij}v_j$ then b_{ij} is a tensor of order two.
- If a_{ij} and c_{ik} are tensors of order two and are related in every coordinate system as $a_{ij}b_{jk} = c_{ik}$ then b_{jk} is a tensor of order two.
- One can deduce the tensor character of most quantities that describe a physical process.
- One can determine the highest possible rank of a tensor connecting a cause and effect in a constitutive equation.

Tinder's book [Tinder, 2008] has detailed analysis on how the tensor properties of crystals develop. An illustration of some common tensor quantities and their order is given in the figure 6.1. Newnham's book [Newnham, 2005] also has a good discussion on the tensor properties of materials, their anisotropy, symmetry and structure.

Constitutive relations

Definition Constitutive relations are those that connect cause and effect.

$$\text{Effect} = \text{Property} \times \text{Cause}$$

- Linear constitutive relations are quite popular.

Heat conduction

Fourier's law

$$\vec{J} = -k\vec{\nabla}T$$

Thermal conductivity k_{ij} is a tensor of order 2 since heat flux $\vec{J}$ and thermal gradient $\vec{\nabla}T$ are vectors.

Elasticity

Hooke's law

$$e = C\sigma$$

Compliance C_{ijkl} is a tensor of order 4 since strain e_{kl} and stress σ_{ij} are tensors of order 2.

Viscosity

Newton's law

$$d_{ij} = \mu_{ijkl} \frac{\partial u_k}{\partial x_l}$$




Figure 6.1: Examples of tensor quantities

Viscosity μ_{ijkl} is a tensor of order 4 since strain rate $\frac{\partial u_k}{\partial x_l}$ and deviatoric stress d_{ij} are tensors of order 2.

Thermal expansion

$$\sigma = \alpha \Delta T$$

Thermal expansion coefficient α_{ij} is a tensor of order 2 since stress σ_{ij} is a tensor of order 2 and temperature difference ΔT is a scalar.

Electrical resistance

Ohm's law

$$\vec{E} = \rho \vec{J}$$

Electrical resistivity ρ_{ij} is a tensor of order 2 since electric field strength $\vec{E}$ and current density $\vec{J}$ are vectors.

Piezoelectric effect

$$P_i = d_{ijk} \sigma_{jk}$$

Direct piezoelectric coefficient d_{ijk} is a tensor of order 3 since polarization $\vec{P}$ is a vector and stress σ_{jk} is a tensor of order 2.

Since centrosymmetric crystals cannot have properties of odd rank tensor, such crystals do not exhibit Piezoelectricity.

Electrostriction

$$x_{ij} = d_{ijk}E_k + M_{ijkl}E_kE_l$$

Direct piezoelectric coefficient d_{ijk} is a tensor of order 3 since polarization $\vec{P}$ is a vector and stress σ_{jk} is a tensor of order 2.

Because of the second term, electrostriction is not limited to non-centrosymmetric crystals.

Solute diffusion

Fick's law

$$\vec{J}_A = -D\vec{\nabla}C_A$$

According to Fick's law, diffusion of a species A is down the concentration gradient. Actually it is down the chemical potential gradient. Since flux of species $\vec{J}_A$ and concentration (or chemical potential) gradient $\vec{\nabla}C_A$ (or $\vec{\nabla}\mu_A$) are vectors, diffusivity D_{ij} must be a tensor of order 2.

Curie Principle

When certain causes lead to certain effects, the symmetry elements of the causes should be observed in these effects.

Neumann Principle

The symmetry of any physical property of a crystal must include the symmetry elements of the point group of the crystal.

Symmetry effects on property tensors

- Gases : Isotropic
- Liquids : Isotropic
- Polycrystalline solids : Isotropic
- Textured solids : Anisotropic, depending on type of texture
- Single crystals : Anisotropic, depending on crystal symmetry

6.1 Apply (Tensors). *List number of independent components and the form of isotropic tensors*

6.3 Isotropic tensors

Definition: A tensor is isotropic if its elements donot change under *any* co-ordinate transformation².

²involving only rotations and reflections but not expansions or contractions ie., $\text{Det}(T_{ij})$ is unity

- Kronecker delta is an isotropic tensor of order two. The general form of an isotropic tensor of order two is

$$a_{ij} = a\delta_{ij}$$

- Levi-Civita density is an isotropic tensor of order three. Proof is given in section A.3 It is also referred to as alternating tensor or permutation tensor.

Relation between ϵ_{ijk} and δ_{ij} and the proof are given in equation 3.1.

- $\delta_{ij}\delta_{kl}$ is an isotropic tensor of order four.

Most general form of an isotropic tensor of order four, where μ_1 , μ_2 and μ_3 are constants:

$$\boxed{\mu_{ijkl} = \mu_1\delta_{ij}\delta_{kl} + \mu_2\delta_{ik}\delta_{jl} + \mu_3\delta_{il}\delta_{jk}} \quad (6.1)$$

Proof is given in section A.4.

General forms of isotropic tensors for properties

- Isotropic tensor of order 2 :

$$\lambda \delta_{ij}$$

- Isotropic tensor of order 3 :

$$\lambda \epsilon_{ijk}$$

- Isotropic tensor of order 4 :

$$\lambda_1 \delta_{ij}\delta_{kl} + \lambda_2 \delta_{il}\delta_{kj} + \lambda_3 \delta_{ik}\delta_{jl}$$

Imposing symmetry on property tensor

If a is a property tensor of order 2, use the following expression to identify the minimum number of elements of a needed to represent it.

$$a_{pq} = T_{pi}T_{qj}a_{ij}$$

Where T_{pi} is the matrix corresponding to a coordinate transformation that represents a symmetry operation.

6.4 Symmetry elements of crystal classes

Herrmann-Mauguin symbol is used for crystal class.

6.2 Apply (Tensors). *Determine a transformation matrix suitable for a symmetry operation*

Transformation matrices for symmetry operations

Twofold rotation 2 || Z_1

$$\begin{bmatrix} 1 & 0 & 0 \\ 0 & -1 & 0 \\ 0 & 0 & -1 \end{bmatrix}$$

Crystal System	Crystal Class	Symmetry Elements
Monoclinic	2	$2 \parallel Z_2$
Orthorhombic	222	$2 \parallel Z_1, 2 \parallel Z_2$
Tetragonal	$\bar{4}2m$	$\bar{4} \parallel Z_3, 2 \parallel Z_1$
Hexagonal	$6/mmm$	$6 \parallel Z_3, m \perp Z_3, m \perp Z_1$
Cubic	$\bar{4}3m$	$\bar{4} \parallel Z_3, 3 \parallel [111]$

Table 6.2: Symmetry elements in some crystal systems

Mirror $m \perp Z_1$

$$\begin{bmatrix} -1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

Threefold rotation $3 \parallel Z_3$

$$\begin{bmatrix} -\frac{1}{2} & \frac{\sqrt{3}}{2} & 0 \\ -\frac{\sqrt{3}}{2} & -\frac{1}{2} & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

Threefold rotation $3 \parallel [111]$

$$\begin{bmatrix} 0 & 1 & 0 \\ 0 & 0 & 1 \\ 1 & 0 & 0 \end{bmatrix}$$

Fourfold rotation $4 \parallel Z_3$

$$\begin{bmatrix} 0 & 1 & 0 \\ -1 & 0 & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

Fourfold inversion $\bar{4} \parallel Z_3$

$$\begin{bmatrix} 0 & -1 & 0 \\ 1 & 0 & 0 \\ 0 & 0 & -1 \end{bmatrix}$$

Most property tensors are symmetric

Microscopic Reversibility Principle For a system in thermodynamic equilibrium, every type of micromotion occurs just as often as its reverse.

Onsager's Reciprocity Principle Provided a proper choice is made for the fluxes and affinities, the matrix of phenomenological coefficients is symmetrical

As an implication of this, thermal conductivity k_{ij} is a symmetric tensor.

6.3 Apply (Tensors). *Apply symmetry principles to reduce the number of independent components of a property tensor*

6.5 Scaffold to reduce components by symmetry operations

A crystal has a property k_{ij} which is known to be a symmetric tensor of order 2.

1. Write down the matrix representation of this tensor in its most general form.
2. If the crystal were to be rotated by 90 degrees, anti-clockwise about the z -axis, write down the new unit vectors in terms of the old unit vectors.
3. Looking at the above three relations, write down the transformation matrix T .
4. Determine the expression for the k_{11}^* component of this tensor property in the new coordinate system.
5. Determine the expression for the k_{21}^* component of this tensor property in the new coordinate system.
6. What does it mean to say $k_{11}^* = k_{11}$? or to say $k_{21}^* = k_{21}$?
7. If $k_{11}^* = k_{11}$, what can you infer?
8. If $k_{21}^* = k_{21}$, what can you infer?
9. If a four fold rotational symmetry is all that this crystal possesses, what can you say about the simplest form of k ? Which crystal system would such a symmetry correspond to?
10. Extend the above steps for two other four fold rotations and arrive at the simplest possible form for k for a cubic crystal.

Applying symmetry to property tensor

Thermal conductivity k_{ij} , a second order symmetric tensor.

$$k_{ij} = \begin{bmatrix} k_{11} & k_{12} & k_{13} \\ k_{12} & k_{22} & k_{23} \\ k_{13} & k_{23} & k_{33} \end{bmatrix}$$

Take the symmetry operation of 4 fold rotation (by 90°) about $\hat{x}_3$. Corresponding transformation matrix is:

$$T = \begin{bmatrix} 0 & 1 & 0 \\ -1 & 0 & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

Combining Neumann Principle and the definition of a second order tensor,

$$k_{pq} = T_{pi} T_{qj} k_{ij}$$

1. Pick a combination of p & q
2. Expand RHS, knowing not all terms of T are non-zero.
3. Repeat for all possible symmetry operations

Using : $T_{12} = T_{33} = 1$, $T_{21} = -1$ and $k_{pq} = T_{pi}T_{qj}k_{ij}$

$$k_{11} = T_{1i}T_{1j}k_{ij} = T_{12}T_{12}k_{22} = k_{22} \implies k_{11} = k_{22}$$

Similarly,

$$k_{21} = T_{2i}T_{1j}k_{ij} = T_{21}T_{12}k_{12} = -k_{12} = -k_{21} \implies k_{21} = k_{12} = 0$$

Using remaining symmetry operations, one can see that all off diagonal terms of k_{ij} vanish and all diagonal terms are same.

$$k_{ij} = \begin{bmatrix} k_{11} & 0 & 0 \\ 0 & k_{11} & 0 \\ 0 & 0 & k_{11} \end{bmatrix} = k_{11}\delta_{ij}$$

6.6 Components of a symmetric tensor property

Triclinic:

$$\begin{bmatrix} S_{11} & S_{12} & S_{13} \\ & S_{22} & S_{23} \\ & & S_{33} \end{bmatrix}$$

Monoclinic:

$$\begin{bmatrix} S_{11} & 0 & S_{13} \\ & S_{22} & 0 \\ & & S_{33} \end{bmatrix}$$

Orthorhombic:

$$\begin{bmatrix} S_{11} & 0 & 0 \\ & S_{22} & 0 \\ & & S_{33} \end{bmatrix}$$

Tetragonal, trigonal, hexagonal:

$$\begin{bmatrix} S_{11} & 0 & 0 \\ & S_{11} & 0 \\ & & S_{33} \end{bmatrix}$$

Cubic:

$$\begin{bmatrix} S_{11} & 0 & 0 \\ & S_{11} & 0 \\ & & S_{11} \end{bmatrix}$$

Diagonalizability theorem

- There exists a coordinate system in which a symmetric tensor can be represented only by diagonal elements.
- Stress is a symmetric tensor because of continuum approximation.
- This is used to arrive at the principal components of a stress state.

6.7 Summary

1. Kronecker delta δ_{ij} can be used: to simplify subscripts, $a_{ik}\delta_{ij} = a_{jk}$, to represent inner / dot products and to represent an isotropic tensor of order two.
2. Levi-Civita / permutation matrix can be used: to represent cross products, to arrive at determinants of matrices and to represent an isotropic tensor of order three.
3. Kronecker delta and Levi-Civita symbol are connected as: $\epsilon_{ijk}\epsilon_{klm} = \delta_{il}\delta_{jm} - \delta_{im}\delta_{jl}$ and $\epsilon_{ijk}\epsilon_{ijm} = 2\delta_{km}$.

Chapter 7

Continuity Equation

7.1 Learning objectives

At the end of this chapter, a student should be able to

1. apply continuity equation to determine unknown components of a velocity field
2. plot stream function as contours to visualize flow field in a 2D domain

7.1 Apply (Fluid Flow). *Derive continuity equation*

7.2 Concept map




Figure 7.1: Concept map to arrive at continuity equation

A concept map that exposes the connections between different concepts behind continuity equation is given in the figure 7.1.

7.3 Type of specifications



Figure 7.2: An image generated by chatgpt to show Euler as traffic police and Lagrange as a driver. Helps connect the specifications to the respective perspectives

Figure 7.3 illustrates a control volume being advected in a fluid. Consider a parameter that can be specified at the center of this control volume. Time derivative of such a parameter could be described either in a coordinate system fixed to the center of the control volume itself or in an external coordinate system of the observer.




Figure 7.3: Motion of a volume element in a fluid

Lagrangian: Velocities are specified at the centre of mass (a_i) and time (t).

Eulerian: Velocities are specified in terms of position (x_i) and time (t).

- Eulerian specification gives spatial gradients of velocities directly.

- Lagrangian specification helps trace the path of an element directly.

7.4 Time derivative

Consider a flow field and trace a particle that moves with the flow. The flow field can be specified in two ways. In the **Eulerian** type of specification, the velocities are specified in terms of position (x_i) and time (t). It gives the spacial distribution of velocity $u_i(x_i, t)$ similar to density, temperature and pressure at any given instant.

In **Lagrangian** type of specification, the dynamical history of a specific piece of material (fluid element) is given. The flow field of the element is given in terms of the position (of the center of mass) of the element and time as $v_i(a_i, t)$.

Eulerian specification gives spacial gradients of velocities directly. Lagrangian specification helps trace the path of an element directly. Unless otherwise specified, one usually uses to the Eulerian frame of reference.

In the Lagrangian specification, since the velocity $v_i(a_i, t)$ is specified at the centre of gravity of the fluid element, acceleration of a fluid element is given by

$$\frac{dv_i}{dt} = \frac{\partial v_i}{\partial t} \quad (7.1)$$

In the Eulerian specification, since the velocity ($u_i(x_i, t)$) is specified in terms of the absolute position where as the location of the fluid element changes as dictated by the flow (see section A.6), acceleration of the fluid element is given as below:

$$\frac{du_i}{dt} = \frac{\partial u_i}{\partial t} + u_j \frac{\partial u_i}{\partial x_j} = \frac{\partial u_i}{\partial t} + u_j \nabla_j u_i \quad (7.2)$$

or

$$\frac{d\vec{u}}{dt} = \frac{\partial \vec{u}}{\partial t} + (\vec{u} \cdot \vec{\nabla}) \vec{u} \quad (7.3)$$

Proof of the same is given in section A.7.

We now define the **material derivative** which is a time derivative following the motion of the fluid as

$$\boxed{\frac{D}{Dt} = \frac{\partial}{\partial t} + (\vec{u} \cdot \vec{\nabla})} \quad (7.4)$$

Lagrangian:

$$\frac{d\phi}{dt} = \frac{\partial \phi}{\partial t}$$

Eulerian:

$$\begin{aligned} \frac{d\phi}{dt} &= \frac{\partial \phi}{\partial t} + \frac{\partial \phi}{\partial x_1} \frac{\partial x_1}{\partial t} + \frac{\partial \phi}{\partial x_2} \frac{\partial x_2}{\partial t} + \frac{\partial \phi}{\partial x_3} \frac{\partial x_3}{\partial t} \\ &= \frac{\partial \phi}{\partial t} + \frac{\partial \phi}{\partial x_1} u_1 + \frac{\partial \phi}{\partial x_2} u_2 + \frac{\partial \phi}{\partial x_3} u_3 \end{aligned}$$

$$= \left[\frac{\partial}{\partial t} + u_1 \frac{\partial}{\partial x_1} + u_2 \frac{\partial}{\partial x_2} + u_3 \frac{\partial}{\partial x_3} \right] \phi$$

$$\frac{d\phi}{dt} = \left[\frac{\partial}{\partial t} + \vec{u} \cdot \vec{\nabla} \right] \phi$$

Acceleration

Lagrangian:

$$\frac{d\vec{V}}{dt} = \frac{\partial \vec{V}}{\partial t}$$

Eulerian:

$$\frac{d\vec{u}}{dt} = \left[\frac{\partial}{\partial t} + \vec{u} \cdot \vec{\nabla} \right] \vec{u}$$

Material derivative:

$$\frac{D}{Dt} \equiv \frac{\partial}{\partial t} + \vec{u} \cdot \vec{\nabla} \equiv \frac{\partial}{\partial t} + u_j \nabla_j$$

7.5 Flux of mass

Convention for flux:




Figure 7.4: Convention for flux of material

Area element has **outward** normal.

$$d\vec{S} = dA \hat{n}$$

$$d\vec{S} = dx_1 dx_3 \hat{x}_2$$

Mass flux:

$$\vec{J} = \rho \vec{u}$$

$$J_2 = \rho u_2$$

Mass flow rate through the area element:

$$\vec{J} \cdot d\vec{S} = \rho u_2 dx_1 dx_3$$

Divergence theorem:




Figure 7.5: Schematic for divergence theorem

Consider for 6 faces of the volume element:

$$\sum \vec{J} \cdot d\vec{S}$$

Total outward mass flow:

$$\begin{aligned} & J_2|_{x_2+\Delta x_2} \Delta x_1 \Delta x_3 - J_2|_{x_2} \Delta x_1 \Delta x_3 \\ & + J_3|_{x_3+\Delta x_3} \Delta x_1 \Delta x_2 - J_3|_{x_3} \Delta x_1 \Delta x_2 \\ & + J_1|_{x_1+\Delta x_1} \Delta x_2 \Delta x_3 - J_1|_{x_1} \Delta x_2 \Delta x_3 \\ & = \left[\frac{\partial J_1}{\partial x_1} + \frac{\partial J_2}{\partial x_2} + \frac{\partial J_3}{\partial x_3} \right] \Delta x_1 \Delta x_2 \Delta x_3 \\ & \Delta V = \Delta x_1 \Delta x_2 \Delta x_3 \end{aligned}$$

Divergence theorem:

$$\begin{aligned} \sum \vec{J} \cdot d\vec{S} &= [\vec{\nabla} \cdot \vec{J}] \Delta V \\ \int_s \vec{J} \cdot d\vec{S} &= \int_v \vec{\nabla} \cdot \vec{J} dV \\ \int_s J_i n_i dS &= \int_v \frac{\partial J_i}{\partial x_i} dV \end{aligned}$$

7.6 Mass balance

Statement in words: Total influx of mass into a control volume equals increase in its mass.

As per our convention, $d\vec{S}$ is outward normal to the face of the control volume. So $\int_s \vec{J} \cdot d\vec{S}$ is total outflux.

Increase in mass of a control volume fixed in space is $\int_v \frac{\partial \rho}{\partial t} dV$.

Statement for a CV

$$\int_v \frac{\partial \rho}{\partial t} dV = - \int_s \vec{J} \cdot d\vec{S}$$

7.7 Continuity equation

Consider a control volume of surface area S and volume V through which a flow $\vec{u}$ is taking place. Conservation of mass requires that the increase in amount of fluid in the element is equal to the amount brought in by the fluid flow (in the absence of sources and sinks that are singular). By convention, the surface normal $\vec{n}$ points *outwards* and hence the conservation can be written as follows.

Mass balance over a control volume fixed in space:

$$\int_V \frac{\partial \rho}{\partial t} dV = - \int_S \vec{J} \cdot \vec{n} dS = - \int_S (\rho \vec{u}) \cdot \vec{n} dS \quad (7.5)$$

$$\int_v \frac{\partial \rho}{\partial t} dV = - \int_s \vec{J} \cdot d\vec{S} = - \int_v \vec{\nabla} \cdot \vec{J} dV = - \int_v \vec{\nabla} \cdot (\rho \vec{u}) dV$$

Expanding the RHS,

$$\begin{aligned} \int_v \frac{\partial \rho}{\partial t} dV &= -\rho \int_v \vec{\nabla} \cdot \vec{u} dV - \int_v \vec{u} \cdot \vec{\nabla} \rho dV \\ \int_v \left[\frac{\partial \rho}{\partial t} + \vec{u} \cdot \vec{\nabla} \rho \right] dV &= - \int_v \rho \vec{\nabla} \cdot \vec{u} dV \end{aligned}$$

Using the Gauss theorem¹ to convert the surface integral to volume integral,

$$\int_v \frac{\partial \rho}{\partial t} dV = - \int_v \vec{\nabla} \cdot (\rho \vec{u}) dV \quad (7.6)$$

For this relation to be valid at *all* locations in the fluid,

$$\boxed{\frac{\partial \rho}{\partial t} + \vec{\nabla} \cdot (\rho \vec{u}) = 0} \quad (7.7)$$

Use the identity in question 19 to expand the above equation as

$$\frac{\partial \rho}{\partial t} + (\vec{u} \cdot \vec{\nabla}) \rho + \rho \vec{\nabla} \cdot \vec{u} = 0 \quad (7.8)$$

¹Actually Gauss-Ostrogradsky theorem

Identifying the definition of material derivative $\frac{D}{Dt}$ and dividing by ρ ,

$$\boxed{\frac{1}{\rho} \frac{D\rho}{Dt} + \vec{\nabla} \cdot \vec{u} = \frac{1}{\rho} \frac{D\rho}{Dt} + \Delta = 0} \quad (7.9)$$

$\vec{\nabla} \cdot \vec{u}$ is called as *rate of dilation* or rate of expansion or compressibility and is indicated by a symbol Δ .

$$\Delta = \vec{\nabla} \cdot \vec{u} = \nabla_i u_i = u_{i,i} \quad (7.10)$$

Equations 7.7 and 7.9 are two alternate forms of the *continuity equation*.

A fluid is called as *incompressible* if the density does not change due to changes in pressure (or) if the rate of change of density following the flow is zero. For *incompressible* fluids, the continuity equation reduces to:

$$\vec{\nabla} \cdot \vec{u} = \Delta = 0 \quad (7.11)$$

Sections A.6 and A.7 state the same thing more rigorously.

7.8 Strain rate tensor

The way velocity gradients would change the shape of a moving control volume in a fluid is illustrate in the following figures.





Figure 7.6: Motion of a control volume due to unidirectional flow along $\hat{x}_1$

From the figures, it is clear that uniform velocities lead to only translation of a control volume but velocity gradients would change the shape.

Figure 7.7: Motion of a control volume due to unidirectional flow along $\hat{x}_2$

$$\varepsilon_{ij} = \frac{\partial u_i}{\partial x_j} = \begin{bmatrix} \frac{\partial u_1}{\partial x_1} & \frac{\partial u_1}{\partial x_2} & \frac{\partial u_1}{\partial x_3} \\ \frac{\partial u_2}{\partial x_1} & \frac{\partial u_2}{\partial x_2} & \frac{\partial u_2}{\partial x_3} \\ \frac{\partial u_3}{\partial x_1} & \frac{\partial u_3}{\partial x_2} & \frac{\partial u_3}{\partial x_3} \end{bmatrix}$$

Changes to a fluid element:

1. Translation
2. Dilation
3. Shear
4. Rotation

7.9 Rate of dilation

Define rate of dilation as:

$$\begin{aligned} \Delta &= \vec{\nabla} \cdot \vec{u} \\ \Delta &= \text{Trace of } \frac{\partial u_i}{\partial x_j} \\ \Delta &= \varepsilon_{ii} = \frac{\partial u_i}{\partial x_i} \end{aligned}$$

7.10 Other forms of continuity equation

$$\frac{1}{\rho} \frac{D\rho}{Dt} + \Delta = 0$$




Figure 7.8: Motion of a control volume due to unidirectional flow

We define an **incompressible fluid** as follows:

$$\frac{1}{\rho} \frac{D\rho}{Dt} = 0$$

Continuity equation of an incompressible fluid:

$$\Delta = \vec{\nabla} \cdot \vec{u} = \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = 0$$

Continuity equation: For incompressible fluids:

$$\vec{\nabla} \cdot \vec{u} = 0$$

Statement in words Divergence of velocity field is zero

Other coordinate systems such as (r, θ, z) or (r, θ, ϕ) :

1. Write down velocity field
2. Look up divergence operator
3. Express continuity equation

Continuity equation : cylindrical coordinate system:

Velocity components:

$$\vec{V} = V_r \hat{e}_r + V_\theta \hat{e}_\theta + V_z \hat{e}_z$$

$\vec{\nabla}$ operator:

$$\vec{\nabla} = \frac{\partial}{\partial r} \hat{e}_r + \frac{1}{r} \frac{\partial}{\partial \theta} \hat{e}_\theta + \frac{\partial}{\partial z} \hat{e}_z$$

Remember:

$$\frac{\partial \hat{e}_r}{\partial \theta} = \hat{e}_\theta \text{ \& } \frac{\partial \hat{e}_\theta}{\partial \theta} = -\hat{e}_r$$




Figure 7.9: Motion of a control volume due to flow with velocity gradient




Figure 7.10: Rate of dilation

Continuity equation:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r} \frac{\partial}{\partial r} (r V_r) + \frac{1}{r} \frac{\partial V_\theta}{\partial \theta} + \frac{\partial V_z}{\partial z} = 0$$

Continuity equation : spherical coordinate system:

Velocity components:

$$\vec{V} = V_r \hat{e}_r + V_\theta \hat{e}_\theta + V_\phi \hat{e}_\phi$$

$\vec{\nabla}$ operator:

$$\vec{\nabla} = \frac{\partial}{\partial r} \hat{e}_r + \frac{1}{r} \frac{\partial}{\partial \theta} \hat{e}_\theta + \frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \hat{e}_\phi$$

Continuity equation:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r^2} \frac{\partial}{\partial r} (r^2 V_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (V_\theta \sin \theta) + \frac{1}{r \sin \theta} \frac{\partial V_\phi}{\partial \phi} = 0$$

7.11 Applications of continuity equation

Continuity equation for an incompressible fluid:

$$\vec{\nabla} \cdot \vec{u} = 0$$

1. Determine valid unidirectional velocity fields
2. Validate components of a velocity field
3. Determine a velocity components if rest are known
4. For 2D flows, reduce the velocity field to a scalar function

7.2 Apply (Fluid Flow). *Determine functional form of unidirectional velocity fields*

7.11.1 Unidirectional velocities

Using the continuity equation for an incompressible fluid, set all velocity components except one as zero and integrate to determine the general form of unidirectional velocity in that direction.

Set $u_2 = 0$ and $u_3 = 0$ in the following equation:

$$\frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = 0$$

The unidirectional velocity along x_1 is of the form:

$$u_1 = f(x_2, x_3)$$

Set two of the three velocity components in the following equation as zero:

$$\frac{1}{r} \frac{\partial}{\partial r} (ru_r) + \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} + \frac{\partial u_z}{\partial z} = 0$$

Thus, the unidirectional velocities in cylindrical coordinate system will be of the following forms, along respective directions:

$$\begin{aligned} u_r &= \frac{f(\theta, z)}{r} \\ u_\theta &= f(r, z) \\ u_z &= f(r, \theta) \end{aligned}$$

Similarly, set two of the three velocity components in the following equation as zero:

$$\frac{1}{r^2} \frac{\partial}{\partial r} (r^2 u_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (u_\theta \sin \theta) + \frac{1}{r \sin \theta} \frac{\partial u_\phi}{\partial \phi} = 0$$

Thus, the unidirectional velocities in spherical coordinate system will be of the following forms, along respective directions:

$$\begin{aligned} u_r &= \frac{f(\theta, \phi)}{r^2} \\ u_\phi &= f(r, \theta) \end{aligned}$$

7.3 Apply (Fluid Flow). *Apply continuity equation to validate a velocity field given by its components*

7.11.2 Interpretation of continuity equation

: Continuity equation for an incompressible fluid in 2D:

$$\frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} = 0$$

1. If $\frac{\partial u_1}{\partial x_1} > 0$ then $\frac{\partial u_2}{\partial x_2} < 0$
2. Increase in magnitude in all directions not possible
3. Flow near corners

7.12 Exercises

Exercise 7.12.49

Which of the following sets of equations represent possible two-dimensional incompressible flow cases?

1. $u = 2x^2 + y^2$; $v = x^3 - x(y^2 - 2y)$
2. $u = 2xy - x^2 + y$; $v = 2xy - y^2 + x^2$

Solution 7.12.49

Evaluate $\nabla \cdot \vec{u} = 0$ and conclude.

Exercise 7.12.50

Which of the following sets of equations represent possible two-dimensional incompressible flow cases?

1. $u_r = U \cos \theta$; $u_\theta = -U \sin \theta$
2. $u_r = -q/2\pi r$; $u_\theta = K/2\pi r$

Solution 7.12.50

Exercise 7.12.51

The y component of velocity in a steady, incompressible flow field in xy plane is $v = Ay/x^2$ where $A = 2\text{m}^2/\text{s}$ and x is measured in meters. Find the simplest y component of velocity for this flow field.

Solution 7.12.51

Exercise 7.12.52

For an incompressible flow in the $r\theta$ plane, the r component of velocity is given as $u_r = -\lambda \cos \theta / r^2$. Determine a possible θ component of velocity. How many possible θ components are there?

Solution 7.12.52

7.13 Further study

1. What is d'Alembert's paradox?
2. Watched any NCFMF videos on youtube? Watch one and write down what you have learned.
3. Have you watched the movie "twister"? Can you try and write down an equation that shows the velocity field of air in a twister?

7.14 Summary

1. Continuity equation states the balance of mass in a differential form.
2. Continuity equation for an incompressible fluid reduces to the divergence of velocity field being zero.
3. Continuity equation can be used to validate a flow field, determine unknown components given the rest of those and to interpret flow profiles.
4. Rate of dilation Δ corresponds to the trace of the strain rate tensor $\varepsilon_{ij} = \partial u_i / \partial x_j$. That is, $\Delta = \varepsilon_{ii} = \partial u_i / \partial x_i$.
5. Continuity equation for incompressible flow in rectangular coordinate system is given as:

$$\frac{\partial u_x}{\partial x} + \frac{\partial u_y}{\partial y} + \frac{\partial u_z}{\partial z} = 0$$

6. Continuity equation for incompressible flow in cylindrical coordinate system is given as:

$$\frac{1}{r} \frac{\partial (r V_r)}{\partial r} + \frac{1}{r} \frac{\partial V_\theta}{\partial \theta} + \frac{\partial V_z}{\partial z} = 0$$

7. Continuity equation for incompressible flow in spherical coordinate system is given as:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r^2} \frac{\partial}{\partial r} (r^2 V_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (V_\theta \sin \theta) + \frac{1}{r \sin \theta} \frac{\partial V_\phi}{\partial \phi} = 0$$

Chapter 8

Planar flows

8.1 Learning objectives

At the end of this lesson, a student should be able to

1. pick a combination of elementary planar flows that suit a given flow condition
2. plot contours of stream function and interpret the direction of the flow field at a given location

8.2 Reducing the number of unknown velocity components

Continuity equation of an incompressible fluid Rectangular coordinate system:

$$\vec{\nabla} \cdot \vec{u} = \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = 0$$

Cylindrical coordinates:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r} \frac{\partial}{\partial r} (r V_r) + \frac{1}{r} \frac{\partial V_\theta}{\partial \theta} + \frac{\partial V_z}{\partial z} = 0$$

Spherical coordinates:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r^2} \frac{\partial}{\partial r} (r^2 V_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (V_\theta \sin \theta) + \frac{1}{r \sin \theta} \frac{\partial V_\phi}{\partial \phi} = 0$$

1. Validate components of a velocity field
2. Determine a velocity components if rest are known
3. For 2D flows, reduce the velocity field to a scalar function

Planar flow concepts Concepts to be familiar with:

1. Stream function ψ
2. Potential Φ

3. Vorticity ω

Elementary planar flows:

1. Uniform flow
2. Source flow
3. Sink flow
4. Doublet
5. Vortex

8.1 Apply (Fluid Flow). *Apply definition of stream function to determine velocity components*

8.3 Stream function

Convince yourself that the following definitions of the velocity components from their respective stream function ψ will satisfy the continuity equation for **any** continuous and well behaved scalar function ψ .

Definition of stream function ψ in rectangular coordinate system is given as follows so that $\vec{\nabla} \cdot \vec{u} = 0$ for a 2D flow:

$$u_x \equiv \frac{\partial \psi}{\partial y} \qquad u_y \equiv -\frac{\partial \psi}{\partial x}$$

Definition of stream function ψ in cylindrical coordinate system is given as follows.

$$v_r \equiv \frac{1}{r} \frac{\partial \psi}{\partial \theta} \qquad v_\theta \equiv -\frac{\partial \psi}{\partial r}$$

Irrotational flow is one in which fluid elements moving in the flow field do not undergo any rotation. This is expected when viscous forces are not dominant. This needs the condition $\vec{\nabla} \times \vec{u} = 0$. Such a flow field can be represented using a potential ϕ defined as follows.

$$\vec{u} = -\vec{\nabla} \phi$$

Velocity components for a potential flow in rectangular coordinate system are given as follows.

$$u_x = -\frac{\partial \phi}{\partial x} \qquad u_y = -\frac{\partial \phi}{\partial y}$$

Velocity components for a potential flow in cylindrical coordinate system are given as follows.

$$u_r = -\frac{\partial \phi}{\partial r} \qquad u_\theta = -\frac{1}{r} \frac{\partial \phi}{\partial \theta}$$

8.3.1 Rectangular

Continuity equation in rectangular coordinates:

$$\vec{\nabla} \cdot \vec{V} = \frac{\partial V_x}{\partial x} + \frac{\partial V_y}{\partial y} + \frac{\partial V_z}{\partial z} = 0$$

Case 1: $V_z = 0$, No z -dependence

$$V_x = \frac{\partial \psi}{\partial y}$$

$$V_y = -\frac{\partial \psi}{\partial x}$$

Following relation comes from these definitions easily.

$$\frac{\partial V_x}{\partial y} - \frac{\partial V_y}{\partial x} = \nabla^2 \psi$$

8.3.2 Cylindrical

Continuity equation in Cylindrical coordinates:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r} \frac{\partial}{\partial r} (r V_r) + \frac{1}{r} \frac{\partial V_\theta}{\partial \theta} + \frac{\partial V_z}{\partial z} = 0$$

Case 2: $V_z = 0$, No z -dependence:

$$V_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta}$$

$$V_\theta = -\frac{\partial \psi}{\partial r}$$

Case 3: $V_\theta = 0$, No θ -dependence:

$$V_r = \frac{1}{r} \frac{\partial \psi}{\partial z}$$

$$V_z = -\frac{1}{r} \frac{\partial \psi}{\partial r}$$

8.3.3 Spherical

Continuity equation in Spherical coordinates:

$$\vec{\nabla} \cdot \vec{V} = \frac{1}{r^2} \frac{\partial}{\partial r} (r^2 V_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (V_\theta \sin \theta) + \frac{1}{r \sin \theta} \frac{\partial V_\phi}{\partial \phi} = 0$$

Case 4: $V_\phi = 0$, No ϕ -dependence:

$$V_r = \frac{1}{r^2 \sin \theta} \frac{\partial \psi}{\partial \theta}$$

$$V_\theta = -\frac{1}{r \sin \theta} \frac{\partial \psi}{\partial r}$$

Classwork: Convince yourself that the above components of the velocity in 2D flow satisfy the corresponding form of continuity equation.

Stream function is represented as $\psi(x, y)$ in a 2D rectangular coordinate system.

Assume $V_z = 0$, no z -dependence of other components

Continuity equation in 2D:

$$\frac{\partial V_x}{\partial x} + \frac{\partial V_y}{\partial y} = 0$$

Define ψ such that:

$$V_x = \frac{\partial \psi}{\partial y} \text{ \& } V_y = -\frac{\partial \psi}{\partial x}$$

Continuity equation is satisfied for **any well behaved** $\psi(x, y)$

Sign convention relating ψ and velocity




Figure 8.1: Sign convention for stream function

Rectangular:

$$V_x = \frac{\partial \psi}{\partial y} \text{ \& } V_y = -\frac{\partial \psi}{\partial x}$$

Convention Differentiation of ψ in a direction gives velocity component 90° clockwise from that direction. Cylindrical:

$$V_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta} \text{ \& } V_\theta = -\frac{\partial \psi}{\partial r}$$

Meaning of ψ

If the flow is two dimensional, with only r and θ components, then we can introduce the stream function ψ as

$$u_r \equiv \frac{1}{r} \frac{\partial \psi}{\partial \theta} \tag{8.1}$$




Figure 8.2: Convention for flow direction using contours of stream function

$$u_\theta \equiv -\frac{\partial \psi}{\partial r} \quad (8.2)$$

such that the continuity equation

$$\frac{\partial (ru_r)}{\partial r} + \frac{\partial u_\theta}{\partial \theta} = 0 \quad (8.3)$$

is satisfied by the fact that the order of differentiation of ψ with respect to r and θ does not matter.

Convention Flux of fluid volume across a line OP is taken positive when it is in the anti-clockwise sense about P.

Exact differential of ψ :

$$d\psi = \frac{\partial \psi}{\partial x} dx + \frac{\partial \psi}{\partial y} dy = -v dx + u dy$$

$$\psi_P - \psi_O = \int_O^P [u dy - v dx]$$

ψ is flux of fluid volume across a line OP.

Stream function $\psi(r, \theta)$

Assume $V_z = 0$, no z -dependence

Continuity equation in 2D:

$$\frac{1}{r} \frac{\partial}{\partial r} (rV_r) + \frac{1}{r} \frac{\partial V_\theta}{\partial \theta} = 0$$

Define ψ such that:

$$V_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta} \text{ \& } V_\theta = -\frac{\partial \psi}{\partial r}$$

Stream function $\psi(r, z)$

Assume $V_\theta = 0$, no θ -dependence

Continuity equation in 2D:

$$\frac{1}{r} \frac{\partial}{\partial r} (r V_r) + \frac{\partial V_z}{\partial z} = 0$$

Define ψ such that:

$$V_r = \frac{1}{r} \frac{\partial \psi}{\partial z} \text{ \& } V_z = -\frac{1}{r} \frac{\partial \psi}{\partial r}$$

Stream function $\psi(r, \theta)$

Assume $V_\phi = 0$, no ϕ -dependence

Continuity equation in 2D:

$$\frac{1}{r^2} \frac{\partial}{\partial r} (r^2 V_r) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (V_\theta \sin \theta) = 0$$

Define ψ such that:

$$V_r = \frac{1}{r^2 \sin \theta} \frac{\partial \psi}{\partial \theta} \text{ \& } V_\theta = -\frac{1}{r \sin \theta} \frac{\partial \psi}{\partial r}$$

8.2 Apply (Fluid Flow). *Validate a velocity profile as irrotational*

8.4 Vorticity

Vorticity is often represented using ω .

Definition

$$\omega = \vec{\nabla} \times \vec{u}$$

Circulation Γ is line integral of tangential velocity component about a closed curve C fixed in the flow.

$$\Gamma = \oint_C \vec{u} \times d\vec{S}$$

Stokes theorem in 2D:

$$\Gamma = \oint_C \vec{u} \times d\vec{S} = \int_A \vec{\nabla} \times \vec{u} dA = \int_A \vec{\omega} \cdot \hat{n} dA$$

In an **irrotational** flow fluid elements do not undergo any rotation:

$$\omega = 0$$

8.3 Apply (Fluid Flow). *Apply definition of velocity potential to determine velocity components*

8.5 Velocity potential

Velocity potential is often represented using Φ .

Using the vector identity $\vec{\nabla} \times \vec{\nabla} \Phi = 0$ for any scalar function Φ , one can propose a **potential** to determine velocity fields of an **irrotational flow**.

Flow is down the potential gradient. Let's define Φ such that:

$$\vec{u} = -\vec{\nabla} \Phi$$
$$u_1 = -\frac{\partial \Phi}{\partial x_1} \text{ \& } u_2 = -\frac{\partial \Phi}{\partial x_2}$$

Generating velocity potentials

Continuity equation for incompressible fluids:

$$\vec{\nabla} \cdot \vec{u} = -\vec{\nabla} \cdot \vec{\nabla} \Phi = 0 \implies \nabla^2 \phi = 0$$

Any scalar function that satisfies the Laplace's equation can be used as Φ to generate 2D velocity field.

Unlike stream function, velocity potentials can be used in 3D too.

8.6 Potential flow

Potential flow in cylindrical coordinate system:

Define Φ such that:

$$u_r = -\frac{\partial \Phi}{\partial r} \text{ \& } u_\theta = -\frac{1}{r} \frac{\partial \Phi}{\partial \theta}$$

Continuity equation in 2D becomes:

$$\frac{\partial^2 \Phi}{\partial r^2} + \frac{1}{r} \frac{\partial \Phi}{\partial r} + \frac{1}{r^2} \frac{\partial^2 \Phi}{\partial \theta^2} = -\nabla^2 \Phi = 0$$

Any scalar function that satisfies the Laplace's equation can be used as Φ to generate 2D velocity field.

Stream function and velocity potential

1. Difference in values of contours of ψ represent volume flow between them.
2. Velocity vector at any point is tangential to the contour of ψ through the point
3. Contours of ψ indicate the sense of flow.
4. Contours of Φ are normal to those of ψ .

8.4 Apply (Fluid Flow). *Plot elementary planar flows*

8.7 Elementary planar flows

8.7.1 Uniform flow

Stream function ψ :

$$\psi = Ay \text{ or } \psi = Ar \cos \theta$$

Velocity Potential Φ :

$$\Phi = -Ax \text{ or } \Phi = Ar \sin \theta$$

Velocities:

$$u = A, v = 0$$




Figure 8.3: Uniform flow using potential function

8.7.2 Stagnation flow

Stream function ψ :

$$\psi = -2xy$$

Velocity Potential Φ :

$$\Phi = x^2 - y^2$$

Velocities:

$$u = -2x \quad v = 2y$$

8.7.3 Sink flow

Q is volume flow rate per unit depth




Figure 8.4: Stagnation flow using potential function

Stream function ψ :

$$\psi = \frac{-Q}{2\pi}\theta$$

Velocity Potential Φ :

$$\Phi = \frac{Q}{2\pi} \ln r$$

Velocities:

$$u_r = \frac{-Q}{2\pi r}, u_\theta = 0$$




Figure 8.5: Sink flow using potential function

8.7.4 Source flow

Q is volume flow rate per unit depth

Stream function ψ :

$$\psi = \frac{Q}{2\pi}\theta$$

Velocity Potential Φ :

$$\Phi = \frac{-Q}{2\pi} \ln r$$

Velocities:

$$u_r = \frac{Q}{2\pi r}, \quad u_\theta = 0$$




Figure 8.6: Source flow using potential function

8.7.5 Doublet

A is strength of doublet.

Stream function ψ :

$$\psi = \frac{-A \sin \theta}{r}$$

Velocity Potential Φ :

$$\Phi = \frac{-A \cos \theta}{r}$$

Velocities:

$$u_r = \frac{-A \cos \theta}{r^2}, \quad u_\theta = \frac{-A \sin \theta}{r^2}$$




Figure 8.7: Doublet flow using potential function

8.7.6 Vortex

A is strength of vortex

Stream function ψ :

$$\psi = \frac{-A}{2\pi} \ln r$$

Velocity Potential Φ :

$$\Phi = \frac{-A}{2\pi} \theta$$

Velocities:

$$u_r = 0, u_\theta = \frac{A}{2\pi r}$$




Figure 8.8: Vortex flow using potential function

8.7.7 Combinations of elementary planar flows

Source flow + Uniform flow $\rightarrow$ Flow past a half-body




Figure 8.9: Source + Uniform flow using potential function

Source or Sink flow + Vortex $\rightarrow$ Spiral flow

Combinations of elementary planar flows




Figure 8.10: Source + Vortex flow using potential function




Figure 8.11: Doublet + Uniform flow using potential function

Doublet + Uniform flow $\rightarrow$ Flow past a cylinder

Doublet + Vortex + Uniform flow $\rightarrow$ Flow past a cylinder with circulation

8.8 Summary

1. Stream function relations
2. Vorticity relations
3. Condition for irrotational flow

8.9 Further study

1. The velocity field near the core of a tornado can be approximated as following.

$$\vec{u} = -\frac{q}{2\pi r}\hat{e}_r + \frac{K}{2\pi r}\hat{e}_\theta$$

Is this an irrotational flow field? Obtain the stream function for this flow.

Ans: $\psi = -(q\theta + K \ln r)/2\pi$.




Figure 8.12: Doublet + Vortex + Uniform flow using potential function

2. An incompressible flow field is defined using stream function as follows.

$$\psi = A(x^2 - y^2)$$

Determine the velocity components of this flow field. Also, check if this flow field is irrotation and if so, determine the velocity potential ϕ for this flow.

3. Using the definitions of ψ and ϕ and the continuity equation for a 2D flow field, show that any scalar function that satisfies the Laplace's equation can represent a 2D, irrotational, incompressible flow field.
4. Volume flow rate across two streamlines is given by $Q = \int u dl$ where l is the distance across the two streamlines. Convince yourself that the volume flow rate Q between two streamlines ψ_1 and ψ_2 is $\psi_2 - \psi_1$.
Hint: Write the exact differential for ψ and evaluate the flow rate between two streamlines keeping either x or y constant.
5. Convince yourself that the constant ψ line at any point is negative reciprocal to the slope of ϕ at that point.
Hint: Use exact differential of ψ and ϕ and write $(\frac{\partial y}{\partial x})_\psi$ etc.,
6. A flow field where the streamlines are concentric circles is called a vortex. What kind of functional form can you think of for the velocity components in a vortex?
7. During welding, argon gas jet is used to protect the liquid melt pool. The gas flows down the cylindrical tube kept at a small height from the plate being welded. Draw schematically the flow field for this situation and design a possible functional form for the velocity components in different regions of this problem.
Hint: There are regions where the flow is unidirectional and where the flow is radially outward (source flow).

Chapter 9

Navier-Stokes Equations - Part 1

9.1 Learning objectives

At the end of this lesson, a student should be able to

1. perform algebraic analysis using subscript notation
2. identify the terms and their role in the Navier-Stokes equations
3. recall Navier-Stokes equations in rectangular coordinate system
4. derive and recall definition of Reynold's number
5. analyse the dominant terms of Navier-Stokes equations for small and large values of Reynold's number

9.2 Concept map

9.1 Understand (Fluid Flow). *List the concepts behind Navier-Stokes equations*

The starting point for momentum balance equation is Newton's second law of motion applied to a moving volume element in a fluid.

The strategy to derive Navier-Stokes equation is illustrated in the concept map below.

9.3 Forces

Long range forces decrease slowly with increase in distance between the interacting elements. These are called body forces or volume forces. Examples such as gravity (due to density ρ gradients), electromagnetic (in metals carrying electric currents) and fictitious (centrifugal or coriolis) act on the whole of the fluid element and are usually proportional to the size of the volume element (δV). They can be represented as:

$$F_i(x_i, t)\rho\delta V$$




Figure 9.1: Concept map of derivation of Navier-Stokes equation

Eg. gravity pointing vertically downwards :

$$F_i = g\hat{x}_2$$

Short range forces decrease rapidly with increase in distance between the interacting elements and are of molecular origin. Examples such as forces applied on surfaces (normal and shear), Marangoni forces (due to surface tension gradients) act on a thin layer of the fluid and are called surface forces. Local short range forces exerted by the fluid on different surface elements (δA) can be represented as:

$$\sigma(x_i, n_j, t)\delta A$$

where, n_j is the unit normal to the surface element δA . σ is called the local **stress**.

9.4 Equation of motion

9.2 Apply (Fluid Flow). Derive equation of motion

Consider a moving fluid element of volume dV and area dS on a surface with normal n_i . Using the material derivative $\frac{D}{Dt}$ introduced earlier, the rate of change of momentum of a small fluid element of volume dv is given by:

$$\frac{D}{Dt} \int_V \rho u_i dV$$

Using the Reynold's transport theorem [A.8] and the continuity equation, one can bring the material derivative inside the integral as illustrated in section [A.9].

$$\frac{D}{Dt} \int_V \rho u_i dV = \int_V \rho \frac{Du_i}{Dt} dV$$

The total force that acts on dV is the sum of body forces and surface forces:

$$\int_V F_i \rho dV + \int_S \sigma_{ij} n_j dS$$

Using Gauss divergence theorem,

$$\int_S \sigma_{ij} n_j dS = \int_V \frac{\partial \sigma_{ij}}{\partial x_j} dV \quad (9.1)$$

From Newton's second law, the rate of change of momentum is equal to the total force acting on the element. Hence,

$$\int_V \frac{Du_i}{Dt} \rho dV = \int_V F_i \rho dV + \int_V \frac{\partial \sigma_{ij}}{\partial x_j} dV \quad (9.2)$$

Since the three integrands are being summed over the same volume element, it will be applicable at *any* location in the fluid if the equation applies to the integrands themselves:

$$\boxed{\frac{Du_i}{Dt} \rho = F_i \rho + \frac{\partial \sigma_{ij}}{\partial x_j}} \quad (9.3)$$

We now need to express σ_{ij} in a way that can minimise the number of unknown parameters in the above equation of motion.

9.5 Stress tensor

Section A.10 stating the Cauchy's stress principle and section A.11 prove that stress is a tensor. We can also use conservation of angular momentum to show that the stress tensor is symmetric as described in section A.12. Hence it can be expressed as

$$\sigma_{ij} = \begin{pmatrix} \sigma_{11} & \sigma_{12} & \sigma_{13} \\ \sigma_{12} & \sigma_{22} & \sigma_{23} \\ \sigma_{13} & \sigma_{23} & \sigma_{33} \end{pmatrix} \quad (9.4)$$

Since it is always possible to find a co-ordinate system such that the matrix containing the elements of a symmetric tensor is diagonal, we can write σ_{ij} as the follows.

$$\sigma_{ij} = \begin{pmatrix} \sigma_{11} & 0 & 0 \\ 0 & \sigma_{22} & 0 \\ 0 & 0 & \sigma_{33} \end{pmatrix} \quad (9.5)$$

or

$$\sigma_{ij} = \begin{pmatrix} \frac{1}{3}\sigma_{kk} & 0 & 0 \\ 0 & \frac{1}{3}\sigma_{kk} & 0 \\ 0 & 0 & \frac{1}{3}\sigma_{kk} \end{pmatrix} + \begin{pmatrix} \sigma_{11} - \frac{1}{3}\sigma_{kk} & 0 & 0 \\ 0 & \sigma_{22} - \frac{1}{3}\sigma_{kk} & 0 \\ 0 & 0 & \sigma_{33} - \frac{1}{3}\sigma_{kk} \end{pmatrix} \quad (9.6)$$

where

$$\sigma_{kk} = \sigma_{11} + \sigma_{22} + \sigma_{33} \quad (9.7)$$

$$\sigma_{ij} = \frac{1}{3}\sigma_{kk}\delta_{ij} + d_{ij} \quad (9.8)$$

We define static pressure of the fluid with the convention that positive pressure is that which acts to compress a fluid element,

$$p = -\frac{1}{3}\sigma_{kk} \quad (9.9)$$

so that

$$\sigma_{ij} = -p\delta_{ij} + d_{ij} \quad (9.10)$$

d_{ij} is called the *deviatoric* part of the tensor and leads only to volume conserving deformation of the fluid elements ie., flow of the fluid. Static pressure, on the other hand, leads to a shape-conserving change in the volume element. It is easy to note that

$$d_{kk} = 0 \quad (9.11)$$

We have separated the stress into two terms:

- *pressure* term ($-p\delta_{ij}$) that tends to change the volume of a fluid element
- *deviatoric stress* term (d_{ij}) that tends to change the shape of a fluid element while keeping the volume constant

By analysing all modes of change of shape of a fluid element, we can relate the deviatoric stress with the terms that quantify the shape changes of a fluid element. For non-zero velocity field, because the fluid element translates as time progresses, we will notice that rate of change of shape is more appropriate to analyse a fluid element.

9.6 Strain rate tensor

The meaning of velocity gradient or a strain rate term $\frac{\partial u_i}{\partial x_j}$ is given in section A.13. Proof that velocity gradient is a tensor of order two is given in section A.14. Strain rate or velocity gradient is represented as below and can be shown to be a second order tensor and thus expressible as a sum of symmetric and anti-symmetric tensors.

$$\frac{\partial u_i}{\partial x_j} = e_{ij} + \Omega_{ij} \quad (9.12)$$

$$e_{ij} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) \quad (9.13)$$

$$\Omega_{ij} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right) \quad (9.14)$$

Define ω as

$$\vec{\omega} = \vec{\nabla} \times \vec{u} \quad (9.15)$$

or

$$\omega_i = \epsilon_{ijk} u_{j,k} = \epsilon_{ijk} \frac{\partial u_j}{\partial x_k} \quad (9.16)$$

so that,

$$\Omega_{ij} = -\frac{1}{2} \epsilon_{ijk} \omega_k \quad (9.17)$$

9.7 Relation between stress and strain-rate

A relation between the deviatoric stress and strain-rate (velocity gradient) is necessary to proceed further to be able to use the equation of motion to solve for the velocity u_i . We have to adopt a *phenomenological* approach.

By definition, d_{ij} is the deviatoric stress which implies that it is zero for a stationary fluid.

The velocities and thus the velocity gradients $\frac{\partial u_i}{\partial x_j}$ are zero for a stationary fluid.

The deviatoric stress represents the frictional interaction between different layers of the fluid and is assumed to be dependent only on the instantaneous and local distribution of the velocities.

From the above observations, we may *assume* that the deviatoric stress and the strain-rate are directly and *linearly* related to each other. Let us propose, as shown in Figure 9.2, a constitutive relation between the deviatoric stress and velocity gradient. Since both the quantities are tensors of order two, the entity that connects them both must be a tensor of order four.

$$d_{ij} = A_{ijkl} \frac{\partial u_k}{\partial x_l} \quad (9.18)$$

Since the above equation connects an effect with a cause, it is a *constitutive relation* and the entity A_{ijkl} is a physical parameter. The material in concern is a fluid in which a directionality can safely be assumed to be absent ie.,




Figure 9.2: Concept map of how the constitutive relation is being proposed between deviatoric stress and velocity gradient

fluids are isotropic

Hence, A_{ijkl} must possess the same properties as that of an isotropic tensor of order four. From the properties of tensors, we know that the general form of an isotropic tensor of order four [A.4] is

$$A_{ijkl} = \mu_1 \delta_{ij} \delta_{kl} + \mu_2 \delta_{il} \delta_{kj} + \mu_3 \delta_{ik} \delta_{jl} \quad (9.19)$$

Since deviatoric stress d_{ij} is symmetric, interchanging the subscripts i and j should keep the quantity identical. In the above equation, this applies also to the R.H.S. ie.,

$$A_{ijkl} = A_{jikl} \Rightarrow \mu_2 = \mu_3 \quad (9.20)$$

$$A_{ijkl} = \mu_1 \delta_{ij} \delta_{kl} + \mu_2 (\delta_{il} \delta_{kj} + \delta_{ik} \delta_{jl}) \quad (9.21)$$

A_{ijkl} is now symmetrical in k and l also.

Expanding the above equation,

$$d_{ij} = A_{ijkl} (e_{kl} + \Omega_{kl}) \quad (9.22)$$

Since A_{ijkl} is now symmetrical in k and l , when it is multiplied by an entity that is anti-symmetric about k and l and the terms are summed over k and l they vanish. Thus, the Ω_{kl} term drops out.

$$d_{ij} = (\mu_1 \delta_{ij} \delta_{kl} + \mu_2 (\delta_{il} \delta_{kj} + \delta_{ik} \delta_{jl})) e_{kl} \quad (9.23)$$

$$d_{ij} = \mu_1 \delta_{ij} \delta_{kl} e_{kl} + \mu_2 (\delta_{il} \delta_{kj} e_{kl} + \delta_{ik} \delta_{jl} e_{kl}) \quad (9.24)$$

We have already (7.10) defined *compressibility* or rate of dilation or rate of expansion as

$$e_{kk} = \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = \Delta \quad (9.25)$$

For the first term, we use the contraction theorem [section 5.2] to get

$$d_{ij} = \mu_1 \delta_{ij} \Delta + 2\mu_2 e_{ij} \quad (9.26)$$

Recalling that $d_{ii} = 0$,

$$d_{ii} = \mu_1 3\Delta + 2\mu_2 \Delta = (3\mu_1 + 2\mu_2)\Delta = 0 \quad (9.27)$$

We would like the above equation to be true also for incompressible fluids ie., also when $\Delta \neq 0$. It can be true only when the term in parantheses vanishes.

Stokes' Assumption: For monoatomic fluids since there is no conversion of translational energy into vibrational / rotational energies, *bulk viscosity* can be assumed to be zero:

$$(3\mu_1 + 2\mu_2) = 0$$

or

$$\mu_1 = -\frac{2}{3}\mu_2 \quad (9.28)$$

Watch out for fluids for which Stokes' assumption is not valid.

Calling the one constant parameter as μ , the equation becomes

$$d_{ij} = -\frac{2}{3}\mu \delta_{ij} \Delta + 2\mu e_{ij} \quad (9.29)$$

$$d_{ij} = 2\mu \left(e_{ij} - \frac{1}{3}\Delta \delta_{ij} \right) \quad (9.30)$$

Now that we have an expression for d_{ij} in terms of velocity gradients, we can substitute the same in the equation of motion.

9.8 Navier-Stokes equations

Combining equation of motion (9.3) and the expressions for stress tensor (9.10 and 9.30), we get,

$$\rho \frac{Du_i}{Dt} = \rho F_i + \frac{\partial}{\partial x_j} \left[-p\delta_{ij} + 2\mu \left(e_{ij} - \frac{1}{3}\Delta\delta_{ij} \right) \right] \quad (9.31)$$

Expanding the term e_{ij} and using the kronecker delta to contract subscripts, we get:

$$\rho \frac{Du_i}{Dt} = \rho F_i - \frac{\partial p}{\partial x_i} + \frac{\partial}{\partial x_j} \left(\mu \frac{\partial u_i}{\partial x_j} \right) + \frac{\partial}{\partial x_j} \left(\mu \frac{\partial u_j}{\partial x_i} \right) + \frac{\partial}{\partial x_i} \left(-\frac{2}{3}\mu\Delta \right) \quad (9.32)$$

Since the order of differentiation should not matter and if μ is not a function of location,

$$\rho \frac{Du_i}{Dt} = \rho F_i - \frac{\partial p}{\partial x_i} + \frac{\partial}{\partial x_j} \left(\mu \frac{\partial u_i}{\partial x_j} \right) + \frac{\partial}{\partial x_i} \left(\mu \frac{\partial u_j}{\partial x_j} \right) + \frac{\partial}{\partial x_i} \left(-\frac{2}{3}\mu\Delta \right) \quad (9.33)$$

$$\rho \frac{Du_i}{Dt} = \rho F_i - \frac{\partial p}{\partial x_i} + \frac{\partial}{\partial x_j} \left(\mu \frac{\partial u_i}{\partial x_j} \right) + \frac{\partial}{\partial x_i} (\mu\Delta) + \frac{\partial}{\partial x_i} \left(-\frac{2}{3}\mu\Delta \right) \quad (9.34)$$

$$\boxed{\rho \frac{Du_i}{Dt} = \rho F_i - \frac{\partial p}{\partial x_i} + \frac{\partial}{\partial x_j} \left(\mu \frac{\partial u_i}{\partial x_j} \right) + \frac{1}{3} \frac{\partial}{\partial x_i} (\mu\Delta)} \quad (9.35)$$

The above set of three equations (for $i = 1, 2, 3$) corresponding to the three components of the velocity of the fluid (u_1 , u_2 and u_3) is called **Navier-Stokes equations**.

If the fluid being considered is incompressible, we can set the last term to zero and obtain the N-S equation with variable property.

A further simplification can be done starting from equation 9.35 as follows. Most of the fluids under normal flow conditions are *incompressible* ie., $\Delta = 0$. The Navier-Stokes equations for *incompressible* fluid flow with *constant viscosity* are obtained by taking μ out of the derivative and setting $\Delta = 0$ in the equation 9.35.

$$\begin{aligned} \rho \frac{Du_i}{Dt} &= \rho F_i - \frac{\partial p}{\partial x_i} + \mu \frac{\partial^2 u_i}{\partial x_j^2} + \mu \left(\frac{\partial^2 u_j}{\partial x_j \partial x_i} \right) \\ \rho \frac{Du_i}{Dt} &= \rho F_i - \frac{\partial p}{\partial x_i} + \mu \frac{\partial^2 u_i}{\partial x_j^2} + \mu \frac{\partial}{\partial x_i} \left(\frac{\partial u_j}{\partial x_j} \right) \\ \rho \frac{Du_i}{Dt} &= \rho F_i - \frac{\partial p}{\partial x_i} + \mu \frac{\partial^2 u_i}{\partial x_j^2} + \mu \frac{\partial}{\partial x_i} (\Delta) \\ \rho \frac{Du_i}{Dt} &= \rho F_i - \frac{\partial p}{\partial x_i} + \mu \frac{\partial^2 u_i}{\partial x_j^2} \end{aligned} \quad (9.36)$$

Expanding the material derivative $\frac{D}{Dt}$ and writing in vector notation:

$$\begin{aligned} \frac{\partial u_1}{\partial t} + (\vec{u} \cdot \vec{\nabla})u_1 &= F_1 - \frac{1}{\rho} \frac{\partial p}{\partial x_1} + \frac{\mu}{\rho} \nabla^2 u_1 \\ \frac{\partial u_2}{\partial t} + (\vec{u} \cdot \vec{\nabla})u_2 &= F_2 - \frac{1}{\rho} \frac{\partial p}{\partial x_2} + \frac{\mu}{\rho} \nabla^2 u_2 \\ \frac{\partial u_3}{\partial t} + (\vec{u} \cdot \vec{\nabla})u_3 &= F_3 - \frac{1}{\rho} \frac{\partial p}{\partial x_3} + \frac{\mu}{\rho} \nabla^2 u_3 \end{aligned} \quad (9.37)$$

These can be expanded to give the N-S equations for incompressible fluids of constant property using the definition of kinematic viscosity as follows:

$$\nu = \frac{\mu}{\rho}$$

$$\boxed{\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial x_1} + u_2 \frac{\partial u_1}{\partial x_2} + u_3 \frac{\partial u_1}{\partial x_3} = F_1 - \frac{1}{\rho} \frac{\partial p}{\partial x_1} + \nu \left(\frac{\partial^2 u_1}{\partial x_1^2} + \frac{\partial^2 u_1}{\partial x_2^2} + \frac{\partial^2 u_1}{\partial x_3^2} \right)} \quad (9.38)$$

$$\boxed{\frac{\partial u_2}{\partial t} + u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} + u_3 \frac{\partial u_2}{\partial x_3} = F_2 - \frac{1}{\rho} \frac{\partial p}{\partial x_2} + \nu \left(\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} + \frac{\partial^2 u_2}{\partial x_3^2} \right)} \quad (9.39)$$

$$\boxed{\frac{\partial u_3}{\partial t} + u_1 \frac{\partial u_3}{\partial x_1} + u_2 \frac{\partial u_3}{\partial x_2} + u_3 \frac{\partial u_3}{\partial x_3} = F_3 - \frac{1}{\rho} \frac{\partial p}{\partial x_3} + \nu \left(\frac{\partial^2 u_3}{\partial x_1^2} + \frac{\partial^2 u_3}{\partial x_2^2} + \frac{\partial^2 u_3}{\partial x_3^2} \right)} \quad (9.40)$$

The continuity equation 7.9 and the three N-S equations 9.35 are solved together to obtain fluid flow. In these four equations, we have four variables (p, u_1, u_2, u_3) - thus the problem is well defined.

Chapter 10

Navier-Stokes Equations - Part 2

10.1 Significance of the linear relation and Viscosity

The linear relation between the deviatoric stress tensor and the strain rate tensor (velocity gradient) is physically meaningful for a large number of fluids. Consider the two dimensional case of pure shear stress applied on a layer of liquid. Newton has observed that the shear stress is directly proportional to the velocity gradient.

$$d_{12} = d_{21} = \mu \frac{\partial u_1}{\partial x_2} \quad (10.1)$$

The proportionality constant μ is *defined* as the **viscosity** of the liquid. Fluids that obey this linear relation are called *Newtonian fluids*. Examples are water, air and most gases (in most of the situations except under shock wave) and liquid metals.

Based on their viscosity and the way they flow, materials can be classified as follows:

10.1 Understand (Fluid Flow). *List different types of fluids in contrast with Newtonian fluid*

Newtonian fluid : Strain rate or velocity gradient is linearly dependent on the shear stress as $\sigma_{12} = \mu u_{1,2}$. Eg: air and most of the gases, water, oils of low molecular weight and liquid metals. Often σ_{12} is referred to as τ_{xy} .

Bingham Plastic : Flow starts above a critical shear stress which is then linear with the strain rate. $\sigma_{12} = \sigma_0 + \mu u_{1,2}$. Eg: drilling muds, peat slurries, margarine, chocolate mixtures, greases, soap, grain-water suspensions, toothpaste, paper pulp, and sewage sludge.

Pseudoplastic : Shear thinning material - viscosity decreases at higher strain rate.

Dilatant : Shear thickening material - viscosity increases at higher strain rate.

Thixotropic : Viscosity decrease with time.

Rheopectic : Viscosity increases with time.

Viscoelastic : The material returns back to its original shape after the stress is removed.




Figure 10.1: Types of fluids

Viscosity is a strong function of temperature. In liquid metals viscosity follows an *Arrhenius* relation. In situations where the temperature is roughly constant through out the flow, viscosity can be taken as constant. For fluids such as air and water, viscosity is negligible for most of the situations. Such fluids are called *inviscid*.

10.2 Reynold's number

Consider the characteristic length scale of a domain to be L . This could be the diameter of a tube through which the fluid flows, the length along a plate over which the fluid flows, the separation between two walls between which the fluid flows and so on. Let U_0 be the characteristic velocity. This could be the maximum or average or externally imposed velocity. The characteristic time scale would then be L/U_0 . Using these, the Navier-Stokes equation can be non-dimensionalized as follows. We take $x_1^* = x_1/L$ as non-dimensionalized distance, $t^* = tU_0/L$ as non-dimensionalized time etc. The non-dimensional velocities are $u_1^* = u_1/U_0$ etc.

$$\frac{\partial}{\partial x_1} = \frac{\partial}{\partial x_1^*} \frac{1}{L}$$

$$\frac{\partial}{\partial t} = \frac{\partial}{\partial t^*} \frac{U_0}{L}$$

Substitute these into the equation 9.38 to obtain:

$$\frac{U_0^2}{L} \left[\frac{\partial u_1^*}{\partial t^*} + u_1^* \frac{\partial u_1^*}{\partial x_1^*} + u_2^* \frac{\partial u_1^*}{\partial x_2^*} + u_3^* \frac{\partial u_1^*}{\partial x_3^*} \right] = F_1 - \frac{1}{\rho L} \frac{\partial p}{\partial x_1^*} + \frac{\nu U_0}{L^2} \left(\frac{\partial^2 u_1^*}{\partial x_1^{*2}} + \frac{\partial^2 u_1^*}{\partial x_2^{*2}} + \frac{\partial^2 u_1^*}{\partial x_3^{*2}} \right) \quad (10.2)$$

Gather the terms to obtain:

$$\frac{\partial u_1^*}{\partial t^*} + u_1^* \frac{\partial u_1^*}{\partial x_1^*} + u_2^* \frac{\partial u_1^*}{\partial x_2^*} + u_3^* \frac{\partial u_1^*}{\partial x_3^*} = \frac{L}{U_0^2} F_1 - \frac{1}{\rho U_0^2} \frac{\partial p}{\partial x_1^*} + \frac{\nu}{LU_0} \left(\frac{\partial^2 u_1^*}{\partial x_1^{*2}} + \frac{\partial^2 u_1^*}{\partial x_2^{*2}} + \frac{\partial^2 u_1^*}{\partial x_3^{*2}} \right) \quad (10.3)$$

Now we can consider that U_0^2/L as the scaling factor for F_1 so that non-dimensional force $F_1^* = F_1 L / U_0^2$. Similarly, the scaling factor for pressure can be taken as ρU_0^2 so that non-dimensional pressure $p^* = p / \rho U_0^2$.

$$\frac{\partial u_1^*}{\partial t^*} + u_1^* \frac{\partial u_1^*}{\partial x_1^*} + u_2^* \frac{\partial u_1^*}{\partial x_2^*} + u_3^* \frac{\partial u_1^*}{\partial x_3^*} = F_1^* - \frac{\partial p^*}{\partial x_1^*} + \frac{\nu}{LU_0} \left(\frac{\partial^2 u_1^*}{\partial x_1^{*2}} + \frac{\partial^2 u_1^*}{\partial x_2^{*2}} + \frac{\partial^2 u_1^*}{\partial x_3^{*2}} \right) \quad (10.4)$$

The scaling factor for the diffusive term in the above equation can be taken as follows:

$$\boxed{Re_L \equiv \frac{LU_0}{\nu} \equiv \frac{LU_0 \rho}{\mu}} \quad (10.5)$$

Thus the non-dimensionalised Navier-Stokes equation for incompressible Newtonian fluid comes to be:

$$\frac{\partial u_1^*}{\partial t^*} + u_1^* \frac{\partial u_1^*}{\partial x_1^*} + u_2^* \frac{\partial u_1^*}{\partial x_2^*} + u_3^* \frac{\partial u_1^*}{\partial x_3^*} = F_1^* - \frac{\partial p^*}{\partial x_1^*} + \frac{1}{Re_L} \left(\frac{\partial^2 u_1^*}{\partial x_1^{*2}} + \frac{\partial^2 u_1^*}{\partial x_2^{*2}} + \frac{\partial^2 u_1^*}{\partial x_3^{*2}} \right) \quad (10.6)$$

The Reynold's number Re_L is now a measure of the importance of the diffusive term in the Navier-Stokes equation while determining the fluid flow evolution. In the limit of $Re_L \rightarrow 0$ the flow field is expected to be governed mainly by the diffusive term.

The subscript used with Reynold's number will be indicative of the characteristic length scale. A bar on the top, like $\bar{Re}$ indicates the use of average velocity for non-dimensionalization.

10.3 Equations in cylindrical co-ordinate system

We should choose a co-ordinate system with an orientation that best captures the symmetry of the problem and simplifies the final form of the solution.

Equations 9.37 are written for constant properties (ρ and μ) and using the operators $\vec{\nabla}$ and ∇^2 . These operators convey a meaning independent of co-ordinate system and enable us to assign a meaning to each term in the equation.

One can (with some endurance) derive the equations by expressing x_1, x_2, x_3 in terms of r, θ, z for cylindrical co-ordinate system or r, θ, ϕ for spherical co-ordinate system and derive the necessary relations. The expansion of these operators and the N-S equations for cylindrical co-ordinate system can be borrowed from Appendix A of [Bird et al., 2002]. Following are the expressions that will be of use to us later.

The velocity vector has the components as follows:

$$\vec{u} = u_r \hat{e}_r + u_\theta \hat{e}_\theta + u_z \hat{e}_z \quad (10.7)$$

The operator $\vec{\nabla}$ is defined as:

$$\vec{\nabla} = \frac{\partial}{\partial r} \hat{e}_r + \frac{1}{r} \frac{\partial}{\partial \theta} \hat{e}_\theta + \frac{\partial}{\partial z} \hat{e}_z \quad (10.8)$$

Remember the following relations before applying the operator directly:

$$\frac{\partial \hat{e}_r}{\partial \theta} = \hat{e}_\theta \quad (10.9)$$

$$\frac{\partial \hat{e}_\theta}{\partial \theta} = -\hat{e}_r \quad (10.10)$$

10.3.1 Continuity equation

Divergence of the velocity vector or continuity equation for an incompressible fluid is written as:

$$\frac{1}{r} \frac{\partial (ru_r)}{\partial r} + \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} + \frac{\partial u_z}{\partial z} = 0 \quad (10.11)$$

10.3.2 Other operators

The curl of velocity vector is given by the following:

$$\vec{\nabla} \times \vec{u} = \left[\frac{1}{r} \frac{\partial u_z}{\partial \theta} - \frac{\partial u_\theta}{\partial z} \right] \hat{e}_r + \left[\frac{\partial u_r}{\partial z} - \frac{\partial u_z}{\partial r} \right] \hat{e}_\theta + \frac{1}{r} \left[\frac{\partial (ru_\theta)}{\partial r} - \frac{\partial u_r}{\partial \theta} \right] \hat{e}_z \quad (10.12)$$

Laplacian operator for a scalar function can be given as:

$$\nabla^2 = \frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2}{\partial \theta^2} + \frac{\partial^2}{\partial z^2} \quad (10.13)$$

$$\vec{u} \cdot \vec{\nabla} = u_r \frac{\partial}{\partial r} + \frac{u_\theta}{r} \frac{\partial}{\partial \theta} + u_z \frac{\partial}{\partial z} \quad (10.14)$$

10.3.3 Stress components

Normal and shear stresses for constant density and viscosity are given as follows:

$$\sigma_{rr} = -p + 2\mu \frac{\partial u_r}{\partial r} \quad (10.15)$$

$$\sigma_{\theta\theta} = -p + 2\mu \left[\frac{1}{r} \frac{\partial u_\theta}{\partial \theta} + \frac{u_r}{r} \right] \quad (10.16)$$

$$\sigma_{zz} = -p + 2\mu \frac{\partial u_z}{\partial z} \quad (10.17)$$

$$\tau_{r\theta} = \mu \left[r \frac{\partial}{\partial r} \left(\frac{u_\theta}{r} \right) + \frac{1}{r} \frac{\partial u_r}{\partial \theta} \right] \quad (10.18)$$

$$\tau_{\theta z} = \mu \left[\frac{\partial u_\theta}{\partial z} + \frac{1}{r} \frac{\partial u_z}{\partial \theta} \right] \quad (10.19)$$

$$\tau_{rz} = \mu \left[\frac{\partial u_r}{\partial z} + \frac{\partial u_z}{\partial r} \right] \quad (10.20)$$

10.3.4 Navier-Stokes equations in cylindrical co-ordinate system

Most of the time we are concerned about incompressible fluids of approximately constant properties. Hence we can borrow the N-S equations in cylindrical co-ordinate system for momentum transfer with these assumptions as reproduced below:

In these equations, kinematic viscosity $\nu \equiv \mu/\rho$ is used to simplify expressions.

$$\begin{aligned} \frac{\partial u_r}{\partial t} + u_r \frac{\partial u_r}{\partial r} + \frac{u_\theta}{r} \frac{\partial u_r}{\partial \theta} + u_z \frac{\partial u_r}{\partial z} - \frac{u_\theta^2}{r} &= F_r - \frac{1}{\rho} \frac{\partial p}{\partial r} \\ + \nu \left[\frac{\partial}{\partial r} \left(\frac{1}{r} \frac{\partial \{ru_r\}}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2 u_r}{\partial \theta^2} - \frac{2}{r^2} \frac{\partial u_\theta}{\partial \theta} + \frac{\partial^2 u_r}{\partial z^2} \right] \end{aligned} \quad (10.21)$$

$$\begin{aligned} \frac{\partial u_\theta}{\partial t} + u_r \frac{\partial u_\theta}{\partial r} + \frac{u_\theta}{r} \frac{\partial u_\theta}{\partial \theta} + \frac{u_r u_\theta}{r} + u_z \frac{\partial u_\theta}{\partial z} &= F_\theta - \frac{1}{\rho r} \frac{\partial p}{\partial \theta} \\ + \nu \left[\frac{\partial}{\partial r} \left(\frac{1}{r} \frac{\partial \{ru_\theta\}}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2 u_\theta}{\partial \theta^2} + \frac{2}{r^2} \frac{\partial u_r}{\partial \theta} + \frac{\partial^2 u_\theta}{\partial z^2} \right] \end{aligned} \quad (10.22)$$

$$\begin{aligned} \frac{\partial u_z}{\partial t} + u_r \frac{\partial u_z}{\partial r} + \frac{u_\theta}{r} \frac{\partial u_z}{\partial \theta} + u_z \frac{\partial u_z}{\partial z} &= F_z - \frac{1}{\rho} \frac{\partial p}{\partial z} \\ + \nu \left[\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial u_z}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2 u_z}{\partial \theta^2} + \frac{\partial^2 u_z}{\partial z^2} \right] \end{aligned} \quad (10.23)$$

Chapter 11

Specific cases of fluid flow - Planar

11.1 Learning objectives

At the end of this lesson, a student should be able to

1. identify the domain, write down boundary conditions and list the allowed assumptions given a flow problem description
2. identify and justify terms of Navier-Stokes equation that can be dropped in a given problem
3. integrate simple partial differential equations across the domain of a flow problem
4. apply boundary conditions to determine integration constants of a flow field solution
5. plot velocity and stress profile across the domain for a flow problem

11.2 Boundary Conditions and Problem Definitions

Fluid-Solid: Due to van der Waals attractions, wetting and any other atomistic phenomena, liquid tends to stick to solid and a relative motion is not possible¹. In most of the situation this phenomena of a solid preventing a liquid in contact with it from having a motion relative to it is called *no slip condition*. Often the solid wall is stationary making the velocity of liquid at the wall zero.

$$u|_{\text{liquid, interface}} = u|_{\text{solid}}$$

Fluid-Liquid: Using the arguments similar to above, there is no relative motion between two layers of liquids in contact with each other². Additionally, since most liquids wet each other, the shear stress at the interface of two liquids has a unique value.

$$\tau|_{\text{liquid1, interface}} = \tau|_{\text{liquid2, interface}}$$

For Newtonian fluids, if we take the interface to be at zero,

$$\mu_1 \left. \frac{\partial u_i}{\partial x_j} \right|_{x_j \rightarrow -0} = \mu_2 \left. \frac{\partial u_i}{\partial x_j} \right|_{x_j \rightarrow +0}$$

¹except under situations where surface tension plays a major role

²except in situations where the two liquids in contact with each other are immiscible and interfacial tension plays a major role

Fluid-Gas: Because the density of gas is usually much smaller than that of liquid, it cannot sustain any shear stress at the top of the liquid layer and will lead to surface deformation. Thus, the shear stress at a *free surface* is zero.

$$\tau|_{\text{liquid, free surface}} = 0$$

For Newtonian fluids, if we take the interface to be at zero,

$$\left. \frac{\partial u_i}{\partial x_j} \right|_{x_j \rightarrow 0} = 0$$

Steady state: Time derivative of the velocity is to be taken zero.

$$\frac{\partial u_i}{\partial t} = 0$$

Unidirectional flow: Velocity has only one component and the other components are to be taken zero.

$$u_2 = u_3 = 0 \neq u_1$$

Fully developed flow: The velocity has no variation along the direction of the flow.

$$\frac{\partial u_i}{\partial x_i} = 0$$

Validity of solution: The analytical solutions given in this chapter are applicable for *laminar regime* of fluid flow where the flow can be visualised as layers of liquid moving with respect to each other and the effects of wall penetrate far into the liquid. When the inertial forces acting on the fluid are far greater than the viscous forces, such an assumption is not valid and the flow is said to be *turbulent*. A transition from *laminar* to *turbulent* regimes is governed by the non-dimensional number indicating the ratio of inertial to viscous forces and is named after **Reynolds**.

$$Re = \frac{\rho D u_0}{\mu} = \frac{D u_0}{\nu}$$

D is the characteristic length scale (diameter for a tube flow, width of channel for flow between two parallel plates etc.), u_0 is the characteristic velocity (typically the average velocity or far field velocity) and ν is the kinematic viscosity.

Range of Re for validity of a laminar solution for a problem of certain geometry is obtained from careful experiments.

Equivalent diameter: For tubes of non-circular cross sections or for other geometries, the equivalent diameter can be defined as

$$D_e = \frac{4 \times \text{cross sectional area}}{\text{wetted perimeter}}$$

Thus, for the case of flow between two parallel plates separated by a distance of 2δ that is much smaller than the width of the plates W , $D_e = 4\delta$.




Figure 11.1: Problem domain to recover Newton's Law

11.3 Trivial case reproducing Newton's Law

Figure 11.1 shows the problem definition.

Assumptions:

- Flow is unidirectional. Only u_1 is to be known, u_2 and u_3 are zero.
- Flow is steady state. $\frac{\partial u_1}{\partial t} = 0$.
- Flow is fully developed. $\frac{\partial u_1}{\partial x_1} = 0$.
- Flow is entirely due to the top surface being moved at $u_{1,max}$ and no body force or pressure gradients exist.

Boundary Conditions:

- No slip condition at bottom layer: at $y = 0$, $u_1 = 0$.
- No slip condition at top layer: at $y = \delta$, $u_1 = u_{1,max}$.

Solution: Use N-S equation for u_1 and eliminate terms as per the assumptions above.

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial x_1} + u_2 \frac{\partial u_1}{\partial x_2} + u_3 \frac{\partial u_1}{\partial x_3} = F_1 - \frac{1}{\rho} \frac{\partial p}{\partial x_1} + \nu \left(\frac{\partial^2 u_1}{\partial x_1^2} + \frac{\partial^2 u_1}{\partial x_2^2} + \frac{\partial^2 u_1}{\partial x_3^2} \right) \quad (11.1)$$

$$\nu \frac{\partial^2 u_1}{\partial x_2^2} = 0 \quad (11.2)$$

or

$$u_1 = Ax_2 + B \quad (11.3)$$

Using the boundary conditions,

$$A = \frac{u_{1,max}}{\delta}$$

$$B = 0$$

or

$$u_1 = u_{1,max} \frac{y}{\delta}$$

Using Newton's law

$$\sigma_{21} = \tau_{yx} = \mu \frac{\partial u_1}{\partial x_2}$$

$$\tau_{yx} = \mu \frac{u_{1,max}}{\delta}$$

The solution is plotted schematically in figure 11.2.




Figure 11.2: Velocity and Stress distribution in the Newton's Law problem

Convention: σ_{12} or τ_{12} is on plane 1 and in the direction 2. As for the sign, there are two different conventions adapted in the literature.

Convention +:

In the above case, we have used the convention that the shear stress is positive and it is exerted by the top layer on the fluid beneath it so that Newton's law is written as $\tau_{21} = \mu \frac{\partial u_1}{\partial x_2}$.

Shear stress τ_{yx} is stress exerted on plane y in the positive direction x by the layer at *greater* y on the layer at *lesser* y .

This is the convention adapted in this handout.

Convention -:

This is favoured by [Bird et al., 2002] for the reasons quoted below.

Shear stress τ_{xy} is stress exerted on plane x in direction y by the layer at *lesser* y on the layer at *greater* y .

Quoting from [Bird et al., 2002] section 1.2, page 19:

Note on the Sign Convention for the Stress Tensor We have emphasised in connection with Eq. 1.1-2 (and in the generalization in this section) that τ_{yx} is the force in the positive x direction on a unit area perpendicular to the y direction, this being the force per unit area exerted by the fluid in the region of the *lesser* y on the fluid of *greater* y . In most fluid dynamics and elasticity books, the words "lesser" and "greater" are interchanged and Eq 1.1-2 is written as $\tau_{yx} = +\mu(dv_x/dy)$. The advantages of the sign convention used in this book are: (a) the sign convention used in Newton's law of viscosity is consistent with that used in Fourier's law of heat conduction and Fick's law of diffusion; (b) the sign convention used for τ_{ij} is the same as that for convective momentum flux $\rho \mathbf{v} \mathbf{v}$ (see section 1.7 and Table 19.2-2); (c) in Eq 1.2-2, the terms $p\delta_{ij}$ and τ_{ij} have the same sign affixed, and the terms p and τ_{ii} are both positive in compression (in accordance with common usage in thermodynamics); (d) all terms in the entropy production in Eq. 24.1-5 have the same sign. Clearly the sign convention in Eqs. 1.1-2 and 1.2-6 is arbitrary, and either sign convention can be used, provided the physical meaning of the sign convention is clearly understood.

Note: Figure 2.8 of [Gaskell, 1992] shows a symmetric plot of velocity profile as well as shear stress profile for a channel flow. There is an error in the shear stress profile. Watch out!

11.4 Film flow

Consider the case of a film of liquid falling on an inclined plane as shown in figure 11.3.




Figure 11.3: Schematic of a film flow problem

Assumptions:

- Flow is unidirectional. Only u_1 needs to be known, $u_2 = u_3 = 0$.
- Flow is steady state: $\frac{\partial u_1}{\partial t} = 0$.
- Flow is fully developed i.e., it varies only along x_2 but not along x_1 or x_3 . $\frac{\partial u_1}{\partial x_1} = 0$ for all x_1 .
- The only driving force for the film to fall is gravity: $\vec{F} = g \cos \theta \hat{x}_1 + g \sin \theta \hat{x}_2$.

Boundary conditions:

- Thickness of the film is δ .
- No slip condition at the bottom of the plane: at $x_2 = \delta$, $u_1 = 0$.
- At $x_2 = 0$, there is a free surface on which the shear stresses are zero. $\mu \frac{\partial u_1}{\partial x_2} = 0$ at $x_2 = 0$.

Solution: Use N-S equation for u and eliminate terms as per the assumptions above.

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial x_1} + u_2 \frac{\partial u_1}{\partial x_2} + u_3 \frac{\partial u_1}{\partial x_3} = F_1 - \frac{1}{\rho} \frac{\partial p}{\partial x_1} + \nu \left(\frac{\partial^2 u_1}{\partial x_1^2} + \frac{\partial^2 u_1}{\partial x_2^2} + \frac{\partial^2 u_1}{\partial x_3^2} \right) \quad (11.4)$$

$$0 = g \cos \theta + \nu \frac{\partial^2 u_1}{\partial x_2^2} \quad (11.5)$$

$$\frac{\partial^2 u_1}{\partial x_2^2} = -\frac{\rho g \cos \theta}{\mu}$$

$$u_1 = -\frac{\rho g \cos \theta x_2^2}{2\mu} + C_1 x_2 + C_2$$

Using the boundary conditions, $C_1 = 0$.

$$C_2 = \frac{\rho g \cos \theta \delta^2}{2\mu}$$

Hence,

$$u_1 = \frac{\rho \delta^2 g \cos \theta}{2\mu} \left[1 - \left(\frac{x_2}{\delta} \right)^2 \right]$$

$$u_1|_{max} = \frac{\rho \delta^2 g \cos \theta}{2\mu}$$

Using Newton's law

$$\sigma_{21} = \tau_{yx} = \mu \frac{\partial u_1}{\partial x_2}$$

$$\tau_{yx} = -\rho g \cos \theta x_2$$

$$\bar{u}_1 = \frac{\int_0^\delta u_1 dx_2}{\delta} = \frac{\rho \delta^2 g \cos \theta}{3\mu} = \frac{2}{3} u_1|_{max}$$

If W is the width of the plane, mass flow rate $\dot{M}$ is:

$$\dot{M} = \rho W \delta \bar{u}_1 = \frac{\rho^2 \delta^3 W g \cos \theta}{3\mu}$$

The solutions are plotted schematically in figure 11.4.

Validity:

$$Re = \frac{4\delta \rho \bar{u}_1}{\mu} \leq 25$$




Figure 11.4: Velocity and Stress distribution in a film flow problem

11.5 Flow between two plates




Figure 11.5: Flow in a channel

Figure 11.5 shows the problem definition. We choose the axes to make the maximum out of the symmetry of the problem.

Assumptions:

- Flow is unidirectional. Only u_1 is to be known, u_2 and u_3 are zero.
- Flow is steady state. $\frac{\partial u_1}{\partial t} = 0$.
- Flow is fully developed. $\frac{\partial u_1}{\partial x_1} = 0$.
- Pressure gradient is constant $-\frac{\partial p}{\partial x_1} = \frac{p_H - p_L}{L}$

Boundary Conditions:

- No slip condition at bottom layer: at $y = -\delta$, $u_1 = 0$.
- No slip condition at top layer: at $y = \delta$, $u_1 = 0$.

Use N-S equation for u_1 and eliminate terms as per the assumptions above.

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial x_1} + u_2 \frac{\partial u_1}{\partial x_2} + u_3 \frac{\partial u_1}{\partial x_3} = F_1 - \frac{1}{\rho} \frac{\partial p}{\partial x_1} + \nu \left(\frac{\partial^2 u_1}{\partial x_1^2} + \frac{\partial^2 u_1}{\partial x_2^2} + \frac{\partial^2 u_1}{\partial x_3^2} \right) \quad (11.6)$$

$$\nu \frac{\partial^2 u_1}{\partial x_2^2} = \frac{1}{\rho} \frac{\partial p}{\partial x_1} = \frac{p_L - p_H}{\rho L} \quad (11.7)$$

or

$$\frac{\partial^2 u_1}{\partial x_2^2} = -2A \quad (11.8)$$

$$A = \frac{p_H - p_L}{2L\mu}$$

$$u_1 = -Ax_1^2 + Bx_1 + C$$

Using the boundary conditions,

$$u_1 = \frac{p_H - p_L}{L} \frac{\delta^2 - x_2^2}{2\mu}$$

Using Newton's law

$$\sigma_{21} = \tau_{21} = \mu \frac{\partial u_1}{\partial x_2}$$

$$\tau_{21} = \frac{p_H - p_L}{2L} (-2x_2)$$

Maximum velocity:

$$u_1|_{max} = \frac{p_H - p_L}{L} \frac{\delta^2}{2\mu}$$

Average velocity:

$$\bar{u}_1 = \frac{2}{3} u_1|_{max} = \frac{p_H - p_L}{L} \frac{\delta^2}{3\mu}$$

The solutions are plotted schematically in figure 11.6.




Figure 11.6: Flow in a channel

Interpretation of τ_{21} . At $x_2 = 0$, $\tau_{21} = +A\mu\delta$. Recollecting **convention** + we are using for Newton's law, the shear stress is exerted by the layer at *greater* x_2 on the layer at *lesser* x_2 ie., by the liquid on the wall. At $x_2 = \delta$, $\tau_{21} = -A\mu\delta$. The shear stress is exerted by the layer at *greater* x_2 on the layer at *lesser* x_2 ie., by the wall on the liquid (thus the negative sign).

Exercise 11.5.53

Mixing film: Problem 2B.3 and 2B.4 of [Bird et al., 2002]. An incompressible Newtonian fluid is contained between two long plates of width $W = 1$ m (along z) and a distance $B = 1$ mm apart as shown in figure 11.7 below. The plate on the right is moved upwards




Figure 11.7: Schematic of a film mixing problem

at a velocity v_0 . Gravity $g = 9.81 \text{ m s}^{-2}$ acts along y axis downwards, density of fluid $\rho = 1000 \text{ kg m}^{-3}$ and viscosity of fluid 0.01 Pa s . Assume the flow is uniaxial, steady state and fully developed. (a) Calculate v_0 such that the net volume flow rate across a y plane is zero. (b) What is the ratio of the width of the fluid layer that flows downwards to the width of the fluid layer that flows upwards. (c) Sketch a schematic of the flow field.

Solution 11.5.53

Exercise 11.5.54

Slag film: Problem 2.5 of [Gaskell, 1992]. A layer of molten slag of density 2700 kg m^{-3} and viscosity 0.3 Pa s is being transferred from one reverberatory furnace to another by flow down a plane between the two furnaces inclined at 10° to the horizontal. The plane is 5 m in width and 5 m in length and the mass flow rate of the slag is 7.5 kg s^{-1} . Neglecting the end effects, calculate (a) thickness of the slag layer (b) average linear flow velocity of the slag and (c) mean residence time of slag on the plane. (d) Fraction of slag that remains on the plane for times equal to or greater than the mean residence time.

Solution 11.5.54

Answer: (a) $4.77 \times 10^{-3} \text{ kg m}^{-1} \text{ s}^{-1}$ (b) 0.116 m s^{-1} (c) 43 s (d) 0.423

Exercise 11.5.55

Squeegee device: A continuous sheet (1.5 m wide) of metal is cold-rolled by passing vertically between rolls at a constant speed of 0.3 m s^{-1} . Before entering the rolls, the sheet passes through a tank of lubricating oil equipped with a squeegee device that coats both sides of the sheet uniformly as it exits. The amount of oil that is carried through can be controlled by the squeegee device. Determine the mass rate of oil as a function of thickness of oil film that usually range between 0 mm and 0.6 mm . Properties of the lubricating oil: $\rho = 962 \text{ kg m}^{-3}$, $\mu = 4.1 \times 10^{-3} \text{ Pa s}$.




Figure 11.8: Squeegee device

Solution 11.5.55

Chapter 12

Specific cases of fluid flow - Cylindrical

12.1 Flow through a pipe




Figure 12.1: Pipe Flow

Figure 12.1 shows the problem definition.

Assumptions:

- Flow is unidirectional: Only u_z is to be known, u_r and u_θ are zero
- Flow is steady state: $\frac{\partial u_z}{\partial t} = 0$
- Flow is fully developed: $\frac{\partial u_z}{\partial z} = 0$
- Pressure gradient is constant: $\frac{\partial p}{\partial z} = \frac{\Delta p}{L}$

Boundary Conditions:

- No slip condition at pipe wall: at $r = R$, $u_z = 0$.
- Finite velocity at center: at $r = 0$, $u_z \neq \infty$.

Use N-S equation in cylindrical co-ordinate system for u_z and eliminate terms as per the assumptions above.

$$\begin{aligned} \frac{\partial u_z}{\partial t} + u_r \frac{\partial u_z}{\partial r} + \frac{u_\theta}{r} \frac{\partial u_z}{\partial \theta} + u_z \frac{\partial u_z}{\partial z} = F_z - \frac{1}{\rho} \frac{\partial p}{\partial z} \\ + \nu \left[\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial u_z}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2 u_z}{\partial \theta^2} + \frac{\partial^2 u_z}{\partial z^2} \right] \end{aligned} \quad (12.1)$$

$$0 = F_z - \frac{1}{\rho} \frac{\Delta p}{L} + \frac{\mu}{\rho} \frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial u_z}{\partial r} \right)$$

$$u_z = - \left[\frac{\rho F_z}{4\mu} - \frac{1}{4\mu} \frac{\Delta p}{L} \right] r^2 + C_1 \ln(r) + C_2$$

Using boundary conditions,

$$\begin{aligned} C_1 &= 0 \\ C_2 &= \left[\frac{\rho F_z}{4\mu} - \frac{1}{4\mu} \frac{\Delta p}{L} \right] R^2 \end{aligned}$$

$$u_z = \left[\frac{\rho F_z}{4\mu} - \frac{1}{4\mu} \frac{\Delta p}{L} \right] (R^2 - r^2)$$

Using Newton's law

$$\begin{aligned} \sigma_{21} = \tau_{zr} &= \mu \frac{\partial u_z}{\partial r} \\ \tau_{zr} &= \left[\frac{\rho F_z}{4\mu} - \frac{1}{4\mu} \frac{\Delta p}{L} \right] (-2r) \end{aligned}$$

The solution is plotted schematically in figure 13.3.

$$u_z|_{max} = \left[\frac{\rho F_z}{4\mu} - \frac{1}{4\mu} \frac{\Delta p}{L} \right] R^2$$

Average flow velocity $\bar{u}_z$:

$$\bar{u}_z = \frac{\int_0^R u_z 2\pi r dr}{\int_0^R 2\pi r dr} = \frac{1}{2} u_z|_{max}$$

Volume flow rate $\dot{V}$:

$$\dot{V} = \pi r^2 \bar{u}_z = \left[\frac{\rho F_z}{8\mu} - \frac{1}{8\mu} \frac{\Delta p}{L} \right] \pi R^4$$

Mass flow rate $\dot{M}$ (Hagen-Poiseuille Equation):

$$\dot{M} = \rho \dot{V} = \left[\frac{\rho^2 F_z}{8\mu} - \frac{\rho}{8\mu} \frac{\Delta p}{L} \right] \pi R^4$$

Exercise 12.1.56

Axial film flow: Problem 2B.7 of [Bird et al., 2002]. A cylindrical rod of radius kR moves axially with velocity $v = v_0$ along the axis of a cylindrical cavity of radius R as shown in figure below. Assuming that the pressure at both ends of the cavity is same and fluid flows through the annular region only because of the rod motion. (a) Find the velocity distribution in the narrow annular region. (b) Find the mass flow rate through the annular




Figure 12.2: Solution to Pipe Flow




Figure 12.3: Axial film flow

region. (c) Obtain the viscous force acting on the rod over a length L .

Solution 12.1.56

(a)

$$\frac{u_z}{u_0} = \frac{\ln(r/R)}{\ln k}$$

(b)

$$\dot{M} = \frac{\pi R^2 u_0 \rho}{2} \left(\frac{1 - k^2}{\ln(1/k)} - 2k^2 \right)$$

(c)

$$F_z = \frac{2\pi L \mu u_0}{\ln(1/k)}$$

Exercise 12.1.57

Leaking tank: Water of viscosity $\mu = 0.01 \text{ Pa s}$ and density $\rho = 1000 \text{ kg m}^{-3}$ from a large tank is to be transported using a rigid smooth tube of 1 cm dia connected at the bottom across a distance of $L = 100 \text{ m}$ as shown in figure 12.4. Assuming that at steady state the tank is large enough that the height of water in it (h) does not change much in time, what should be h such that the flow rate in the tube is one litre per minute.




Figure 12.4: Leaking Tank


Solution 12.1.57

Figure 12.5: Cubic network of pipes

Exercise 12.1.58

Cubic network of pipes: Problem 2B.12 of [Bird et al., 2002]. A fluid is flowing in laminar flow from A to B through a network of tubes, as depicted in figure 12.5. Obtain an expression for the mass flow rate w of the fluid entering at A (or leaving at B) as a function of the modified pressure drop $p_A - p_B$. Neglect the disturbances at the various tube junctions. Neglect any body forces that may act on some of the segments due to their orientation.

Solution 12.1.58

Writing volume flow rate through each pipe at junctions as follows:

At junction 2:

$$V_{A2} = V_{26} + V_{24}$$

$$\frac{p_2 - p_A}{L} D^4 \frac{\pi}{8\mu} = \frac{p_6 - p_2}{L} D^4 \frac{\pi}{8\mu} + \frac{p_4 - p_2}{L} D^4 \frac{\pi}{8\mu}$$

$$p_A = 3p_2 - p_4 - p_6$$

Skip the term $\frac{D^4 \pi}{L 8\mu}$ for the remaining equations.

At junction 3:

$$V_{A3} = V_{36} + V_{35}$$

$$(p_3 - p_A) = (p_6 - p_3) + (p_5 - p_3)$$

$$p_A = 3p_3 - p_5 - p_6$$

At junction 6:

$$V_{36} + V_{26} = V_{6B}$$

$$\frac{p_6 - p_3}{L} D^4 + \frac{p_6 - p_2}{L} D^4 = \frac{p_B - p_6}{L} D^4$$

$$p_B = 3p_6 - p_2 - p_3$$

Add the above three to obtain:

$$3p_B = 3(p_4 + p_5 + p_6) - 2(p_1 + p_2 + p_3)$$

At junction 5:

$$V_{35} + V_{15} = V_{5B}$$

$$\frac{p_5 - p_3}{L} D^4 + \frac{p_5 - p_1}{L} D^4 = \frac{p_B - p_5}{L} D^4$$

$$p_B = 3p_5 - p_3 - p_1$$

At junction 1:

$$V_{A1} = V_{15} + V_{14}$$

$$\frac{p_1 - p_A}{L} D^4 = \frac{p_5 - p_1}{L} D^4 + \frac{p_4 - p_1}{L} D^4$$

$$p_A = 3p_1 - p_4 - p_5$$

At junction 4:

$$V_{14} + V_{24} = V_{4B}$$

$$\frac{p_4 - p_1}{L} D^4 + \frac{p_4 - p_2}{L} D^4 = \frac{p_B - p_4}{L} D^4$$

$$p_B = 3p_4 - p_1 - p_2$$

Add the above three to obtain:

$$3p_A = 3(p_1 + p_2 + p_3) - 2(p_4 + p_5 + p_6)$$

Write the flow rate at junction A:

$$V_A = V_{A1} + V_{A2} + V_{A3}$$

$$V_A = (p_1 - p_A + p_2 - p_A + p_3 - p_A) \frac{D^4 \pi}{L 8\mu}$$

$$V_A = (p_1 + p_2 + p_3 - 3p_A) \frac{D^4}{L} \frac{\pi}{8\mu}$$

Multiply the equations with 2 and 3 to add to eliminate $p_4 + p_5 + p_6$ term and give:

$$6p_B + 9p_A = 6(p_4 + p_5 + p_6) - 4(p_1 + p_2 + p_3) + 9(p_1 + p_2 + p_3) - 6(p_4 + p_5 + p_6)$$

$$6p_B + 9p_A = 5(p_1 + p_2 + p_3)$$

Now, using the equation for V_A , we can write:

$$V_A = \left(\frac{6p_B + 9p_A}{5} - 3p_A \right) \frac{D^4}{L} \frac{\pi}{8\mu}$$

$$V_A = \frac{6\pi}{40\mu} (p_B - p_A) \frac{D^4}{L}$$

$$V_A = \frac{3\pi}{20\mu} (p_B - p_A) \frac{D^4}{L}$$

$$\dot{M} = \frac{3\pi (p_A - p_B) R^4 \rho}{20\mu L}$$

Exercise 12.1.59

Blasius equation: Section 4.1 of [Gaskell, 1992]. For steady viscous flow through a circular tube, the axial velocity profile is given approximately by the Blasius' equation below.

$$u = u_0 \left(1 - \frac{r}{R} \right)^m$$

For turbulent flow, $m = 1/7$. Assuming the density is constant, what is the average velocity? Is it closer to the maximum than in the case of Poiseuille flow? Comment.

Solution 12.1.59

$$0.817u_0$$

Exercise 12.1.60

Channel flow between porous walls: Problem 3B.16 of [Bird et al., 2002]. Newtonian fluid flows through a rectangular channel with porous walls with a height h and infinite extensions along x_1 and x_3 directions as shown in figure 12.6. The fluid leaks through the walls at a constant velocity of v_w . The plane flow is steady, density ρ and viscosity μ are constant and there are no body forces. The flow takes place due to a constant pressure gradient $\frac{\Delta p}{L}$. Velocity is fully developed along x_1 . (a) Use the continuity equation to obtain $u_2(x_2)$. (b) Write the Navier-Stokes equation for u_1 after simplification. (c) Assuming no slip boundary conditions applicable for u_1 , show that the velocity distribution can be given by the expression below. (d) Show that in the limit $v_w \rightarrow 0$, we retrieve the velocity profile




Figure 12.6: Channel flow between porous walls

of a plane channel flow. Note the location of axes different from the ones used in the class.

$$u_1(x_2) = \frac{\Delta p}{L} \frac{h}{\rho v_w} \left(\frac{x_2}{h} - \frac{1 - e^{-\frac{v_w x_2}{\nu}}}{1 - e^{-\frac{v_w h}{\nu}}} \right)$$

Solution 12.1.60

Exercise 12.1.61

Euler equation: Euler equation governs the flow of inviscid fluids i.e., fluids with nearly zero viscosity. (a) Use the information given at the end of the question paper and write down Euler equation in one dimension case for flow in a vertical tube due to both gravity as well as pressure gradient. (b) Show that in steady state, it reduces to the following expression popularly known as Bernoulli equation.

$$\frac{p}{\rho} + gz + \frac{v_z^2}{2} = \text{constant}$$

Solution 12.1.61

Exercise 12.1.62

Couette flow: The Navier-Stokes equation for the θ component of velocity in cylindrical coordinate system is given to you. Annular region between two coaxial cylindrical surfaces of radii r_i and r_o (for inner and outer radii, respectively) is filled with a fluid. The outer cylinder is rotating with an angular velocity of Ω_o and the inner cylinder is rotating with an angular velocity of Ω_i , both clockwise. Assume that the fluid flow is uniform, steady state and fully developed and is only due to the rotation of outer cylinder. (a) Determine the velocity distribution in the liquid in the annular region. (b) Show that the result will approximate to Newton's Law when the difference of radii is very small compared to either

radii.

Solution 12.1.62

Exercise 12.1.63

Channel flow of two stratified immiscible fluids: Section 2.5 of [Bird et al., 2002]. Two immiscible incompressible fluids of viscosities μ_1 (bottom) and μ_2 (top) are flowing between two stationary parallel plates under a pressure gradient $\frac{\Delta P}{L}$. Assume $\mu_1 > \mu_2$. The thickness of the two layers δ is same. (a) Derive an expression for the shear stress as a function of distance between the two plates. (b) Determine the location of zero shear stress from the bottom. (c) Draw schematically the shear stress profile.

Solution 12.1.63

Exercise 12.1.64

The Navier-Stokes equation for the θ component of velocity in cylindrical coordinate system is given below. Annular region between two coaxial cylindrical surfaces of radii r_i and r_o (for inner and outer radii, respectively) is filled with a fluid. The outer cylinder is rotating with an angular velocity of Ω_o and the inner cylinder is rotating with an angular velocity of Ω_i , both clockwise. Assume that the fluid flow is uniform, steady state and fully developed and is only due to the rotation of outer cylinder. (a) Determine the velocity distribution in the liquid in the annular region. (b) Show that the result will approximate to Newton's Law when the difference of radii is very small compared to either radii.

$$\frac{\partial v_\theta}{\partial t} + v_r \frac{\partial v_\theta}{\partial r} + \frac{v_\theta}{r} \frac{\partial v_\theta}{\partial \theta} + \frac{v_r v_\theta}{r} + v_z \frac{\partial v_\theta}{\partial z} = F_\theta - \frac{1}{\rho r} \frac{\partial p}{\partial \theta} + \nu \left[\frac{\partial}{\partial r} \left(\frac{1}{r} \frac{\partial \{r v_\theta\}}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2 v_\theta}{\partial \theta^2} + \frac{2}{r^2} \frac{\partial v_r}{\partial \theta} + \frac{\partial^2 v_\theta}{\partial z^2} \right]$$

Solution 12.1.64

With the assumptions of steady state, fully developed uniform flow without any body forces or pressure gradients, set $\frac{\partial v_\theta}{\partial t}$, v_r , v_z , $\frac{\partial v_\theta}{\partial \theta}$, F_θ and $\frac{\partial p}{\partial \theta}$ and variations along z to zero.

$$\frac{\partial}{\partial r} \left(\frac{1}{r} \frac{\partial \{r v_\theta\}}{\partial r} \right) = 0$$

Integrating twice and recognizing that the first integration constant C_1 anyway needs to be found out (so that we can drop the 2 in the denominator),

$$v_\theta = C_1 r + \frac{C_2}{r}$$

Using the boundary conditions of $v_\theta = r_i \Omega_i$ at $r = r_i$ and $v_\theta = r_o \Omega_o$ at $r = r_o$,

$$r_i \Omega_i = C_1 r_i + \frac{C_2}{r_i}$$

$$r_o \Omega_o = C_1 r_o + \frac{C_2}{r_o}$$

Multiplying the first equation with r_i and the second with r_o and subtracting,

$$C_1 = \frac{r_i^2 \Omega_i - r_o^2 \Omega_o}{r_i^2 - r_o^2}$$

Similarly, divide the first equation with r_i and the second with r_o and subtract to get,

$$C_2 = \frac{(\Omega_i - \Omega_o) r_i^2 r_o^2}{r_o^2 - r_i^2}$$

Substituting,

$$v_\theta = \frac{r_i^2 \Omega_i - r_o^2 \Omega_o}{r_i^2 - r_o^2} r + \frac{(\Omega_i - \Omega_o) r_i^2 r_o^2}{r_o^2 - r_i^2} \frac{1}{r}$$

To approximate the situation to that of Newton's law, set $\Omega_i = 0$, $r_o \Omega_o = u_o$, $r_i = R \approx r_o$, $r_o - r_i = \delta$, $r = R + y$.

$$v_\theta = \frac{-r_o u_o}{r_i^2 - r_o^2} r + \frac{-u_o r_i^2 r_o}{r_o^2 - r_i^2} \frac{1}{r}$$

$$v_\theta = \frac{R u_o}{2 R \delta} \left(\frac{r^2 - R^2}{r} \right)$$

$$v_\theta = \frac{u_o}{2 \delta} \left(\frac{(r + R)y}{r} \right) = \frac{u_o y}{\delta} \left[\frac{r + R}{2r} \right]$$

In the limit of y being very small compared to R , the term in the square brackets tends to unity, leaving the relation

$$v_\theta = \frac{u_o y}{\delta}$$

which is the same as definition of Newton's law.

Chapter 13

Creeping flow

13.1 Learning objectives

At the end of this lesson, a student should be able to

1. list the assumptions and concepts behind Stoke's law
2. recollect the Stoke's law
3. apply Stoke's law to simple problems of force balance

13.2 Concept map

A concept map exposing the connection between different concepts behind Stoke's law is given in the figure 13.1.

13.3 N-S equations using stream function

The Navier-Stokes equations can be written for 2D flow without body force term as follows:

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial x_1} + u_2 \frac{\partial u_1}{\partial x_2} = -\frac{1}{\rho} \frac{\partial p}{\partial x_1} + \nu \left(\frac{\partial^2 u_1}{\partial x_1^2} + \frac{\partial^2 u_1}{\partial x_2^2} \right) \quad (13.1)$$

$$\frac{\partial u_2}{\partial t} + u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} = -\frac{1}{\rho} \frac{\partial p}{\partial x_2} + \nu \left(\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} \right) \quad (13.2)$$

Differentiate eqn 13.1 with respect to x_2 and eqn 13.2 with respect to x_1 and subtract the second from the first.




Figure 13.1: Concept map for Stokes law derivation

$$\begin{aligned}
 & \frac{\partial}{\partial t} \left(\frac{\partial u_1}{\partial x_2} - \frac{\partial u_2}{\partial x_1} \right) + \\
 & \frac{\partial}{\partial x_2} \left[u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} \right] - \\
 & \frac{\partial}{\partial x_1} \left[u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} \right] = \nu \frac{\partial}{\partial x_2} \left[\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} \right] - \\
 & \nu \frac{\partial}{\partial x_1} \left[\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} \right]
 \end{aligned} \tag{13.3}$$

From the definition of u_1 and u_2 using a stream function ψ , it is easy to note the following simplification.

$$\frac{\partial u_1}{\partial x_2} - \frac{\partial u_2}{\partial x_1} = \nabla^2 \psi \tag{13.4}$$

One can simplify the R.H.S. of eqn 13.3 to the following:

Define a new operator ∇^4 as follows:

$$\nabla^4 \psi \equiv \nabla^2 \nabla^2 \psi$$

$$\frac{\partial}{\partial x_2} \left[\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} \right] - \frac{\partial}{\partial x_1} \left[\frac{\partial^2 u_2}{\partial x_1^2} + \frac{\partial^2 u_2}{\partial x_2^2} \right] = \nabla^4 \psi \tag{13.5}$$

$$\frac{\partial \nabla^2 \psi}{\partial t} + \left[\frac{\partial}{\partial x_2} (\vec{u} \cdot \vec{\nabla} u_1) - \frac{\partial}{\partial x_1} (\vec{u} \cdot \vec{\nabla} u_2) \right] = \nu \nabla^4 \psi$$

Expanding the velocities using the stream function, the term in the square brackets can be simplified to be the following. **any error here?**

$$\left[\frac{\partial}{\partial x_2} (\vec{u} \cdot \vec{\nabla} u_1) - \frac{\partial}{\partial x_1} (\vec{u} \cdot \vec{\nabla} u_2) \right] = \frac{\partial \psi}{\partial x_2} \frac{\partial}{\partial x_1} \nabla^2 \psi - \frac{\partial \psi}{\partial x_1} \frac{\partial}{\partial x_2} \nabla^2 \psi$$

Classwork: Convince yourself about the above expression by substituting for the velocity components and using differentiation by parts.

$$\frac{\partial}{\partial x_2} \left[u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} \right] - \frac{\partial}{\partial x_1} \left[u_1 \frac{\partial u_2}{\partial x_1} + u_2 \frac{\partial u_2}{\partial x_2} \right] = - \left[\frac{\partial \psi}{\partial x_1} \frac{\partial \nabla^2 \psi}{\partial x_2} - \frac{\partial \psi}{\partial x_2} \frac{\partial \nabla^2 \psi}{\partial x_1} \right] \quad (13.6)$$

We now define the following expression using the Jacobian notation of determinant of a matrix as follows.

$$\frac{\partial (\psi, \nabla^2 \psi)}{\partial (x_1, x_2)} \equiv \begin{vmatrix} \frac{\partial \psi}{\partial x_1} & \frac{\partial \psi}{\partial x_2} \\ \frac{\partial}{\partial x_1} \nabla^2 \psi & \frac{\partial}{\partial x_2} \nabla^2 \psi \end{vmatrix}$$

The R.H.S. of the above equation can be written as Jacobian Determinant in 2D as follows.

$$\left[\frac{\partial \psi}{\partial x_1} \frac{\partial \nabla^2 \psi}{\partial x_2} - \frac{\partial \psi}{\partial x_2} \frac{\partial \nabla^2 \psi}{\partial x_1} \right] = \frac{\partial (\psi, \nabla^2 \psi)}{\partial (x_1, x_2)} \quad (13.7)$$

Combining equations 13.4, 13.4 and 13.7 with 13.3, we get the Navier-Stokes equation in 2D, without body force term using stream function ψ as follows:

$$\boxed{\frac{\partial \nabla^2 \psi}{\partial t} - \frac{\partial (\psi, \nabla^2 \psi)}{\partial (x_1, x_2)} = \nu \nabla^4 \psi} \quad (13.8)$$

13.4 The E^2 operator

As can be seen above, the Laplacian operator is an important operator for the stream function use. The definition of this operator for different coordinate systems is as follows.

Laplacian in rectangular coordinates:

$$\nabla^2 \equiv \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + \frac{\partial^2}{\partial z^2}$$

Laplacian in cylindrical coordinates:

$$\nabla^2 \equiv \frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2}{\partial \theta^2} + \frac{\partial^2}{\partial z^2}$$

Laplacian in spherical coordinates:

$$\nabla^2 \equiv \frac{1}{r^2} \frac{\partial}{\partial r} \left(r^2 \frac{\partial}{\partial r} \right) + \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left(\sin \theta \frac{\partial}{\partial \theta} \right) + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2}{\partial \phi^2}$$

The Laplacian operator and the Navier-Stokes equation take special forms for 2D flow in cylindrical and spherical coordinates if additional symmetry is imposed on the flow field.

Cylindrical with $V_z = 0$ and no z dependence:

$$\nabla^2 = \frac{\partial^2}{\partial r^2} + \frac{1}{r} \frac{\partial}{\partial r} + \frac{1}{r^2} \frac{\partial^2}{\partial \theta^2}$$

Navier-Stokes equation for this situation reduces to:

$$\frac{\partial}{\partial t} (\nabla^2 \psi) - \frac{1}{r} \frac{\partial (\psi, \nabla^2 \psi)}{\partial \theta} = \nu \nabla^4 \psi$$

In situations where the flow is axisymmetrical, we need to define a new operator E as follows:

Cylindrical with $V_\theta = 0$ and no θ dependence:

$$E^2 \equiv \frac{\partial^2}{\partial r^2} - \frac{1}{r} \frac{\partial}{\partial r} + \frac{\partial^2}{\partial z^2}$$

Navier-Stokes equation for this situation reduces to:

$$\frac{\partial}{\partial t} (E^2 \psi) - \frac{1}{r} \frac{\partial (\psi, E^2 \psi)}{\partial z} - \frac{2}{r^2} \frac{\partial \psi}{\partial z} E^2 \psi = \nu E^4 \psi$$

Note the difference in the operator used and the reduced form of Navier-Stokes equation in the above two situations for a 2D flow in cylindrical coordinate system.

Spherical with $V_\phi = 0$ and no ϕ dependence:

$$E^2 \equiv \frac{\partial^2}{\partial r^2} + \frac{\sin \theta}{r^2} \frac{\partial}{\partial \theta} \left(\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \right)$$

Navier-Stokes equation in this situation reduces to:

$$\frac{\partial}{\partial t} (E^2 \psi) - \frac{1}{r^2 \sin \theta} \frac{\partial (\psi, E^2 \psi)}{\partial \theta} + \frac{2E^2 \psi}{r^2 \sin^2 \theta} \left(\frac{\partial \psi}{\partial r} \cos \theta - \frac{1}{r} \frac{\partial \psi}{\partial \theta} \sin \theta \right) = \nu E^4 \psi$$

In both the above situations, the E^4 is defined as $E^2(E^2)$.

Note the difference in the definition of E^2 for the cylindrical and spherical coordinates.

13.5 Creeping flow over a sphere

When $Re < 0.1$, the flow around a smooth sphere is such that the viscous effects are present all around the sphere and no *flow separation* takes place. For such a flow regime called *creeping flow*. around a sphere, we are interested not in the flow distribution around it but the viscous

drag. The velocity of a sphere falling in a liquid column (terminal velocity) or the far field velocity of a fluid flowing around a sphere is u_∞ or simply U as shown in the figure 13.2.




Figure 13.2: Creeping flow around a sphere

For very low Reynolds number, the acceleration terms can be neglected. The Navier-Stokes equation can then be approximated by the Stoke's equation. The stream-function form of Stoke's equation for this situation is given by:

$$E^4 \psi = 0$$

This needs to be solved for the following boundary conditions.

Classwork: Convince yourself about the following forms of boundary conditions.

$$V_r(R, \theta) = 0 \implies \frac{\partial}{\partial \theta} \psi(R, \theta) = 0$$

$$V_\theta(R, \theta) = 0 \implies \frac{\partial}{\partial r} \psi(R, \theta) = 0$$

$$V_r(\infty, \theta) \rightarrow U \cos \theta \implies \frac{\partial}{\partial \theta} \psi(\infty, \theta) \rightarrow r^2 U \sin \theta \cos \theta$$

$$V_\theta(\infty, \theta) \rightarrow -U \sin \theta \implies \frac{\partial}{\partial r} \psi(\infty, \theta) \rightarrow r U \sin^2 \theta$$

Combining the two above, we can say that the boundary condition on ψ at (∞, θ) is:

$$\psi(\infty, \theta) \rightarrow \frac{r^2 U \sin^2 \theta}{2}$$

We propose that the solution of $\psi(r, \theta)$ for this problem can be of the following form.

$$\psi(r, \theta) = f(r) \sin^2 \theta$$

We need to determine the form of $f(r)$ to satisfy the above conditions.

Substitute the proposed solution in the Stoke's equation to get the following:

$$E^4\psi = E^2 (E^2) \psi = \left[\frac{\partial^2}{\partial r^2} + \frac{\sin \theta}{r^2} \frac{\partial}{\partial \theta} \left(\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \right) \right]^2 f(r) \sin^2 \theta = 0$$

Classwork: Convince yourself that this expression can be reduced to the following. Use differentiation by parts and simplify.

$$\left[\frac{\partial^2}{\partial r^2} - \frac{2}{r^2} \right]^2 f(r) = 0$$

We suspect a form of r^n may satisfy this equation.

Classwork: Convince yourself that the above equation when used with $f(r) = r^n$ simplifies to the following.

$$(n+1)(n-1)(n-2)(n-4)r^{n-4} = 0$$

We see that the equation turns out to be true only for the values of n in $\{-1, 1, 2, 4\}$. We take a linear combination of these four possible solutions to arrive at a general solution as follows.

$$f(r) = Ar^4 + Br^2 + Cr + \frac{D}{r}$$

The boundary conditions for this equation shall be:

$$f(R) = 0$$

$$\left. \frac{\partial f}{\partial r} \right|_R = 0$$

$$f(\infty) \rightarrow \frac{r^2 U}{2}$$

Inspecting the boundary conditions that this expression of $f(r)$ should satisfy, we can arrive at the values of the four coefficients.

Classwork: Show that the coefficients take the following values:
 $A = 0$, $B = U/2$, $C = -3UR/4$ and $D = UR^3/4$.

Thus, the final solution of ψ comes out as follows.

$$\psi(r, \theta) = UR^2 \sin^2 \theta \left[\frac{1}{2} \left(\frac{r}{R} \right)^2 - \frac{3}{4} \left(\frac{r}{R} \right) + \frac{1}{4} \left(\frac{R}{r} \right) \right]$$

Homework: Plot contours of the above function using, say, Matlab and convince yourself about the nature of the flow around a sphere in 2D.

Using this stream function, the two velocity components can be arrived at as:

$$V_r(r, \theta) = U \cos \theta \left[1 - \frac{3}{2} \left(\frac{R}{r} \right) + \frac{1}{2} \left(\frac{R}{r} \right)^3 \right]$$

$$V_\theta(r, \theta) = -U \sin \theta \left[1 - \frac{3}{4} \left(\frac{R}{r} \right) - \frac{1}{4} \left(\frac{R}{r} \right)^3 \right]$$

13.5.1 Pressure

Substitute the above two velocity components in the Navier-Stokes equation, without the acceleration term as follows.

Substitute the solution for V_r in the simplified form of Navier-Stokes equation for V_r in spherical coordinate system:

$$0 = -\frac{\partial p}{\partial r} + \mu \left[\frac{1}{r^2} \frac{\partial^2}{\partial r^2} (r^2 V_r) + \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left(\sin \theta \frac{\partial V_r}{\partial \theta} \right) \right]$$

This gives the first variation of pressure as follows.

$$\frac{\partial p}{\partial r} = 3R\mu U \left(\frac{1}{r^3} \right) \cos \theta$$

Similarly, substitute the solution for V_θ and V_r in the Navier-Stokes equation for V_θ in spherical coordinate system:

$$0 = -\frac{1}{r} \frac{\partial p}{\partial \theta} + \mu \left[\frac{1}{r^2} \frac{\partial}{\partial r} \left(r^2 \frac{\partial V_\theta}{\partial r} \right) + \frac{1}{r^2} \frac{\partial}{\partial \theta} \left(\frac{1}{\sin \theta} \frac{\partial (V_\theta \sin \theta)}{\partial \theta} \right) + \frac{2}{r^2} \frac{\partial V_r}{\partial \theta} \right]$$

This gives the second variation of pressure as follows.

$$\frac{\partial p}{\partial \theta} = \frac{3}{2} \frac{\mu U}{R} \left(\frac{R}{r} \right)^2 \sin \theta$$

Classwork: Convince yourself about the above derivatives of pressure and the below integrated form.

Integrating the two, we obtain:

$$p = -\frac{3}{2} \frac{\mu U}{R} \left(\frac{R}{r} \right)^2 \cos \theta + \text{constant}$$

It turns out that the integration constant is $p_0 - \rho g z$.

13.5.2 Drag forces

We borrow the expressions for pressure and stress for creeping flow around a sphere from section 2.6 of Bird's book on Transport Phenomena.

Pressure:

$$p = p_0 - \rho g z - \frac{3}{2} \frac{\mu u_\infty}{R} \left(\frac{R}{r} \right)^2 \cos \theta$$

We can choose to have $p_0 = 0$ for the following discussion.

Look up BLS book to obtain the expressions for different stresses in spherical coordinates.

Shear Stress:

$$\sigma_{rr} = \mu \left[2 \frac{\partial V_r}{\partial r} \right]$$

$$\tau_{r\theta} = \mu \left[r \frac{\partial}{\partial r} \left(\frac{V_\theta}{r} \right) + \frac{1}{r} \frac{\partial V_r}{\partial \theta} \right]$$

Substitute the expression for V_r to get the following.

$$\sigma_{rr} = \frac{3\mu v_\infty}{R} \left[- \left(\frac{R}{r} \right)^2 + \left(\frac{R}{r} \right)^4 \right] \cos \theta$$

$$\tau_{r\theta} = \frac{3}{2} \frac{\mu u_\infty}{R} \left(\frac{R}{r} \right)^4 \sin \theta$$

An elemental area on the surface of the sphere of radius R is given by $R d\theta R \sin \theta d\phi = R^2 \sin \theta d\theta d\phi$.

Substitute $z = R \cos \theta$ in the pressure term before integrating.

Classwork: Convince yourself about the following integration.

Watch out confusion between θ and ϕ here. Also the integration limits correspondingly

The normal force along z due to the z component of pressure and normal stress τ_{rr} is given as:

$$\begin{aligned} F_n &= \int_0^\pi \int_0^{2\pi} (-p|_{r=R} + \sigma_{rr}|_{r=R}) \cos \theta R^2 \sin \theta d\theta d\phi \\ &= \frac{4}{3} \pi R^3 \rho g + 2\pi \mu R u_\infty \end{aligned}$$

The first term $\frac{4}{3} \pi R^3 \rho g$ is called *buoyancy force*.

The second term $2\pi \mu R u_\infty$ is called *form drag*.

Classwork: Convince yourself about the following integration.

The tangential force along z due to z component of shear stress $\tau_{r\theta}$ is given as:

$$\begin{aligned} F_t &= \int_0^\pi \int_0^{2\pi} (\tau_{r\theta}|_{r=R} \sin \theta) R^2 \sin \theta d\theta d\phi \\ &= 3\pi\mu R u_\infty \int_0^\pi \sin^3 \theta d\theta \\ &= 4\pi\mu R u_\infty \end{aligned}$$

This term $4\pi\mu R u_\infty$ is called *friction drag*.

13.5.3 Terminal velocity

A sphere is to fall with terminal velocity u_∞ in a fluid when there are no forces acting on it. If the weight of the sphere equals the drag forces acting on it due to fluid flow around it, then the velocity of the sphere relative to the fluid can be referred to as terminal velocity. This is then also the far field velocity of the fluid in a coordinate system fixed to the sphere.

The weight of the falling sphere should equal the sum of form drag and friction drag. Here, ρ_s is the density of the sphere and ρ is the density of the fluid.

$$\frac{4}{3}\pi R^3 \rho_s g = \frac{4}{3}\pi R^3 \rho g + 6\pi\mu R u_\infty$$

Collecting the terms on the LHS and simplifying, we obtain the **Stokes Law**.

$$\frac{4}{3}\pi R^3 (\rho_s - \rho) g = 6\pi\mu R u_\infty$$

In case of a sphere falling down a fluid column, u_∞ is also referred to as **terminal velocity**.

The above expression is valid only for $Re \ll 0.1$ where creeping flow is valid.

13.6 Summary

13.7 Exercises

Exercise 13.7.65

Example 3.2 of [Gaskell, 1992]. When a hollow sphere of diameter 0.005 m and composite density 1500 kg m^{-3} is dropped into a column of oil of density 888 kg m^{-3} , it attains a terminal velocity of 0.01 m s^{-1} . (a) Calculate the viscosity of the oil. (b) Comment if the estimate is valid.

Solution 13.7.65

Answer: $\mu = 0.834 \text{ Pa}\cdot\text{s}$.

Exercise 13.7.66

Example 3.3 of [Gaskell, 1992]. The product of the deoxidation of liquid steel by the addition of aluminum is solid alumina. It forms throughout the liquid and floats to the top. This process is performed for a fixed duration of time after which the floating mass is skicked off. Those particles that take longer to float will remain in the solidified steel as inclusions and are detrimental to the mechanical properties. Assuming that the solid alumina forms as small spheres, (a) calculate the size of the smallest sphere that can float to the surface of a 1.5 m deep quiescent liquid steel in 20 min. (b) Comment if the estimate is valid.

Solution 13.7.66

Answer: $R = 33.2 \mu\text{m}$.

Exercise 13.7.67

Problem 3.1 of [Gaskell, 1992]. Viscosities of experimental glasses are being determined by measuring the terminal velocity of a platinum sphere falling through a column of molten glass. When dropped into a column of standard glass of viscosity $10 \text{ Pa}\cdot\text{s}$ and density 2500 kg m^{-3} , the measured terminal velocity is 0.0258 m s^{-1} . When dropped into an experimental glass of density 3000 kg m^{-3} , the measured velocity is 0.0168 m s^{-1} . Calculate the viscosity of the experimental molten glass. Density of platinum is $21\,450 \text{ kg m}^{-3}$.

Solution 13.7.67

Answer: $\mu = 14.96 \text{ Pa}\cdot\text{s}$.

Exercise 13.7.68

Problem 3.4 of [Gaskell, 1992]. Small glass spheres of density 2620 kg m^{-3} are allowed to fall through CCl_4 of density 1590 kg m^{-3} and viscosity $9.58 \times 10^{-4} \text{ Pa}\cdot\text{s}$. Calculate (a) the maximum diameter of sphere for which the flow obeys Stoke's law (b) the terminal velocity that a sphere of this diameter attains.

Solution 13.7.68

Answer: (a) $46.8 \mu\text{m}$ (b) 1.28 mm s^{-1}

13.8 Creeping flow through a porous medium




Figure 13.3: Porous medium and its approximation as a bundle of tubes

A porous medium is characterised by the fraction of voids or porosity ϵ .

$$\epsilon = \frac{\text{volume of voids}}{\text{volume of porous body}}$$

For a given porosity, the distribution of porosity could be such that the surface area is a second variable. Thus a porous medium is also characterised by surface area per unit volume of solid S_0 .

$$S_0 = \frac{\text{wetable surface area}}{\text{volume of solid}}$$

If a porous medium can be imagined to act like a bundle of thin tubes, then the equivalent diameter could be defined as hydraulic radius:

$$R_h = \frac{\text{volume of voids}}{\text{wetable surface area}}$$

Using the definition of ϵ , volume of voids is $V\epsilon$. Using the definition of S_0 , the wettable surface area is $S_0V(1 - \epsilon)$.

$$R_h = \frac{\epsilon}{S_0(1 - \epsilon)} \quad (13.9)$$

If A is the cross sectional area of the porous body, then $A\epsilon$ is the cross sectional area of the voids through which the liquid can flow. If $\bar{u}$ is the actual velocity of the fluid through the void, we can define the average (superficial) velocity $\bar{u}_s$ through the entire porous body such that the volume flow rate $\dot{V}$ is same:

$$\bar{u}_s A = \bar{u} A \epsilon = \dot{V}$$

or

$$\bar{u}_s = \bar{u} \epsilon \quad (13.10)$$

We take clue from the *Poiseuille flow* the connects the pressure gradient with the flow through a tube:

$$\bar{u} = \frac{\Delta p}{L} \frac{R^2}{8\mu} = \frac{1}{K_1} \frac{\Delta p}{L} \frac{R^2}{\mu} \quad (13.11)$$

Darcy's Law: Considering a porous medium as a bundle of tubes, the volume flow rate is proportional to the cross sectional area and the pressure gradient. The proportionality constant is called as *permeability coefficient*.

$$\dot{V} = k_D A \frac{\Delta p}{L} \quad (13.12)$$

Considering that the nature of flow through a porous medium is a lot tortuous than through a tube, the constant K_1 in equation 13.11 is taken not as 8 but 4.2 as has also been validated through experiments.

Now substituting equations 13.10, 13.9 into 13.11 with 4.2 as the constant, we get the *Blake-Kozeny equation*:

$$\bar{u}_s = \frac{1}{4.2} \frac{\Delta p}{L} \frac{\epsilon^3}{\mu S_0^2 (1 - \epsilon)^2} \quad (13.13)$$

Validity:

Evaluating Re for porous medium taking the equivalent diameter as $2R_h$,

$$Re = \frac{\bar{u} D \rho}{\mu} = 2 \frac{\rho \bar{u}_s}{\mu S_0 (1 - \epsilon)}$$

We define the Reynolds number for porous medium as:

$$Re_c = \frac{\rho \bar{u}_s}{\mu S_0 (1 - \epsilon)} \quad (13.14)$$

The Blake-Kozeny equation is valid for $Re_c < 2$

Packed bed of spheres: If the porous medium is made of spherical particles of diameter d_p , then S_0 , the surface area per unit volume of solid can be estimated directly since total wettable area is the sum of surface area of all spheres and total volume of solid is the sum of volume of all spheres.

$$S_0 = \frac{4\pi R^2}{\frac{4}{3}\pi R^3} = \frac{3}{R} = \frac{6}{d_p}$$

Substituting this in Blake-Kozeny equation, we get the following equation:

$$\frac{\Delta p}{L} = \frac{150 \mu \bar{u}_s (1 - \epsilon)^2}{d_p^2 \epsilon^3} \quad (13.15)$$

Evaluating Re for porous medium made of spherical particles (packed bed of spheres) and taking the equivalent diameter as d_p ,

$$Re = \frac{\bar{u} D \rho}{\mu} = \frac{\rho \bar{u}_s d_p}{\mu 3 (1 - \epsilon)}$$

We define the Reynolds number for packed bed of spheres as:

$$Re_E = \frac{\rho \bar{u}_s d_p}{\mu (1 - \epsilon)} \quad (13.16)$$

13.9 Exercises

1. Problem 3.12 of [Geiger and Poirier, 1994]. Preliminary experimental studies have shown that the porosity in a newly developed packed bed reactor is $\epsilon < 0.6$. The pellets have a diameter of 30 mm and the reducing gas flows through the bed at a rate of 0.025 kg s^{-1} . The reactor has $3 \text{ m} \times 3 \text{ m}$ square cross section and is 15 m in height. A constant pressure difference of 690 Pa is maintained between the inlet and outlet nozzles, and it may be assumed that the temperature is uniform throughout the reactor. You are required to evaluate the bed porosity. The properties of the gas are $\mu = 2.07 \times 10^{-5} \text{ Pa s}$ and $\rho = 1.2 \text{ kg m}^{-3}$. Comment if the solution is valid.

Answer: $\epsilon = 0.054$.

Chapter 14

Correlations for turbulent regime

14.1 Learning objectives

At the end of this lesson, a student should be able to

1. apply the concept of friction factor to determine velocity in a simple flow problem
2. apply the definition to derive friction factor as a function of Reynold's number and other non-dimensional parameters
3. iteratively identify the appropriate friction factor correlation for simple flow problems

14.2 Concept map

At large Reynolds numbers, the flow distribution cannot be obtained through a simple analytical expression as it could be time dependent. In such cases, we are interested in the force associated with the flow and its effectiveness in imparting kinetic energy to the fluid. For this, we define a quantity called *friction factor* and express it as a function of non-dimensional quantities such as Re and relative roughness ζ . For laminar flow, the expression for friction factor must result back to the analytical expressions derived for the situation.

14.3 Friction factor

Friction factor f is defined in the following expression:

$$F_k = f A \frac{1}{2} \rho \bar{u}^2 \quad (14.1)$$

$\frac{1}{2} \rho \bar{u}^2$ is the kinetic energy per unit volume of the fluid with average velocity $\bar{u}$.

For internal flow, A is the wetted area.

For external flow or flow over submerged objects, A is the area projected on a plane perpendicular to the velocity $\bar{u}$.




Figure 14.1: Concept map on how one usually goes about problem solution using friction factors

F_k is the force associated with the fluid flow. For flow through a tube, it would be the pressure times the cross-sectional area over which it acts. For a sphere falling through a liquid, it would be the buoyancy force.

14.4 Flow through tube

For internal flow through a tube of diameter D , length L due to pressure gradient $\frac{\Delta p}{L}$,

$$\Delta p \cdot \pi \frac{D^2}{4} = f \cdot \pi D L \cdot \frac{1}{2} \rho \bar{u}^2$$

or

$$f = \frac{1}{4} \frac{\Delta p}{L} \frac{D}{\frac{1}{2} \rho \bar{u}^2} \quad (14.2)$$

For laminar regime, we know that

$$\bar{u} = \frac{\Delta p}{L} \frac{R^2}{8\mu}$$

Substitute the following in equation 14.1:

$$A = 2\pi R L$$

$$F_k = \Delta p \pi R^2$$

to get

$$\boxed{\frac{\Delta p}{L} = f \frac{\rho \bar{u}^2}{R}} \quad (14.3)$$

Eliminating $\frac{\Delta p}{L}$ using the expression for Poiseuille flow, we get

$$f = \frac{8\mu}{\rho R \bar{u}} = 16 \frac{\mu}{\rho D \bar{u}} = \frac{16}{Re}$$

Friction factors for pipe flow:

Laminar flow through smooth pipe ($Re < 2100$):

$$f = \frac{16}{Re}$$

Turbulent flow through smooth pipe ($3000 < Re < 10^5$):

$$f = 0.0791 Re^{-0.25}$$

Turbulent flow through rough pipe ($4 \times 10^4 < Re < 10^8$):

$$f^{-0.5} = -3.6 \log_{10} \left[\left(\frac{\zeta}{3.7} \right)^{1.11} + \frac{6.9}{Re} \right]$$

Here, ζ is relative roughness

14.5 Flow across a sphere

For laminar regime, we know that the force associated with the flow is given by Stoke's law.

Substitute the following in equation 14.1:

A is projected area for flow over submerged objects:

$$A = \pi R^2$$

$$\bar{u} = u_\infty$$

$$F_k = 6\pi\mu R u_\infty$$

to get

$$6\pi\mu R u_\infty = f \cdot \pi R^2 \cdot \frac{1}{2} \rho u_\infty^2$$

Simplifying, we get

$$f = \frac{24}{Re}$$

Friction factors for flow over sphere:

$$\boxed{F = f \pi R^2 \frac{1}{2} \rho u_\infty^2} \quad (14.4)$$

Friction Factor	Re range	Remarks
$f = 24/Re$	$Re < 0.1$	Laminar
$f = 18.5Re^{-0.6}$	$2 < Re < 500$	Turbulent
$f = \left(\sqrt{24/Re} + 0.5407 \right)^2$	$Re < 6000$	Turbulent
$f = 0.44$	$500 < Re < 2 \times 10^5$	Newtons Law

14.6 Flow through a porous medium

For creeping flow through a porous medium, we can use the Darcy's law to approximate the porous medium to be a bundle of tubes and obtain the following relation from equation 13.13.

Use the definition of friction factor applied for tube flow and expressions as used in the derivation of 13.13:

$$\Delta p \cdot \pi \frac{D_h^2}{4} = f \cdot \pi D_h L \cdot \frac{1}{2} \rho u^2$$

$$\frac{\Delta p}{L} = f \cdot \frac{\rho u_s^2}{\epsilon^2 R_h}$$

Thus,

$$\boxed{\frac{\Delta p}{L} = f \frac{S_0 (1 - \epsilon)}{\epsilon^3} \rho u_s^2} \quad (14.5)$$

Substituting equation 13.13 in the above to eliminate pressure drop,

$$f = 4.2 \frac{(1 - \epsilon) S_0 \mu}{\rho \bar{u}_s} = \frac{4.2}{Re_c}$$

Friction factors for flow through porous medium:

For $Re_c < 2$:

$$f = \frac{4.2}{Re_c}$$

For $2 < Re_c < 1000$:

$$f = \frac{4.2}{Re_c} + 0.292$$

For $1000 < Re_c < 10^5$:

$$f = 0.292$$

14.7 Flow through a packed bed of spheres

For creeping flow through a packed bed of sphere, we can use the porous medium equation 13.13 and substitute expression for S_0 .

$$S_0 = \frac{6}{d_p}$$

Substitute the same in equation 14.5 to get

$$\frac{\Delta p}{L} = f \frac{6(1-\epsilon)}{d_p \epsilon^3} \rho u_s^2 \quad (14.6)$$

We define $6f$ as f_E so that:

$$\boxed{\frac{\Delta p}{L} = f_E \frac{(1-\epsilon)}{d_p \epsilon^3} \rho u_s^2} \quad (14.7)$$

Eliminating $\frac{\Delta p}{L}$, we get

$$f_E = 150 \frac{(1-\epsilon) \mu}{\rho \bar{u}_s d_p} = \frac{150}{Re_E}$$

Friction factors for flow through packed bed of spheres:

For $Re_E < 10$:

$$f_E = \frac{150}{Re_E}$$

For $10 < Re_E < 1000$:

$$f_E = \frac{150}{Re_E} + 1.75$$

For $1000 < Re_E < 10^5$:

$$f_E = 1.75$$

14.8 Summary

14.9 Exercises

Exercise 14.9.69

Flow past infinite cylinder: Problem 6B.9 of [Bird et al., 2002]. The flow past a long cylinder is very different from the flow past a sphere. It is found that, when the fluid approaches a velocity u_∞ , the kinetic force acting on a length L of the cylinder is given by:

$$F_k = \frac{4\pi\mu u_\infty L}{\ln(7.4/Re)}$$

The Reynolds number is defined here as $Re = Du_\infty\rho/\mu$ and the above equation is valid up to $Re = 1$. For this range, what is the formula for the friction factor as a function of the

Reynolds number?

Solution 14.9.69**Exercise 14.9.70**

The drag force on a plate of width W and length L may be calculated from the dimensionless velocity gradient at the wall as follows where the symbols have their usual meaning. Calculate the friction factor for this flow.

$$F = 1.328 \sqrt{\rho \mu L W^2 u_\infty^3}$$

For turbulent flow in the same situation, an approximate boundary layer treatment based on the $1/7$ power velocity distribution gives the drag force on the plate as follows.

$$F = 0.072 \rho u_\infty^2 W L (L u_\infty \rho / \mu)^{-1/5}$$

Determine the friction factor for this regime by defining the Reynold's number appropriately.

Solution 14.9.70**Exercise 14.9.71**

Consider a circular disc immersed completely in a fluid and rotating about its center with an angular velocity Ω . For such a situation, one may use the definition of friction factor f in terms of the torque needed to keep the disc rotating T_z as $T_z/R = f A K$ where the appropriate area is the wetted area of the disc on both sides $A = 2\pi R^2$ and the kinetic energy per unit volume is taken as $K = \frac{1}{2} \rho \Omega^2 R^2$. It is known that for laminar regime, an exact boundary layer development gives $T_z = 0.616 \pi \rho R^4 \sqrt{\mu \Omega^3 / \rho}$. For turbulent flow, an approximate boundary layer treatment based on the $1/7$ power velocity distribution leads to $T_z = 0.073 \rho \Omega^2 R^5 (\mu / R^2 \Omega \rho)^{0.2}$. Develop expressions for friction factor for this situation in both the regimes.

Solution 14.9.71**Exercise 14.9.72**

Examples 4.1, 4.3 of [Gaskell, 1992]. (a) Calculate the pressure drop required to pass water at 300 K through a 300 m long smooth pipe of inside diameter 0.05 m at the rate of $1.5 \times 10^{-3} \text{ m}^3 \text{ s}^{-1}$. $\rho = 997 \text{ kg m}^{-3}$, $\mu = 8.57 \times 10^{-4} \text{ Pa s}$. (b) What would be the answer if the pipe is not smooth but has a relative roughness of 0.002?

Solution 14.9.72

Answer: (a) $3.8 \times 10^4 \text{ Pa}$ (b) $4.64 \times 10^4 \text{ Pa}$.

Exercise 14.9.73

Examples 4.2, 4.4 of [Gaskell, 1992]. (a) Calculate the flow rate of water at 300 K in a smooth pipe of 0.07 m inner diameter when the pressure drop per unit length is 125 Pa m^{-1} . (b) What would be the answer if the pipe has a relative roughness of 0.002.

Solution 14.9.73

Answer: (a) 3.7 kg s^{-1} (b) 3.17 kg s^{-1} .

Exercise 14.9.74

Problem 4.2 of [Gaskell, 1992]. Water at 300 K is pumped at an average linear flow velocity of 2 m s^{-1} through a 30 m length of horizontal pipe of inside diameter 0.025 m and relative roughness of 0.004. (a) Calculate the pressure drop over the length of pipe. (b) The rough pipe is replaced by a smooth walled pipe of that diameter, which with the same pressure drop, gives the same average linear flow velocity. Calculate the required diameter of the smooth walled pipe.

Solution 14.9.74

Answer: (a) 72.07 kPa (b) 0.0183 m.

Exercise 14.9.75

Problem 4.4 of [Gaskell, 1992]. The average flow velocity of water at 300 K in a smooth pipe of internal diameter 0.07 m is 1 m s^{-1} when the rate of pressure drop is 125 Pa m^{-1} . Calculate the average flow velocity if the relative roughness were 0.002.

Solution 14.9.75

Answer: 0.83 m s^{-1} .

Useful information:

Density of water at 300 K can be taken as 997 kg m^{-3} . Viscosity can be taken as $8.57 \times 10^{-4} \text{ Pa s}$.

$$\text{Laminar: } f = \frac{16}{Re} \text{ for } Re < 2100$$

$$\text{Turbulent: } f = 0.0791 Re^{-0.25} \text{ for } 3000 < Re < 10^5$$

$$\text{Rough Pipe: } f^{-0.5} = -3.6 \log_{10} \left[\left(\frac{\zeta}{3.7} \right)^{1.11} + \frac{6.9}{Re} \right] \text{ for } 4 \times 10^4 < Re < 10^8$$

ζ is relative roughness

$$R = 3.5 \times 10^{-2} \text{ m}$$

Using laminar assumption: Estimate the velocity using Poiseuille flow.

$$u = \frac{1}{8\mu} \frac{\Delta P}{L} R^2 = 22.3 \text{ m/s}$$

Evaluate Reynold's number for this velocity:

$$Re = \frac{uD\rho}{\mu} = 1.8 \times 10^6$$

This means, the flow velocity given by Poiseuille flow expression is not valid.

Using turbulent assumption: Use the friction factor expression for turbulent flow through a smooth pipe.

$$\Delta P \pi R^2 = f 2\pi RL \frac{1}{2} \rho u^2$$

$$f = \frac{1}{2} \frac{\Delta P}{L} \frac{D}{\rho u^2}$$

Substituting, we get

$$0.0791 \left[\frac{uD\rho}{\mu} \right]^{-0.25} = \frac{1}{2} \frac{\Delta P}{L} \frac{D}{\rho u^2}$$

$$u^{1.75} 0.0791 \left[\frac{D\rho}{\mu} \right]^{-0.25} = \frac{1}{2} \frac{\Delta P}{L} \frac{D}{\rho}$$

$$u^{1.75} = 0.937$$

$$u = 0.96 \text{ m/s}$$

Reynold's number for this velocity is $Re = \frac{uD\rho}{\mu} = 78470$, the expression used is valid.

Turbulent flow through rough pipe

From the definition of friction factor, we have

$$f = \frac{1}{2} \left(\frac{\Delta P}{L} \right) \frac{D}{\rho u^2}$$

Taking inverse square root on both sides (keeping in mind that we need expression for $f^{-0.5}$ readily:

$$f^{-0.5} = u \left[\frac{2\rho}{D \left(\frac{\Delta P}{L} \right)} \right]^{0.5}$$

From the empirical correlation of friction factors for rough pipes, we have:

$$f^{-0.5} = -3.6 \log \left[\left(\frac{\zeta}{3.7} \right)^{1.11} + \frac{6.9\mu}{uD\rho} \right]$$

Combining the two expressions above to eliminate f ,

$$u \left[\frac{2\rho}{D \left(\frac{\Delta P}{L} \right)} \right]^{0.5} = -3.6 \log \left[\left(\frac{\zeta}{3.7} \right)^{1.11} + \frac{6.9\mu}{uD\rho} \right]$$

$$u = -3.6 \times \left[\frac{2\rho}{D \left(\frac{\Delta P}{L} \right)} \right]^{-0.5} \times \log_{10} \left[\left(\frac{\zeta}{3.7} \right)^{1.11} + \frac{6.9\mu}{uD\rho} \right] = q(u)$$

Where, $q(u)$ is a function of u .

While evaluating this function $q(u)$ in your calculator, first enter the initial guess and press "=" sign so that the value is stored in the variable "Ans". Now enter the expression for $q(u)$ as above taking care to use $\log_{10}$ instead of $\log$ and using "Ans" where u is to be enter. Now press "=" button to evaluate the expression to get the next value of u . Repeat till value does not change much.

Take the solution for turbulent flow through smooth pipe as the first guess.

$$\begin{aligned} u_0 &= 0.96 \\ u_1 &= q(u_0) = 0.8198 \\ u_2 &= q(u_1) = 0.82773 \\ u_3 &= q(u_2) = 0.82756 \\ u_4 &= q(u_3) = 0.82756 \end{aligned}$$

We can say that thanks to a good initial guess, the single point iteration has converged to the solution of u as 0.82756 m/s.

Reynold's number for this velocity is $Re = \frac{uD\rho}{\mu} = 67393$, means the expression used is valid.

Exercise 14.9.76

Example 4.7 of [Gaskell, 1992]. Calculate the terminal velocity attained by a steel sphere of diameter 0.01 m when it is dropped in still air. The density of steel is 7500 kg m^{-3} , density of air is 1.177 kg m^{-3} and viscosity of air is $1.85 \times 10^{-5} \text{ Pa s}$.

Solution 14.9.76

Answer: 43.5 m s^{-1} .

Exercise 14.9.77

Problem 4.5 of [Gaskell, 1992]. Density of lead is 11340 kg m^{-3} . A lead shot of diameter 3 mm is fired upward into still air at 300 K over open water. Calculate (a) the drag force that the shot experiences as it leaves the gun barrel at a velocity of 150 m s^{-1} (b) the terminal velocity that it attains when it falls through the still air and (c) the terminal velocity that it attains when it falls through the still water.

Solution 14.9.77

Answer: (a) 0.0412 N (b) 29.3 m s⁻¹ (c) 0.9618 m s⁻¹.

Exercise 14.9.78

Settling ratio is defined as the ratio of sizes of two particles that settle at the same time. It is useful to know the settling ratio of two minerals in a given medium so that they could later be mechanically separated using a sieve. Assuming smooth spherical shapes of particles, estimate the settling ratio of mineral A to mineral B in water for (a) laminar flow regime and (b) turbulent flow regime. The properties of water are $\rho = 997 \text{ kg m}^{-3}$, $\mu = 8.57 \times 10^{-5} \text{ Pa s}$. Density of minerals are $\rho_A = 2700 \text{ kg m}^{-3}$ and $\rho_B = 3400 \text{ kg m}^{-3}$.

Solution 14.9.78

Answer: (a) 1.19 (b) 1.41.

Exercise 14.9.79

Problem 4.8 of [Gaskell, 1992]. Air at 300 K and an average pressure of 101.2 kPa is flowing through a packed bed of spheres of 1 cm diameter. The bed is cylindrical in geometry with 0.1 m in dia and 0.2 m in height and a porosity of 0.35. Calculate the pressure drop across the bed required to give a mass flow rate of air of 0.05 kg s⁻¹.

Solution 14.9.79

Answer: 21 kPa.

Exercise 14.9.80

Problem 3.13 of [Geiger and Poirier, 1994]. Molten aluminum is passed through a horizontal filter bed of Al₂O₃ spheres in order to remove drossy oxides from the aluminum. The filter bed comprises of two different packings arranged in series. The first packing encountered by the flow captures large drossy particles and the second packing captures the smaller drossy particles. Given the lengths as $L_1 = 0.7L_2$, $\epsilon_1 = \epsilon_2$, $d_{p,1} = 2d_{p,2}$, compute the ratio of the pressure drop across the first and second beds for the cases of (a) creeping flow through the bed (b) fully turbulent flow through the bed.

Solution 14.9.80

Answer: (a) 0.175 (b) 0.35

Chapter 15

Energy Transport

15.1 Learning objectives

At the end of this lesson, a student should be able to

1. recall the generalized Fourier heat conduction equation in rectangular coordinate systems
2. analyse Fourier's first law of heat conduction to determine the thermal gradients for steady heat flow across composite walls

15.2 Introduction

Energy transport or heat transfer is basically through two means: conduction and radiation. The third mode of heat transfer by convection could be imagined as a combination of conduction and advection. *Conduction* is a mode of energy transport by vibrational, rotational and translational degrees of freedom of atoms. The first two are predominant modes of energy exchange between atoms in solid and liquid states while the third is predominant in gaseous state. Energy transport by *radiation* involves emission and absorption of electromagnetic radiation as photons typically in the infrared wavelength range. Taking cue from *Lambert's law* that the attenuation of electromagnetic radiation in a medium is exponential ($q_z = q_0 \exp(-mz)$), the absorption coefficient m being higher for medium of higher density, one can consider that radiative heat transfer is mostly a surface phenomena for solids and liquids. Thus, it is often taken in to account in the boundary conditions.

15.3 Thermal equilibrium

In this section we talk about thermal equilibrium, how the second law of thermodynamics comes of use and the broad direction of heat transfer laws from this.

Consider the case of two identical blocks of T_1 and T_2 being brought in perfect contact with each other. The system is insulated from the rest of the universe. After a while, the two blocks are in thermal equilibrium if they reach a temperature of $\bar{T} = 0.5 * (T_1 + T_2)$. During this process, the entropy change of the first block is given by:

$$\Delta S_1 = \int_{T_1}^{\bar{T}} \frac{\delta q}{T}$$

At constant pressure, which is the typical condition during heat transfer, we can use the change in enthalpy for the amount of heat given to a body.

$$\delta q = mC_p dT$$

$$\Delta S_1 = \int_{T_1}^{\bar{T}} \frac{mC_p dT}{T} = mC_p \ln \left(\frac{\bar{T}}{T_1} \right)$$

Similarly, the entropy change for the second block is given by:

$$\Delta S_2 = \int_{T_2}^{\bar{T}} \frac{\delta q}{T} = mC_p \ln \left(\frac{\bar{T}}{T_2} \right)$$

The total entropy change is

$$\Delta S_{\text{total}} = \Delta S_1 + \Delta S_2 = mC_p \ln \left(\frac{\bar{T}^2}{T_1 T_2} \right)$$

If we can show the following equation to be true then it implies that $\Delta S_{\text{total}} \geq 0$ which means that the thermal equilibration is spontaneous and that heat flows from a location of high temperature to a location of low temperature until thermal equilibrium is achieved.

$$\frac{\bar{T}^2}{T_1 T_2} \geq 1 \tag{15.1}$$

$$\frac{\bar{T}^2}{T_1 T_2} = \frac{(T_1 + T_2)^2}{4T_1 T_2} = \frac{T_1^2 + T_2^2 + 2T_1 T_2}{4T_1 T_2}$$

Since T_1 and T_2 are different, the following is always true:

$$(T_1 - T_2)^2 \geq 0$$

This implies $T_1^2 + T_2^2 - 2T_1 T_2 \geq 0$ or $T_1^2 + T_2^2 \geq 2T_1 T_2$ or $T_1^2 + T_2^2 + 2T_1 T_2 \geq 4T_1 T_2$ or that equation 15.1 is true. Thus one can say that thermal equilibration is a spontaneous process.

15.4 Balance of Enthalpy

The governing equation for heat transfer by conduction can be derived similar to the way the governing equations for momentum transfer (Navier-Stokes equations) were derived. In that process we had followed the following sequence of steps:

- Balance equation or conservation principle
- Gauss theorem to convert surface integral to volume integral
- Linear constitutive relation
- Curie principle to simplify property tensor

We will follow the same steps to derive the governing equation for energy transport.

The balance equation for heat transfer is the first law of thermodynamics or the conservation of energy. If dU is the change in the internal energy, dq is the heat flow into the system, $-pdV$ is the work done by the system and dW_{other} is the work done by the system other than reduction in volume,

$$dU = dq - pdV + dW_{\text{other}}$$

dW_{other} is usually zero for the kind of situations we are interested in.

Using definition of enthalpy H as $H = U + PV$,

$$dH = dU + pdV + Vdp = dq - pdV + pdV + Vdp = dq + Vdp$$

Writing H as a function of T and p ,

$$dH = \left(\frac{\partial H}{\partial T} \right)_p dT + \left(\frac{\partial H}{\partial p} \right)_T dp$$

Since pressure is usually left constant at atmospheric pressure, H is usually H_p . Thus,

$$\boxed{dH_p = dq = \rho C_p dT = \rho C_p (T - T_{\text{ref}})} \quad (15.2)$$

If T_{ref} is chosen as a reference temperature where H_p is taken as 0 then one can integrate the above equation to arrive at the following.

$$H_p = \rho C_p (T - T_{\text{ref}}) \quad (15.3)$$

If the volumetric heat generation term is g and J_i is the surface heat flux through a surface of area dS and surface normal n_i , then we can write the energy balance for a control volume of volume dV as

$$\frac{D}{Dt} \int_V H dV = \int_V g dV - \int_S J_i n_i dS$$

Using equation 15.2 and making use of Reynold's transport theorem (section A.8) to take the material derivative inside the integral:

$$\int_V \rho \frac{D}{Dt} C_p (T - T_{\text{ref}}) dV = \int_V g dV - \int_S J_i n_i dS \quad (15.4)$$

Using the Gauss theorem to convert the surface integral to volume integral,

$$\int_V \rho \frac{D}{Dt} C_p (T - T_{\text{ref}}) dV = \int_V g dV - \int_V \frac{\partial J_i}{\partial x_i} dV \quad (15.5)$$

Since the integration is over the same control volume dV , we can equate the integrands.

$$\rho \frac{D}{Dt} C_p T = g - \frac{\partial J_i}{\partial x_i} \quad (15.6)$$

To obtain a relation between the surface heat flux J_i and its effects, we seek a linear constitutive equation as given in the following section.

15.5 Fourier's first law

Since surface heat flux J_i tends to increase temperatures locally leading to temperature differences in the body, it can be related to temperature gradients. The most general way of such a relation could be as given below:

$$J_j = -k_{ij} \frac{\partial T}{\partial x_i}$$

The thermal conductivity (k_{ij}) is a tensor of order 2. Usually, the materials of interest are polycrystalline metallic materials and liquids, both of which can be considered as isotropic in most of the situations¹. Using Curie principle, thermal conductivity being a material property, it must exhibit at least as much symmetry as the material itself. Thermal conductivity for an isotropic material will be an isotropic tensor and can be written as $k_{ij} = k\delta_{ij}$.

For single crystalline materials that are anisotropic, one can use symmetry arguments to reduce the number of independent values necessary to write the thermal conductivity tensor. **Lars Onsager's** reciprocal relations come of great use here in stating that for crystals of rotational symmetry such as 3, 4 and 6 fold, the property tensor can be represented by a symmetric matrix. Using the theorem that all symmetric tensors can be diagonalised (section A.2), and applying the four fold symmetry on the tensor to reduce the number of independent values to one as shown in section A.5, we can write the thermal conductivity tensor as following for *polycrystalline materials, liquids and single crystalline materials with four fold symmetry*:

$$k_{ij} = k\delta_{ij}$$

However, for single crystalline materials that donot possess cubic symmetry such as graphite, thermal conductivity should be written as a tensor (with two or more components).

Thus, for the kind of materials that we interested in (i.e., isotropic), the flux can be expressed in terms of temperature gradient as :

$$J_j = -k\delta_{ij} \frac{\partial T}{\partial x_i}$$

or

First law of Fourier heat conduction:

$$\boxed{J_i = -k \frac{\partial T}{\partial x_i}} \quad (15.7)$$

The Fourier's equation can be written in a co-ordinate system independent general form as:

$$\vec{q} = -k\vec{\nabla}T$$

such that it can be written for different co-ordinate systems as follows:

¹Highly textured polycrystalline materials and liquid crystals are exceptions

Cartesian (x_1, x_2, x_3) :

$$\vec{q} = -k \left(\frac{\partial T}{\partial x_1} \hat{x}_1 + \frac{\partial T}{\partial x_2} \hat{x}_2 + \frac{\partial T}{\partial x_3} \hat{x}_3 \right)$$

Cylindrical (r, θ, z) :

$$\vec{q} = -k \left(\frac{\partial T}{\partial r} \hat{r} + \frac{1}{r} \frac{\partial T}{\partial \theta} \hat{\theta} + \frac{\partial T}{\partial z} \hat{z} \right)$$

Spherical (r, θ, ϕ) :

$$\vec{q} = -k \left(\frac{\partial T}{\partial r} \hat{r} + \frac{1}{r} \frac{\partial T}{\partial \theta} \hat{\theta} + \frac{1}{r \sin \theta} \frac{\partial T}{\partial \phi} \hat{\phi} \right)$$

15.6 Fourier's second law

Substituting equation 15.7 in to 15.6:

$$\begin{aligned} \frac{D}{Dt} \rho C_p T &= g - \frac{\partial}{\partial x_i} \left(-k \frac{\partial T}{\partial x_i} \right) \\ \frac{D \rho C_p T}{Dt} &= \frac{\partial}{\partial x_i} \left(k \frac{\partial T}{\partial x_i} \right) + g \end{aligned} \quad (15.8)$$

For constant properties, using thermal diffusivity $\alpha = \frac{k}{\rho C_p}$

$$\boxed{\frac{DT}{Dt} = \frac{\partial T}{\partial t} + \vec{u} \cdot \vec{\nabla} T = \alpha \nabla^2 T + \frac{g}{\rho C_p}} \quad (15.9)$$

Expanding the ∇ operator for different co-ordinate systems:

Cartesian:

$$\frac{\partial T}{\partial t} + u_1 \frac{\partial T}{\partial x_1} + u_2 \frac{\partial T}{\partial x_2} + u_3 \frac{\partial T}{\partial x_3} = \alpha \left(\frac{\partial^2 T}{\partial x_1^2} + \frac{\partial^2 T}{\partial x_2^2} + \frac{\partial^2 T}{\partial x_3^2} \right) + \frac{g}{\rho C_p} \quad (15.10)$$

Cylindrical:

$$\frac{\partial T}{\partial t} + u_r \frac{\partial T}{\partial r} + \frac{u_\theta}{r} \frac{\partial T}{\partial \theta} + u_z \frac{\partial T}{\partial z} = \alpha \left(\frac{1}{r} \frac{\partial}{\partial r} \left[r \frac{\partial T}{\partial r} \right] + \frac{1}{r^2} \frac{\partial^2 T}{\partial \theta^2} + \frac{\partial^2 T}{\partial z^2} \right) + \frac{g}{\rho C_p} \quad (15.11)$$

Spherical:

$$\begin{aligned} &\frac{\partial T}{\partial t} + u_r \frac{\partial T}{\partial r} + \frac{u_\theta}{r} \frac{\partial T}{\partial \theta} + \frac{u_\phi}{r \sin \theta} \frac{\partial T}{\partial \phi} = \\ &\alpha \left(\frac{1}{r^2} \frac{\partial}{\partial r} \left[r^2 \frac{\partial T}{\partial r} \right] + \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left[\sin \theta \frac{\partial T}{\partial \theta} \right] + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2 T}{\partial \phi^2} \right) + \frac{g}{\rho C_p} \end{aligned} \quad (15.12)$$

Recognising that for solids, $\vec{u} = 0$, leading to $\frac{D}{Dt} = \frac{\partial}{\partial t} + \vec{u} \cdot \vec{\nabla} = \frac{\partial}{\partial t}$, we can use co-ordinate system independent notation to write the *Fourier's second law* as:

$$\boxed{\frac{\partial T}{\partial t} = \alpha \nabla^2 T + \frac{g}{\rho C_p}} \quad (15.13)$$

The expanded forms for the three co-ordinate systems of interest are:

Cartesian (x_1, x_2, x_3) :

$$\frac{\partial T}{\partial t} = \alpha \left(\frac{\partial^2 T}{\partial x_1^2} + \frac{\partial^2 T}{\partial x_2^2} + \frac{\partial^2 T}{\partial x_3^2} \right) + \frac{g}{\rho C_p} \quad (15.14)$$

Cylindrical (r, θ, z) :

$$\frac{\partial T}{\partial t} = \alpha \left(\frac{1}{r} \frac{\partial}{\partial r} \left[r \frac{\partial T}{\partial r} \right] + \frac{1}{r^2} \frac{\partial^2 T}{\partial \theta^2} + \frac{\partial^2 T}{\partial z^2} \right) + \frac{g}{\rho C_p} \quad (15.15)$$

Spherical (r, θ, ϕ) :

$$\frac{\partial T}{\partial t} = \alpha \left(\frac{1}{r^2} \frac{\partial}{\partial r} \left[r^2 \frac{\partial T}{\partial r} \right] + \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left[\sin \theta \frac{\partial T}{\partial \theta} \right] + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2 T}{\partial \phi^2} \right) + \frac{g}{\rho C_p} \quad (15.16)$$

15.7 Boundary conditions

Neumann boundary condition: Heat flux is specified at the boundary.

Dirichlet boundary condition: Temperature is specified at the boundaries.

Newton's Law of cooling: Heat flux as a function of boundary temperature is specified at the boundary.

The rate of heat transfer from a surface of a solid to the fluid it is in contact with is proportional to the difference in temperatures of the fluid and the solid.

$$q = h (T_s - T_\infty)$$

The heat transfer coefficient (h) is a property dependent on several factors including velocity of the fluid, geometry of the surface and thermophysical properties of the two materials.

A heat flux balance at the surface will connect the Fourier's equation with the Newton's law of cooling as follows:

$$q|_{x=0} = h (T_s - T_\infty) = -k \frac{\partial T}{\partial x} \Big|_{x=0}$$

Since h is always defined as a positive quantity irrespective of the direction of heat flow,

$$h = \left| \frac{-k \frac{\partial T}{\partial x} \Big|_{x=0}}{T_s - T_\infty} \right|$$

Interface resistance: When smooth surfaces of two solids are in perfect contact, the interface can be said to be at one temperature. However, if the surfaces are not smooth and the contact is not perfect, there could be a jump in the interface temperatures² and the resistance to heat flow across the interface is characterized by a parameter h , interfacial heat transfer coefficient. The heat flux across the two interfaces can then be written similar to Newton's law as

$$q|_{\text{interface}} = h (T_{s1} - T_{s2})$$

²at a macro-scale. The temperature will be continuous without a jump when measured at micro-scale. Kapitza resistance is an exception

Radiative heat flux: For gases at high temperatures or surfaces of solids or liquids at high temperatures, radiation can be a significant mode of energy transport. When expressed as a boundary heat flux, it can be written as:

$$q = e\sigma_{SB}T^4$$

σ_{SB} is the Stefan-Boltzmann constant and e is the emissivity. Radiative heat flux from surface 1 to surface 2 (of areas A_1 and A_2) that have *view factors* F_{12} and F_{21} is

$$q_{12} = A_1 F_{12} (T_1^4 - T_2^4) = A_2 F_{21} (T_1^4 - T_2^4)$$

15.8 Summary

1. Fourier's first law in different coordinate systems

Chapter 16

Steady state heat transfer in solids

16.1 Concept map




Figure 16.1: Concept map on heat transfer solutions

16.2 Steady state 1D heat transfer

16.2.1 Across a rectangular slab

At steady state, if q is the rate of heat transfer (Js^{-1}) across a slab area A :




Figure 16.2: Heat flow across a slab

$$\frac{q}{A} = -k \frac{\partial T}{\partial x}$$

If the surface temperatures of the slab are T_1 and T_2 at x_1 and x_2 , respectively, then:

$$\int_{T_1}^{T_2} dT = \frac{-q}{Ak} \int_{x_1}^{x_2} dx$$

$$T_2 - T_1 = \frac{q}{Ak}(x_1 - x_2) = -\frac{q}{Ak} \Delta x$$

$$\boxed{\frac{T_1 - T_2}{q} = \frac{\Delta x}{Ak}} \quad (16.1)$$

Taking the analogy of electricity, $T_1 - T_2$ is the driving force similar to voltage, q is the flux similar to current and $\frac{\Delta x}{Ak}$ is the resistance. Now the resistance to heat flow is known, they can be combined in serial and parallel similar to the circuits in electricity.

As can be seen from the equation for flux:

$$\frac{q}{A} = k \frac{T_1 - T_2}{\Delta x}$$

doubling the slab thickness Δx will halve the heat flux.

We can write the heat flux at the inner wall as follows:

$$\left. \frac{q}{A} \right|_1 = \left(k \frac{\Delta T}{\Delta x} \right) f \quad (16.2)$$

Here, the geometric factor f is equal to unity for planar shells.

16.2.2 Across a cylindrical wall

At steady state, if q is the rate of heat transfer (Js^{-1}) across a cylindrical wall of (variable) area $A = 2\pi rL$:

$$\frac{q}{A} = \frac{q}{2\pi rL} = -k \frac{\partial T}{\partial r}$$

Heat flow across a hollow cylindrical wall of inner radius R_1 and outer R_2 at temperatures T_1 and T_2 , respectively, is then given by:




Figure 16.3: Heat flow across a cylindrical wall

$$\int_{T_1}^{T_2} dT = \frac{-q}{2\pi Lk} \int_{R_1}^{R_2} \frac{dr}{r}$$

$$T_2 - T_1 = \frac{-q}{2\pi Lk} \ln \frac{R_2}{R_1}$$

$$\boxed{\frac{T_1 - T_2}{q} = \frac{\ln \frac{R_2}{R_1}}{2\pi Lk}} \quad (16.3)$$

Drawing the analogy to electricity as above, the resistance to heat flow across a cylindrical wall is $\frac{\ln \frac{R_2}{R_1}}{2\pi Lk}$.

As can be seen from the equation for flux:

$$\frac{q}{A}|_{r=R_1} = \frac{q}{2\pi L R_1} = k \frac{T_1 - T_2}{R_1 \ln \frac{R_2}{R_1}} = k \frac{T_1 - T_2}{R_1 \ln(1 + \frac{\Delta R}{R_1})}$$

Doubling the slab thickness ΔR will *not necessarily* halve the heat flux. It can be noted that in the limit of large curvature, $R_1 \rightarrow \infty$, $\frac{\Delta R}{R_1}$ is a small quantity and $\ln(1 + \frac{\Delta R}{R_1})$ can be approximated to $\frac{\Delta R}{R_1}$ leading to the above expression as:

$$\frac{q}{A}|_{r=R_1 \rightarrow \infty} = k \frac{T_1 - T_2}{R_1 \frac{\Delta R}{R_1}} = k \frac{T_1 - T_2}{\Delta R}$$

which is the limit where a cylindrical wall of thickness ΔR can be approximated to a rectangular slab of same thickness.

We can write the heat flux at the inner wall as follows:

$$\frac{q}{A}|_1 = \left(k \frac{\Delta T}{\Delta R} \right) f \quad (16.4)$$

Here, the geometric factor f for cylindrical shell is written as:

$$f = \frac{\frac{\Delta R}{R_1}}{\ln \left(1 + \frac{\Delta R}{R_1} \right)} \quad (16.5)$$

16.2.3 Across a spherical shell

At steady state, if q is the rate of heat transfer ($J s^{-1}$) across a spherical shell of (variable) area $A = 4\pi r^2$:

$$\frac{q}{A} = \frac{q}{4\pi r^2} = -k \frac{\partial T}{\partial r}$$

Heat flow across a hollow sphere of inner radius R_1 and outer R_2 at temperatures T_1 and T_2 , respectively, is then given by:

$$\begin{aligned} \int_{T_1}^{T_2} dT &= \frac{-q}{4\pi k} \int_{R_1}^{R_2} \frac{dr}{r^2} \\ T_2 - T_1 &= \frac{-q}{4\pi k} \left(\frac{1}{R_1} - \frac{1}{R_2} \right) \\ \boxed{\frac{T_1 - T_2}{q} = \frac{1}{4\pi k} \left(\frac{1}{R_1} - \frac{1}{R_2} \right)} \end{aligned} \quad (16.6)$$

Drawing the analogy to electricity as above, the resistance to heat flow across a cylindrical wall is $\frac{1}{4\pi k} \left(\frac{1}{R_2} - \frac{1}{R_1} \right)$.

$$\left. \frac{q}{A} \right|_{r=R_1 \rightarrow \infty} = k \frac{(T_1 - T_2) R_2}{\Delta R R_1} = k \frac{T_1 - T_2}{\Delta R} \left(1 + \frac{\Delta R}{R_1} \right) \Big|_{R_1 \rightarrow \infty} = k \frac{T_1 - T_2}{\Delta R}$$

which is the limit where a spherical shell of thickness ΔR can be approximated to a rectangular slab of same thickness.

We can write the heat flux at the inner wall as follows:

$$\left. \frac{q}{A} \right|_1 = \left(k \frac{\Delta T}{\Delta R} \right) f \quad (16.7)$$

Here, the geometric factor f for spherical shell is written as:

$$f = \left(1 + \frac{\Delta R}{R_1} \right) \quad (16.8)$$

16.2.4 Point effect of diffusion

When the temperature differences and the properties are kept constant, heat flux (heat per unit time per unit area) depends on the geometry - with the following geometries in the decreasing order of effectiveness: point, line, plane, edge, corner. Such a sequence of effectiveness of thermal diffusion arises from the amount of space available for exchange of energy. Point effect of diffusion comes of use when interpreting defects in casting.

As can be seen from the equation for flux:

Doubling the slab thickness ΔR will *not necessarily* halve the heat flux. It can be noted that in the limit of large curvature, $R_1 \rightarrow \infty$, $\frac{\Delta R}{R_1}$ is a small quantity and goes to zero leading to the above expression as:

$$\left. \frac{q}{A} \right|_{r=R_1 \rightarrow \infty} = k \frac{T_1 - T_2}{\Delta R}$$

which is the limit where a spherical wall of thickness ΔR can be approximated to a slab of same thickness.

The rationale behind this is the what we call as *point effect of diffusion*. Taking the wall thickness to be same, we plot the three geometries below:




Figure 16.4: Point effect of diffusion

16.2.5 Across a planar composite wall




Figure 16.5: Box type multi-walled furnace schematic created using Gemini 2.0 Flash.

In the figure 16.5, the multi-walled furnace is shown schematically. The wall comprises of a ceramic layer, glass wool layer and then a steel sheet that forms the furnace box. One can estimate the heat loss through this composite wall at steady state as follows.

Using the electrical analogy of the previous section, flux boundary condition $\frac{q}{A} = h(T_s - T_\infty)$ can be written such that the resistance to heat flow is $\frac{1}{Ah}$.

At steady state, if q is the rate of heat transfer (Js^{-1}) across a planar composite wall of constant area A :

$$\frac{q}{A} = h_a(T_a - T_1) = -k_{12}\frac{T_2 - T_1}{\Delta x_{12}} = -k_{23}\frac{T_3 - T_2}{\Delta x_{23}} = -k_{34}\frac{T_4 - T_3}{\Delta x_{34}} = h_b(T_4 - T_b)$$

In the figure 16.6, k_{12} is thermal conductivity of the ceramic wall of width Δx_{12} , k_{23} is thermal conductivity of the glass wool wall of width Δx_{23} , k_{34} is thermal conductivity of the steel wall of width Δx_{34} . The heat transfer coefficients are h_a for inner wall and h_b for the outer wall. The ambient temperature is T_b and the furnace temperature is T_a .

$$T_a - T_b = \frac{q}{A} \left[\frac{1}{h_a} + \frac{\Delta x_{12}}{k_{12}} + \frac{\Delta x_{23}}{k_{23}} + \frac{\Delta x_{34}}{k_{34}} + \frac{1}{h_b} \right]$$

Analogy with electricity: $\frac{1}{h}$ and $\frac{\Delta x}{k}$ act as resistances. Temperature is analogous to voltage difference (driving force for the current). $\frac{q}{A}$ is analogous to current.

16.2.6 Across a cylindrical composite wall




Figure 16.6: Schematic thermal profile across a composite wall of a furnace. The image of the furnace was created using Gemini 2.0 Flash.

Using the electrical analogue of the previous section, the heat flow across a composite hollow cylindrical wall is given by:

$$T_a - T_b = \frac{q}{2\pi L} \left[\frac{1}{r_1 h_1} + \frac{\ln \frac{r_2}{r_1}}{k_{12}} + \frac{\ln \frac{r_3}{r_2}}{k_{23}} + \frac{\ln \frac{r_4}{r_3}}{k_{34}} + \frac{1}{r_4 h_4} \right]$$

The radial distances of the walls from the centre for the tubular furnace are given as r_1 , r_2 etc., The length of the tubular furnace is L . Rest of the parameters are simialar to the rectangular case above.

16.3 Summary

1. Thermal resistances for rectangular coordinate system are: $\frac{1}{Ah}$ for convective boundary condition, $\frac{\Delta x}{Ak}$ for conduction across a slab of thickness Δx .
2. Thermal resistances for cylindrical coordinate system are: $\frac{1}{2\pi L r h}$ for convective boundary condition, $\frac{\log \frac{r_2}{r_1}}{2\pi L r_1 k}$ for conduction across a cylindrical slab of thickness $r_2 - r_1$ considering heat flux at the inner wall at radial distance r_1 .
3. As the radius of curvature becomes very large, a cylindrical or spherical shell can be assumed to be rectangular slab for constant heat flow across it.

16.4 Exercises

1. Heat is flowing at steady state through an annular wall of a cylinder of inner radius R_1 and outer radius R_2 . Thermal conductivity of the wall material is approximated to be linear function of temperature with a value of k_1 at the inner wall temperature T_1 and k_2 at the outer wall temperature T_2 . (a) Derive an expression for the heat flow across the cylindrical shell. (b) Simplify the expression for the case when the wall thickness is very small compared to the radius of the cylinder.
2. Example 6.3 of [Gaskell, 1992]. Hot water flows through a glass tube of inner radius 3 cm and outer radius 5 cm. The temperatures of the inner and outer surfaces of the tube are, respectively, 90 °C and 85 °C and the mean thermal conductivity of the glass is 0.84 W m⁻¹ K⁻¹. (a) Calculate the rate of heat loss from the tube per unit length. (b) By how much is the rate of heat loss decreased if the wall thickness of the tube is doubled keeping the inner radius same.

Answer: (a) 51.7 W m⁻¹ (b) 31.1 W m⁻¹

3. An iron slab of thickness 2 cm carries an electric current that generates heat at a rate of 10×10^6 W m⁻³. If the right side face of the slab is at 20 °C, what should be the temperature of the left side face such that all the heat flux in the slab is from the left face to the right face at steady state? Properties of steel are $k = 45$ W m⁻¹ K⁻¹, $\rho = 7210$ kg m⁻³ and $C_p = 750$ J kg⁻¹ K⁻¹.
4. Example 6.4 of [Gaskell, 1992]. A furnace wall consists of 15 cm thick silica brick ($k = 1.1$ W m⁻¹ K⁻¹), a 5 cm glass fibre ($k = 0.035$ W m⁻¹ K⁻¹) and a 1 cm steel ($k = 45$ W m⁻¹ K⁻¹). Inner temperature of the furnace is 500 °C and heat transfer coefficient on the inner wall is 15 W m⁻² K⁻¹. Ambient temperature is 20 °C and heat transfer coefficient on the outer wall is 20 W m⁻² K⁻¹. (a) Calculate the power loss per unit area of furnace wall at steady state. (b) Temperatures at each junction.

Answer: (a) 285.4 W m⁻² (b) $T_i = 481$ °C, $T_1 = 442$ °C, $T_2 \approx T_3 \approx 34$ °C.

5. A 50 cm long tubular furnace is made of a 1 cm thick silica tube of 10 cm inner radius kept in a 5 mm thick steel tube of 15 cm outer dia with glass wool in between. Knowing that the glass wool would melt at 800 °C and that furnace converts all its electrical power to heat energy, (a) what is the highest temperature that can be set in the furnace and (b) what is the power consumption at that temperature setting? Ignore end effects and assume steady state. The heat transfer coefficients for inside and outside of the furnace can be taken to be 20 W m⁻² K⁻¹. Assume room temperature to be 300 K.

6. Example 6.7 of [Gaskell, 1992]. A copper wire of diameter 1 mm has an insulating plastic sheath of 0.5 mm around it. The heat transfer coefficient on the surface exposed to ambient air at 30 °C is $8 \text{ W m}^{-2} \text{ K}^{-1}$. If the insulating plastic softens above 100 °C, calculate the maximum current that can be passed through the wire. Properties of copper are $k = 380 \text{ W m}^{-1} \text{ K}^{-1}$, $\sigma = 1.96 \times 10^{-8} \Omega \text{ m}$. Properties of the insulating plastic are $k = 0.35 \text{ W m}^{-1} \text{ K}^{-1}$ and $\sigma \approx 0 \Omega \text{ m}$.

Answer: 14.3 A

Chapter 17

Transient heat transfer in solids

17.0.1 Introduction

Within the domain of unidirectional heat transfer where the transient evolution of temperatures is of interest, one can think of two extreme cases. The first where the heat transfer from the solid is limited by thermal diffusion through its bulk. This is when the removal of heat from the interface is not constrained. An example could be a hot ceramic piece kept in front of a fan.

The second case is when bulk diffusion of heat within the solid is not constrained at all but the heat transfer at the interface is limited by the surrounding medium. An example could be a hot copper block kept in still air.

In the second case, one can assume that no thermal gradients would be present within the solid and use what is known as *lumped heat capacitance method* to obtain the variation of average temperature of the solid with time. This forms the *interface dominated* heat transfer.

In the first case, one needs to solve the equation of thermal diffusion in solid to determine the thermal gradients that drive the heat flux across the interface of the solid with the ambient medium. This forms the *conduction dominated* heat transfer.

17.0.2 Interface dominated

The change in the temperature of an object immersed in a fluid at different temperature can be estimated easily if the thermal conductivity of the object is high enough that no thermal gradients develop within the object.

If the characteristic length scale of the object is L , we require that the inner temperature of the object T_i is as close to the surface temperature T_s as possible. A balance of flux at the surface gives:

$$k \frac{T_i - T_s}{L} = h (T_s - T_\infty)$$

or

$$\frac{T_i - T_s}{T_s - T_\infty} = \frac{hL}{k}$$

We define Biot Number as

$$Bi = \frac{hL}{k}$$

If $Bi \leq 0.1$, T_i is close enough to T_s that thermal gradients within the object can be neglected so that Newtonian cooling is applicable. In such as case, we can write,

$$hA(T - T_\infty) = -\rho C_p V \frac{dT}{dt}$$

$$\int_{T_0}^T \frac{dT}{T - T_\infty} = \frac{-hA}{\rho C_p V} \int_0^t dt$$

or

$$\ln \frac{T - T_\infty}{T_0 - T_\infty} = \frac{-hAt}{\rho C_p V}$$

or

$$\frac{T - T_\infty}{T_0 - T_\infty} = \exp\left(-\frac{hAt}{\rho C_p V}\right)$$

Defining V/A as L , the characteristic length scale,

$$\frac{ht}{\rho C_p L} = \frac{hL}{k} \frac{\alpha t}{L^2} = Bi.Fo$$

where, we define Fourier number as:

$$Fo = \frac{\alpha t}{L^2} = \frac{kt}{\rho C_p L^2}$$

Thus, when $Bi \leq 0.1$,

$$\frac{T - T_\infty}{T_0 - T_\infty} = \exp(-Bi.Fo)$$

17.0.3 Conduction dominated

In problems where heat transfer is dominated by conduction, temperature as a function of time and spatial coordinates can be obtained by solving the Fourier heat conduction equation.

For the problem of semi-infinite domain where temperature at one end is fixed and we are interested in its evolution as a function of distance and time, the governing equation can be written for a one dimensional case as follows.

$$\frac{\partial T}{\partial t} = \alpha \frac{\partial^2 T}{\partial x^2}$$

While variable separation is one way of solving this equation, it leads to summation of a series. We use a co-ordinate transformation to make the equation simpler.

Put

$$\eta = \frac{x}{2\sqrt{\alpha t}}$$

leading to

$$\frac{\partial \eta}{\partial x} = \frac{1}{2\sqrt{\alpha t}}$$




Figure 17.1: Regimes of domination of convective and conduction heat transfer

$$\frac{\partial \eta}{\partial t} = \frac{-\eta}{2t}$$

$$\frac{\partial T}{\partial \eta} = \frac{\partial T}{\partial x} \frac{1}{2\sqrt{\alpha t}}$$

$$\frac{\partial^2 T}{\partial \eta^2} = \frac{\partial^2 T}{\partial x^2} \frac{1}{4\alpha t}$$

Equation 17.0.3 becomes

$$\frac{\partial^2 T}{\partial \eta^2} = -2\eta \frac{\partial T}{\partial \eta}$$

or

$$\frac{\ddot{T}}{\dot{T}} = -2\eta$$

Integrating once,

$$\log \dot{T} = -\eta^2 + \text{constant}$$

or

$$\dot{T} = C_1 e^{-\eta^2}$$

Integrating once more,

$$T = \int_{\eta=0}^{\eta=\eta} C_1 e^{-\eta^2} d\eta + C_2$$

The integral cannot be simplified and is often given as a tabulated function with the following definition and properties

$$\text{erf}(\eta) = \frac{2}{\sqrt{\pi}} \int_0^{\eta} e^{-\eta^2} d\eta$$

$$\frac{\partial}{\partial \eta} \text{erf}(\eta) = \frac{2}{\sqrt{\pi}} e^{-\eta^2}$$

$$\text{erf}(0) = 0$$

$$\text{erf}(\infty) = 1$$

$$\text{erf}(-\eta) = -\text{erf}(\eta)$$

Thus, the solution of 17.0.3 in a semi-infinite domain can be written as :

$$T = A \text{erf}\left(\frac{x}{2\sqrt{\alpha t}}\right) + B$$

The constants A and B can be determined using the boundary conditions.

17.1 Moving boundary condition

Problem: Liquid is poured at T_M in a *thick* mould kept at T_0 . Assuming that all the latent heat is extracted through mould, arrive at the rate of solidification.




Figure 17.2: Temperature profile during solidification

Solution:

Solidification is usually antiparallel to the direction of heat flux¹

¹Solidification in undercooled melts is an exception

Heat flux at $x = 0$ is

$$\vec{J} = -k_m \left. \frac{\partial T}{\partial x} \right|_{x=0} \hat{x}$$

Latent heat release per unit volume of solid formed is $\rho_s \Delta H_f$

Let the heat transfer be across a constant mould-solid surface area of A

Balancing the two,

$$AJ = -\rho_s \Delta H_f \frac{\partial V}{\partial t}$$

since a positive J implies heat flux in $+\hat{x}$ direction leading to a negative rate of solidification.

$$Ak_m \left. \frac{\partial T}{\partial x} \right|_{x=0} = \rho_s \Delta H_f \frac{\partial V}{\partial t}$$

Writing the error function solution to the temperature in the mould (properties of mould indicated by subscript m),

$$\frac{T_M - T}{T_M - T_0} = \operatorname{erf}\left(\frac{-x}{2\sqrt{\alpha_m t}}\right)$$

Substituting,

$$Ak_m(T_M - T_0) \frac{2}{\sqrt{\pi}} \frac{1}{2\sqrt{\alpha_m t}} = \rho_s \Delta H_f \frac{\partial V}{\partial t}$$

or

$$\frac{1}{A} \frac{\partial V}{\partial t} = \frac{(T_M - T_0)}{\rho_s \Delta H_f \sqrt{\pi}} \sqrt{k_m \rho_m C_{pm}} \frac{1}{\sqrt{t}}$$

Define *heat diffusivity* H_D as

$$\boxed{H_D = \sqrt{k_m \rho_m C_{pm}}}$$

Integrating from $V = 0$ at $t = 0$ to $V = V$ at $t = t$,

$$\boxed{\frac{V}{A} = \frac{2}{\sqrt{\pi}} \frac{(T_M - T_0) H_{Dm}}{\rho_s \Delta H_f} \sqrt{t}}$$

Chvorinov's Rule:

$$\frac{V}{A} \propto \sqrt{t}$$

17.1.1 Solidification: mould and solid conductivity controlled

Problem: Liquid at T_M is poured in to a mould at T_0 . Heat transfer is controlled by conduction through solid as well as mould. If the mould-solid interface temperature is T_S after a thickness of M of solid has formed, derive expressions to estimate the two quantities.

Boundary conditions:




Figure 17.3: Temperature profile during solidification

BC1: $T = T_0$ at $x = -\infty$

BC2: $T = T_S$ at $x = 0$ and $t = \tau$

BC3: Flux balance

$$-k_m \left. \frac{\partial T}{\partial x} \right|_{x \rightarrow -0} = -k_s \left. \frac{\partial T}{\partial x} \right|_{x \rightarrow +0}$$

BC4: $T = T_M$ at $x = M$ and $t = \tau$

BC5: Flux balance

$$Ak_s \left. \frac{\partial T}{\partial x} \right|_{x=M} = \rho_s \Delta H_f \frac{\partial V}{\partial t}$$

Solution:

Using BC1 and BC2, write the error function solution for heat conduction in the mould as:

$$\frac{T_S - T}{T_S - T_0} = \text{erf}\left(\frac{-x}{2\sqrt{\alpha_m t}}\right)$$

Similarly the error function solution for heat conduction in the solid is:

$$T = A \text{erf}\left(\frac{x}{2\sqrt{\alpha_s t}}\right) + B$$

Using BC2 and BC4 and naming $\frac{M}{2\sqrt{\alpha_s \tau}}$ as ϕ , write the solution for temperature in the solid as

$$T = T_S + \frac{T_M - T_S}{\text{erf}(\phi)} \text{erf}\left(\frac{x}{2\sqrt{\alpha_s t}}\right)$$

BC3 provides an estimate of T_S for a given ϕ :

$$k_m \frac{T_S - T_0}{\sqrt{\pi \alpha_m \tau}} = k_s \frac{T_M - T_S}{\sqrt{\pi \alpha_s \tau}} \frac{1}{\text{erf}(\phi)}$$

Using the definition of heat diffusivity,

$$H_{Dm}(T_S - T_0) = \frac{H_{Ds}}{\text{erf}(\phi)}(T_M - T_S)$$

Call

$$p = \frac{H_{D_s}}{H_{D_m} \text{erf}(\phi)}$$

$$\boxed{T_S = \frac{pT_M + T_0}{p + 1}}$$

BC5 provides an estimate for ϕ as a function of physical parameters.

$$Ak_s \frac{2}{\sqrt{\pi}} e^{-\phi^2} \frac{T_M - T_S}{\text{erf}(\phi) 2\sqrt{\alpha_s t}} = \rho_s \Delta H_f \frac{\partial V}{\partial t}$$

Recognising that $\frac{V}{A} = M$,

$$k_s \frac{2}{\sqrt{\pi}} e^{-\phi^2} \frac{(T_M - T_S)}{2\sqrt{\alpha_s t} \text{erf}(\phi)} = \rho_s \Delta H_f \frac{\partial M}{\partial t}$$

Integrating the equation from $M = 0$ at $t = 0$ to $M = M$ at $t = \tau$,

$$k_s \frac{2}{\sqrt{\pi}} e^{-\phi^2} \frac{(T_M - T_S) \sqrt{\tau}}{\sqrt{\alpha_s} \text{erf}(\phi)} = \rho_s \Delta H_f M$$

Simplifying,

$$\boxed{\phi \text{erf}(\phi) e^{\phi^2} = \frac{C_{ps}(T_M - T_S)}{\Delta H_f \sqrt{\pi}}}$$

Using a table / plot of $\phi \text{erf}(\phi) e^{\phi^2}$ as a function of ϕ , one can look up for the RHS of above equation for the corresponding ϕ which gives the relation $M = 2\phi\sqrt{\alpha_s \tau}$.

17.2 Exercises

1. A long copper wire of 2 mm diameter is exposed to air stream at a temperature of 400 K. After a minute, the average temperature of the wire increased from 280 K to 350 K. (a) Estimate the average heat transfer coefficient on the surface (b) Using the Biot number, comment on the validity of your solution.
2. Small droplets of a molten glass maintain their amorphicity if they cool at a rate of atleast 10 K s^{-1} measured at 1070 K. For a spherical droplet with 0.1 mm diameter, what is the required heat transfer coefficient to achieve the minimum cooling rate? The quench environment is maintained at 293 K. Properties of glass are $\rho = 3000 \text{ kg m}^{-3}$, $C_p = 840 \text{ J kg}^{-1} \text{ K}^{-1}$, $k = 17 \text{ W m}^{-1} \text{ K}^{-1}$. Verify if your answer is valid for lumped capacitance method to work.
3. A typical human body generates about 100 W due to metabolism. In order to keep the body temperature at 37°C , the heat must be dissipated through various mechanisms such as convective heat transfer, radiation, evaporation and conduction that are dynamically balanced depending on the outside temperature. If the heat loss is significant and the core temperature drops below 21°C , death occurs. Assuming the surface area of a human body to be about 2 m^2 , estimate how long a human can stay alive in (a) quiescent water at 10°C where $h = 230 \text{ W m}^{-2} \text{ K}^{-1}$ and (b) in flowing water at 10°C moving at 0.25 m s^{-1} where $h = 580 \text{ W m}^{-2} \text{ K}^{-1}$. Assume C_p of human body to be about $3470 \text{ J kg}^{-1} \text{ K}^{-1}$.
4. A two inch slab of aluminium is cast in a mold made of silica sand on one side and an unknown material on the other side. The cast slab is sectioned to look at the plane of last solidification that can be identified by porosity. If it is known that the plane is located 30 mm away from the silica side of the mould, (a) estimate the heat diffusivity of the unknown mould material. From the properties of mould materials given below, (b) guess which one comes closest. Neglect superheat.

Typical values of physical properties:

Material	k in $\text{W m}^{-1} \text{ K}^{-1}$	ρ in kg m^{-3}	C_p in $\text{J kg}^{-1} \text{ K}^{-1}$
Silica	0.6	1500	1160
Mullite	0.37	1600	770
Zircon	1.0	2720	840

5. A liquid metal (L) at temperature T_p is poured into a mould (m) kept at temperature T_0 . (a) If the mould-metal surface reaches thermal equilibrium instantly, find its temperature T_s when the freezing is yet to start. (b) A component is formed from an alpha brass alloy poured into a mould kept at 25°C . If the freezing takes place over a temperature range from 1055°C to 1045°C , find the minimum pouring temperature to prevent instantaneous freezing. Properties are as follows. $k_m = 1.6 \text{ W m}^{-1} \text{ K}^{-1}$, $k_L = 109 \text{ W m}^{-1} \text{ K}^{-1}$, $\rho_m = 3.2 \times 10^3 \text{ kg m}^{-3}$, $\rho_L = 8.52 \times 10^3 \text{ kg m}^{-3}$, $C_{p,m} = 1 \times 10^3 \text{ J kg}^{-1} \text{ K}^{-1}$, $C_{p,L} = 385 \text{ J kg}^{-1} \text{ K}^{-1}$.

Chapter 18

Heat tranfer with advection term

18.1 Steady state heat transfer

18.1.1 Heat transfer normal to plug flow

Plug flow is defined as spatially constant fluid flow. One usually approximates flow regimes in a chemical reactor to be plug flow. Also, flow across a porous medium under constant pressure drop leads to constant flow.

The equation for heat transfer is given as:

$$\frac{\partial T}{\partial t} + u_1 \frac{\partial T}{\partial x_1} + u_2 \frac{\partial T}{\partial x_1} + u_3 \frac{\partial T}{\partial x_1} = \alpha \left(\frac{\partial^2 T}{\partial x_1^2} + \frac{\partial^2 T}{\partial x_2^2} + \frac{\partial^2 T}{\partial x_3^2} \right) + \frac{g}{\rho C_p}$$

Let us assume that the constant flow is along $\hat{x}_1$ and the steady state unidirectional heat transfer is along $\hat{x}_2$. Setting these values, we can see that the governing equation reduces to:

$$k \frac{\partial^2 T}{\partial x_2^2} + g = 0$$

Thus, plug flow normal to steady state unidirectional heat transfer has no effect on the temperature profile. Since there are no velocity gradients in a plug flow, viscous dissipation is also not considered. Thus, often, $g = 0$.

In the case of a velocity profile such as channel flow normal to steady state unidirectional heat transfer, the equation remains the same except that the source term g can be given by the viscous dissipation. Assuming that the fluid is Newtonian and the flow to be channel flow, we can write:

$$k \frac{\partial^2 T}{\partial x_2^2} + \mu \frac{u_0^2}{\delta^2} = 0$$

We can solve the above equation subject to the following boundary conditions:

BC1:

$$T|_{x_2=0} = T_0$$

BC2:

$$\left. \frac{\partial T}{\partial y} \right|_{x_2=\delta} = 0$$

$$\frac{k}{\mu u_0^2} (T - T_0) = \frac{x_2}{\delta} - \frac{1}{2} \left(\frac{x_2}{\delta} \right)^2$$

18.1.2 Heat transfer along plug flow

Let us assume that the constant flow and the steady state unidirectional heat transfer are both along $\hat{x}_1$. We can write the governing equation as:

$$u_0 \frac{\partial T}{\partial x} = \alpha \frac{\partial^2 T}{\partial x^2} + \frac{g}{\rho C_p}$$

If we ignore heat generation term due to viscous dissipation, then the solution can be written subject to the following boundary conditions.

BC1:

$$T|_{x \rightarrow x_1} = T_1$$

BC2:

$$T|_{x \rightarrow x_2} = T_2$$

The solution is of the form

$$T = A \exp \left(\frac{u_0 x}{\alpha} \right) + B$$

Applying the boundary conditions, we get the solution as

$$\frac{T_1 - T}{T_1 - T_2} = \frac{\exp \left(\frac{u_0 x_1}{\alpha} \right) - \exp \left(\frac{u_0 x}{\alpha} \right)}{\exp \left(\frac{u_0 x_1}{\alpha} \right) - \exp \left(\frac{u_0 x_2}{\alpha} \right)}$$

In the limit of $u_0 \rightarrow 0$, we note that $\frac{u_0 x}{\alpha}$ is very small so that $\exp \left(\frac{u_0 x}{\alpha} \right) \approx 1 + \frac{u_0 x}{\alpha}$.

This makes the solution take the following form:

$$\frac{T_1 - T}{T_1 - T_2} \approx \frac{\left[1 + \left(\frac{u_0 x_1}{\alpha} \right) \right] - \left[1 + \left(\frac{u_0 x}{\alpha} \right) \right]}{\left[1 + \left(\frac{u_0 x_1}{\alpha} \right) \right] - \left[1 + \left(\frac{u_0 x_2}{\alpha} \right) \right]} = \frac{x_1 - x}{x_1 - x_2}$$

One can see that as $u_0 \rightarrow 0$, the solution approaches the linear profile as in steady state conduction for unidirectional heat transfer.

18.2 Exercises

1. A journal bearing of outer diameter 20 cm has a separation between the rotating shaft and the stationary journal of 1 mm filled with a lubricant liquid. The angular velocity of the shaft is 1000 rpm. Assuming that the shaft is kept at 20 °C and the journal at 30 °C, determine the temperature distribution along the radial direction in the lubricant layer taking viscous dissipation into account. The properties of the lubricant are: $\rho = 900 \text{ kg m}^{-3}$, $k = 0.15 \text{ W m}^{-1} \text{ K}^{-1}$, $\mu = 0.8 \text{ Pa s}$. Calculate the maximum temperature in the liquid lubricant layer. Assume the liquid to be flowing with usual limitations as that of Couette flow.

18.3 Heat transfer in a smooth pipe

Energy transport in fluids involves the complete form of equation 15.9.

$$\frac{\partial T}{\partial t} + \vec{u} \cdot \vec{\nabla} T = \alpha \nabla^2 T + \frac{g}{\rho C_p} \quad (18.1)$$

We will limit this chapter to the cases with the following assumptions:

- $\vec{u}$ is known analytically
- Flow is unidirectional, steady state and fully developed
- Heat transfer is steady state

Problem: For a fluid flowing unidirectionally through a pipe at steady state and with fully developed velocity profile and a given entry temperature, what is $T(r, z)$ for a given surface heat flux. In addition to the assumptions above, we make the following ones too.

Assumptions:

- $\vec{u} = u_{\max} \left[1 - \left(\frac{r}{R} \right)^2 \right] \hat{z}$
- Surface heat flux is constant. $q_0 = k \frac{\partial T}{\partial r} = \text{constant}$
- Cylindrical symmetry. Nothing happens along $\hat{\theta}$ direction.

We can write the governing equation as follows:

$$u_{\max} \left[1 - \left(\frac{r}{R} \right)^2 \right] \frac{\partial T}{\partial z} = \alpha \left[\frac{1}{r} \frac{\partial}{\partial r} r \frac{\partial T}{\partial r} \right]$$

subject to the following boundary conditions:

BC1: Finite temperature at the center of pipe

$$T(r = 0, z) = \text{finite}$$

BC2: Constant wall heat flux

$$q_0 = -k \frac{\partial T}{\partial r}$$

BC3: Entry temperature

$$T(r, z = 0) = T_0$$

Before attempting to solve the above differential equation, it is a good idea to non-dimensionalize the variables that could possibly simplify the derivation as well as the final expressions. In this process, we recognise that $\frac{q_0 R}{k}$ has units of temperature, R is the characteristic length scale, $\tau_0 = \frac{R^2}{\alpha}$ is the characteristic time scale and that along $\hat{z}$ the fluid moves a characteristic distance of $u_{\max} \tau_0$ that can be used to scale z .

Scaling:

$$T^* = \frac{T - T_0}{\frac{q_0 R}{k}}$$

$$r^* = \frac{r}{R}$$

$$z^* = \frac{z \alpha}{u_{\max} R^2}$$

leading to

$$\frac{\partial T}{\partial z} = \frac{\partial T^*}{\partial z^*} \frac{k R u_{\max}}{\alpha q_0}$$

$$\frac{\partial T}{\partial r} = \frac{\partial T^*}{\partial r^*} \frac{k}{q_0 R^2}$$

Thus the governing equation can be non-dimensionalised to:

$$(1 - r^{*2}) \frac{\partial T^*}{\partial z^*} = \frac{1}{r^*} \frac{\partial}{\partial r^*} \left(r^* \frac{\partial T^*}{\partial r^*} \right)$$

The above equation needs to be solved subject to the following boundary conditions:

BC1:

$$T^*(r^* = 0, z^*) = \text{finite}$$

BC2:

$$\left. \frac{\partial T^*}{\partial r^*} \right|_{r^*=1} = 1$$

BC3:

$$T^*(r^*, z^* = 0) = 0$$

As we would notice later, BC3 should actually be stated in integral form to state that the starting temperature is not given as a function of r^* but as a flow averaged (bulk) value.

We propose the following solution:

$$T^* = C_0 z^* + \phi(r^*)$$

Substituting the solution into the governing equation,

$$(1 - r^{*2}) C_0 = \frac{1}{r^*} \frac{\partial}{\partial r^*} \left(r^* \frac{\partial \phi}{\partial r^*} \right)$$

Integrating once w.r.t r^* ,

$$r^* \frac{\partial \phi}{\partial r^*} = C_0 \left(\frac{r^{*2}}{2} - \frac{r^{*4}}{4} \right) + C_1$$

Integrating once more,

$$\phi = C_0 \left(\frac{r^{*2}}{4} - \frac{r^{*4}}{16} \right) + C_1 \ln r^* + C_2$$

Thus, the solution is:

$$T^* = C_0 z^* + C_0 \left(\frac{r^{*2}}{4} - \frac{r^{*4}}{16} \right) + C_1 \ln r^* + C_2 \quad (18.2)$$

BC1 implies $C_1 = 0$

BC2 implies $C_0 = 4$

$$T^* = 4z^* + \left(\frac{r^{*2}}{1} - \frac{r^{*4}}{4} \right) + C_2 \quad (18.3)$$

BC3 is not useful in arriving at C_2 . We need one more boundary condition. We use the *overall* balance of energy for the same.

BC4: The overall energy entering the pipe at a length z is given by

$$Q_z = \int_0^{2\pi} \int_0^R \rho C_p T(r, z) u(r) dr \quad r d\theta$$

The overall energy entering the pipe at a length $z = 0$ is given by

$$Q_0 = \int_0^{2\pi} \int_0^R \rho C_p T_0 u(r) dr \quad r d\theta$$

The overall balance $Q_z - Q_0 = 2\pi R z q_0$ can now be written as:

$$\int_0^{2\pi} \int_0^R \rho C_p (T - T_0) u_{\max} \left[1 - \left(\frac{r}{R} \right)^2 \right] dr \quad r d\theta = 2\pi R z q_0 \quad (18.4)$$

$$\int_0^R (T - T_0) \left[1 - \left(\frac{r}{R} \right)^2 \right] r dr = \frac{R z q_0}{u_{\max} \rho C_p} = \frac{R q_0}{k} \frac{z \alpha}{u_{\max}}$$

This can be expressed in the non-dimensional form as:

$$\int_0^1 T^* (1 - r^{*2}) r^* dr^* = z^* \quad (18.5)$$

Substituting 18.3 in to 18.5,

$$\int_0^1 \left[4z^* + r^{*2} - \frac{1}{4} r^{*4} + C_2 \right] [1 - r^{*2}] r^* dr^* = z^*$$

$$\int_0^1 \left[r^{*2} - \frac{1}{4} r^{*4} + C_2 \right] [1 - r^{*2}] r^* dr^* = 0$$

$$\frac{C_2}{4} + \int_0^1 \left[r^{*2} - \frac{1}{4} r^{*4} \right] [1 - r^{*2}] r^* dr^* = 0$$

We use the above integral BC4 to arrive at $C_2 = \frac{7}{24}$. Thus, the final solution for temperature distribution in a fluid flowing through a tube with constant heat flux is

$$T^* = 4z^* + r^{*2} - \frac{1}{4}r^{*4} - \frac{7}{24}$$

Surface temperature is given by setting $r = R$. Express T_s by setting $r^* = 1$ as follows:

$$T_s^* = 4z^* + 1^2 - \frac{1^4}{4} - \frac{7}{24} = 4z^* + \frac{11}{24}$$

$$\frac{T_s - T_0}{\frac{q_0 R}{k}} = 4 \frac{z \alpha}{u_{\max} R^2} + \frac{11}{24}$$

$$T_s = T_0 + \frac{4z q_0}{R u_{\max} \rho C_p} + \frac{11}{24} \frac{q_0 R}{k} = T_0 + \frac{4z q_0}{R u_{\max} \rho C_p} + \frac{11}{48} \frac{q_0 D}{k} \quad (18.6)$$

18.3.1 Bulk temperature

We now define *bulk temperature* or *flow averaged temperature* T_b as

$$T_b = \frac{\langle T u_z \rangle}{\langle u_z \rangle} = \frac{\int_0^{2\pi} \int_0^R T(r, z) u(r) dr \, r d\theta}{\int_0^{2\pi} \int_0^R u(r) dr \, r d\theta}$$

For our case of unidirectional, fully developed flow,

$$T_b = \frac{\int_0^R T(r, z) u(r) r dr}{\int_0^R u(r) r dr}$$

Now, look at equation 18.4 to write the following.

Numerator is

$$\frac{2\pi R z q_0}{\rho C_p} + T_0 \int_0^{2\pi} \int_0^R u(r) dr \, r d\theta = \frac{2\pi R z q_0}{\rho C_p} + 2\pi u_{\max} \frac{R^2}{4} T_0$$

Denominator is

$$2\pi u_{\max} \frac{R^2}{4}$$

$$T_b = T_0 + \frac{4q_0 z}{\rho C_p R u_{\max}}$$

Rearranging using 18.6,

$$\frac{(T_s - T_b) k}{q_0 D} = \frac{11}{48}$$

$$Nu = \frac{q_0 D}{(T_s - T_b) k} = \frac{48}{11}$$

We define the heat transfer coefficient for tube flow as $h = \frac{q_0}{(T_s - T_b)}$.

18.4 Constant Surface Temperature solution

The solution is in the form of an infinite series:

$$\frac{T_s - T}{T_s - T_b} = \sum_{n=0}^{\infty} C_{2n} \left(\frac{r}{R} \right)^{2n}$$

Where the coefficients are given as follows:

$$\begin{aligned} C_0 &= 1 \\ C_2 &= -\frac{1}{4}\lambda_0^2 = -1.828397 \\ C_{2n} &= \frac{\lambda_0^2}{(2n)^2} (C_{2n-4} - C_{2n-2}) \\ \lambda_0 &= 2.704364 \end{aligned}$$

The Nusselt number for the above temperature distribution can be shown to be:

$$Nu = \frac{\lambda_0^2}{2} = 3.657$$

18.5 Definitions of some non-dimensional numbers

Biot Number:

$$Bi = \frac{hL}{k_s}$$

Fourier Number:

$$Fo = \frac{\alpha t}{L^2}$$

Grashof Number:

$$Gr_L = \frac{g\beta(T_s - T_{\infty})L^3}{\nu^2}$$

Rayleigh Number:

$$Ra_x = \frac{g\beta(T_s - T_{\infty})x^3}{\nu\alpha}$$

Nusselt Number:

$$Nu_L = \frac{hL}{k_f}$$

Peclet Number:

$$Pe_L = \frac{VL}{\alpha}$$

Prandtl Number:

$$Pr = \frac{\nu}{\alpha}$$

Stanton Number:

$$St = \frac{h}{\rho V C_p}$$

18.6 Forced convection correlations

External flow over flat plate at uniform surface temperature:

- Laminar external flow for $Pr \geq 0.6$:

$$Nu_x = \frac{h_x x}{k} = 0.332 Re_x^{1/2} Pr^{1/3}$$

- Laminar external flow for $0.6 < Pr < 50$:

$$\bar{N}u_x = \frac{\bar{h}_x x}{k} = 0.664 Re_x^{1/2} Pr^{1/3}$$

- Laminar Flow of liquid metal for $Pr \leq 0.05$, $Pe_x \geq 10^2$ where $Pe_x = Re_x Pr$:

$$Nu_x = 0.565 Pe_x^{1/2}$$

- Laminar flow of fluids of all Prandtl numbers, $Pe_x \geq 10^2$:

$$Nu_x = \frac{0.3387 Re_x^{1/2} Pr^{1/3}}{\left[1 + \left(\frac{0.0468}{Pr}\right)^{2/3}\right]^{1/4}}$$

- Turbulent flow for $0.6 < Pr < 60$, $Re < 10^8$:

$$Nu_x = St Re_x Pr = 0.0296 Re_x^{4/5} Pr^{1/3}$$

- Laminar + Turbulent flow where the representative $Re_{x,c}$ for transition is taken as 5×10^5 , $0.6 < Pr < 60$, $5 \times 10^5 < Re_L < 10^8$:

$$\bar{N}u_L = \left(0.037 Re_L^{4/5} - 871\right) Pr^{1/3}$$

Flat plate with uniform surface flux:

- Laminar flow, $Pr \geq 0.6$:

$$Nu_x = 0.453 Re_x^{1/2} Pr^{1/3}$$

- Turbulent flow, $0.6 < Pr < 60$:

$$Nu_x = 0.0308 Re_x^{4/5} Pr^{1/3}$$

External flow over circular cylinder:

- Correlation for wide range of parameters:

$$\bar{N}u_D = \frac{\bar{h}D}{k} = C Re_D^m Pr^{1/3}$$

Re_D	C	m
0.4 – 4	0.989	0.33
4 – 40	0.911	0.385
40 – 4000	0.683	0.466
$4 \times 10^3 - 4 \times 10^4$	0.193	0.618
$4 \times 10^4 - 4 \times 10^5$	0.027	0.805

When properties are not constant over the temperature range involved, for $0.7 < Pr < 500$ and $1 < Re_D < 10^6$,

$$\bar{Nu}_D = C Re_D^m Pr^n \left(\frac{Pr}{Pr_s} \right)^{\frac{1}{4}}$$

If $Pr \leq 10$, $n = 0.37$ and if $Pr \geq 10$, $n = 0.36$

Re_D	C	m
1- 40	0.75	0.4
40 - 10^3	0.51	0.5
2×10^5 - 10^6	0.076	0.7

Comprehensive equation for all Re_D and $Pr > 0.2$

$$\bar{Nu}_D = 0.3 + \frac{0.62 Re_D^{1/2} Pr^{1/3}}{\left[1 + \left(\frac{0.4}{Pr} \right)^{2/3} \right]^{\frac{1}{4}}} \left[1 + \left(\frac{Re_D}{282000} \right)^{\frac{5}{8}} \right]^{\frac{4}{5}}$$

External flow over a sphere :

- For $0.71 < Pr < 380$, $3.5 < Re_D < 7.6 \times 10^4$, $1 < \mu/\mu_s < 3.2$:

$$Nu_D = 2 + \left[0.4Re_D^{1/2} + 0.06Re_D^{2/3} \right] Pr^{0.4} \left[\frac{\mu}{\mu_s} \right]^{1/4}$$

- For freely falling droplets of liquids:

$$Nu_D = 2 + 0.6Re_D^{1/2} Pr^{1/3}$$

Internal flow through circular tube:

- Laminar, fully developed flow, uniform heat flux, $Pr \geq 0.6$:

$$Nu_D = 4.36$$

- Laminar, fully developed flow, uniform surface temperature, $Pr \geq 0.6$:

$$Nu_D = 3.66$$

- Turbulent, fully developed flow, $0.7 \leq Pr \leq 16700$, $Re_D \geq 10^4$, $L/D \geq 10$:

$$Nu_D = 0.027Re_D^{4/5} Pr^{1/3} \left(\frac{\mu}{\mu_s} \right)^{0.14}$$

- Liquid metals, Turbulent, fully developed, uniform heat flux, $3.6 \times 10^3 < Re_D < 9.05 \times 10^5$, $10^2 < Pe_D < 10^4$:

$$Nu_D = 4.82 + 0.0185 (Re_D Pr)^{0.827}$$

- Liquid metals, Turbulent, fully developed, uniform surface temperature, $Pe_D > 10^2$:

$$Nu_D = 5.0 + 0.025 (Re_D Pr)^{0.8}$$

18.7 Exercises

1. A solar water heater is made of a parabolic mirror that concentrates a total heat flux of 2 kW s^{-2} on to a thin copper tube that carries the water. If the inlet water is at 20°C and at a flow rate of 0.02 kg s^{-1} and the outlet shall have 60°C , what should be the length of the tube? Assuming fully developed flow of water through the tube with $Nu = \frac{48}{11}$ applicable, estimate the surface temperature at the outlet. Properties of water are: $C_p = 4200 \text{ J kg}^{-1} \text{ K}^{-1}$, $k = 0.67 \text{ W m}^{-1} \text{ K}^{-1}$, $\mu = 0.35 \times 10^{-3} \text{ Pa s}$, $Pr = 2.2$.

18.8 Summary




Figure 18.1: 1D Profiles of thermal conduction problems

Chapter 19

Mass Transfer

19.1 Introduction

In this section, you will see that balance of mass taking individual species into consideration will lead to the continuity equation. Also, the meaning of velocity $\vec{u}$ used for the advective term in the earlier chapters in relation to the velocities of individual species will also be evident. Diffusional flux will be expressed using the difference in the velocity of a species compared to that of the center of mass.

In this chapter, the subscripts refer to the species and/or reactions. They should not be confused with subscript notation.

19.2 Organization of topics

Mass transfer topics fall into the following four major categories.

- **Solid state diffusion:** discussed mainly in the context of physical metallurgy.
- **Convective mass transfer:** when flux is more important to arrive at overall solute balances.
- **Reaction with a generation term:** when solute is generated or consumed at a location because of a reaction. The rate of formation of a certain product is of interest here. We can use balance of fluxes taking into account the fact that more than one species are involved in the transport.
- **Solute redistribution:** as it occurs during partitioning during a phase transformation. For example, during solidification. Solute element partitioning is important not only for segregation of solute elements but also to understand formation of porosity due to dissolved gases.

Unlike the parameters used for Momentum transfer (Velocity) and heat transfer (Temperature), the parameters used for mass transfer are varied in their physical meaning as well as in their units.

- Concentration (mass per unit volume): default variable for us

- Atom/Mole fraction or percentage or ppm: popular in physical metallurgy
- Weight fraction or percentage or ppm: a practicable quantity used in process metallurgy
- Partial pressure: useful unit when dealing with gases
- Fugacity
- Activity

In our discussion, unless otherwise specified, we deal with the concentration as our variable and convert the rest of the quantities to concentration when necessary.

In addition, we must also specify for which of the species are we writing down the balance equation. Meaning, instead of C as our variable, really we have C_i as our set of variables where i goes over the range of number of species participating in the mass transfer. Unless specified, we will be dealing with a situation where the balance is written down only for one species.

19.3 Chemical equilibrium

We first introduce the idea of chemical equilibrium here with inputs from Metallurgical thermodynamics. The role of chemical potential is to be clarified with respect to things that happen in metallurgical scenario such as carburization as well as precipitation. Evening out of solute concentrations is to be shown as a special case of ideal solutions.

The different variables that describe the content of solute are to be listed with their significance. The choice of solute concentration and conversions across are to be listed.

The subtle difference in chemical potential and diffusion potential and the difference between slope and intercept of G_m versus X_B plots to be explained. How these things are reconciled in binary and multi-component systems to be explained.

The need for definition of velocity in continuum and its reconciliation with species velocities is to be raised here.

Also we should introduce the concept of vapour pressure as function of temperature here.

19.4 Reaction Equilibrium

19.4.1 Objectives

1. To illustrate the equivalence of gibbs energy minimization method and entropy maximization method at constant temperature and pressure to arrive at the equilibrium condition.
2. To write down the reaction from the equilibrium condition
3. To determine the direction of a reaction if the equilibrium is disturbed

19.4.2 Example system

Consider an example reaction between species CO, O₂ and CO₂. The species are in an isolated container and the temperature of the system is T and the total pressure of the system is p_{tot} . Let the number of moles of each species be designated as follows: n_{CO_2} , n_{CO} and n_{O_2} for the species CO₂, CO and O₂, respectively. It is known that these species mix with each other - like ideal gases - and their activities can be given as follows.

$$a_{\text{CO}_2} = \frac{p_{\text{CO}_2}}{p_{\text{tot}}} \quad (19.1)$$

If $p_{\text{tot}} = 1 \text{ atm}$, then we can write $a_{\text{CO}_2} = p_{\text{CO}_2}$. Similarly for other two species.

The species form a solution in the gas phase and so one can write the Gibbs energy of the mixture using partial molar quantities as follows.

$$G = n_{\text{CO}_2} \bar{G}_{\text{CO}_2} + n_{\text{CO}} \bar{G}_{\text{CO}} + n_{\text{O}_2} \bar{G}_{\text{O}_2} \quad (19.2)$$

We can use the symbol μ_i instead of $\bar{G}_i$ for the partial molar Gibbs energy of species i . Note that for ideal solutions, partial molar Gibbs energy is same as molar Gibbs energy.

$$G = n_{\text{CO}_2} \mu_{\text{CO}_2} + n_{\text{CO}} \mu_{\text{CO}} + n_{\text{O}_2} \mu_{\text{O}_2} \quad (19.3)$$

Partial molar Gibbs energy of any species can be expressed with respect to a standard state as follows.

$$\mu_{\text{CO}_2} = \mu_{\text{CO}_2}^o + RT \ln a_{\text{CO}_2} \quad (19.4)$$

We can write the expressions for the other two species similarly.

$$\mu_{\text{CO}} = \mu_{\text{CO}}^o + RT \ln a_{\text{CO}} \quad (19.5)$$

$$\mu_{\text{O}_2} = \mu_{\text{O}_2}^o + RT \ln a_{\text{O}_2} \quad (19.6)$$

If we denote m_{O} as the total number of oxygen atoms divided by the Avogadro number, then we can write the following balance equations to keep the total number of atoms of any element to be conserved within the system.

$$m_{\text{O}} = 2n_{\text{O}_2} + n_{\text{CO}} + 2n_{\text{CO}_2} \quad (19.7)$$

$$m_C = n_{\text{CO}_2} + n_{\text{CO}} \quad (19.8)$$

During the reaction, the total number of atoms of any element does not change. Thus, the change in number of moles of any species is then related to that in others through the following relations.

$$dm_O = 0 \implies 2dn_{\text{O}_2} + dn_{\text{CO}} + 2dn_{\text{CO}_2} = 0 \quad (19.9)$$

$$dm_C = 0 \implies dn_{\text{CO}_2} + dn_{\text{CO}} = 0 \quad (19.10)$$

19.4.3 Gibbs energy minimization method

We can use the Lagrangian multiplier method to arrive at the condition of equilibrium between three species.

The problem statement will be as follows:

Minimize the function G given by

$$G = n_{\text{CO}_2} \mu_{\text{CO}_2} + n_{\text{CO}} \mu_{\text{CO}} + n_{\text{O}_2} \mu_{\text{O}_2} \quad (19.11)$$

subject to the following two constraints:

$$m_O = 2n_{\text{O}_2} + n_{\text{CO}} + 2n_{\text{CO}_2} \quad (19.12)$$

$$m_C = n_{\text{CO}_2} + n_{\text{CO}} \quad (19.13)$$

So we can construct a composite function F using two Lagrangian multipliers λ_O and λ_C as follows

$$\begin{aligned} F &= n_{\text{CO}_2} \mu_{\text{CO}_2} + n_{\text{CO}} \mu_{\text{CO}} + n_{\text{O}_2} \mu_{\text{O}_2} \\ &+ \lambda_O [m_O - (2n_{\text{O}_2} + n_{\text{CO}} + 2n_{\text{CO}_2})] \\ &+ \lambda_C [m_C - (n_{\text{CO}_2} + n_{\text{CO}})] \end{aligned} \quad (19.14)$$

Minimization of F (not strictly but conveniently) with respect to the five variables will be given as:

$$\begin{aligned} \frac{\partial F}{\partial n_{\text{CO}_2}} = 0 &\implies \mu_{\text{CO}_2} - 2\lambda_O - \lambda_C = 0 \\ \frac{\partial F}{\partial n_{\text{CO}}} = 0 &\implies \mu_{\text{CO}} - \lambda_O - \lambda_C = 0 \\ \frac{\partial F}{\partial n_{\text{O}_2}} = 0 &\implies \mu_{\text{O}_2} - 2\lambda_O = 0 \\ \frac{\partial F}{\partial \lambda_O} = 0 &\implies m_O = 2n_{\text{O}_2} + n_{\text{CO}} + 2n_{\text{CO}_2} \\ \frac{\partial F}{\partial \lambda_C} = 0 &\implies m_C = n_{\text{CO}_2} + n_{\text{CO}} \end{aligned} \quad (19.15)$$

We can combine the first three equations to eliminate λ_C and λ_O to get the condition for equilibrium as:

$$2\mu_{CO} + \mu_{O_2} = 2\mu_{CO_2} \quad (19.16)$$

Looking at the coefficients of the chemical potentials of each species, we could then write the stoichiometric equation as:

$$2CO + O_2 = 2CO_2 \quad (19.17)$$

If we denote Gibbs energy change per mole of oxygen for this reaction as ΔG_r then we could express it as:

$$\Delta G_r = 2\mu_{CO_2} - 2\mu_{CO} - \mu_{O_2} \quad (19.18)$$

The convention will then be: ΔG_r = Sum of chemical potentials on RHS multiplied with their stoichiometric coefficients **minus** Sum of chemical potentials on LHS multiplied with their stoichiometric coefficients.

The oxidation reactions are generally written with **one** mole of oxygen so that the interpretation of ΔG_r the way we write is *Gibbs energy change for the reaction per mole of oxygen*.

Expanding the chemical potentials using their activities, we could then write,

$$\Delta G_r = 2(\mu_{CO_2}^o + RT \ln a_{CO_2}) - 2(\mu_{CO}^o + RT \ln a_{CO}) - (\mu_{O_2}^o + RT \ln a_{O_2}) \quad (19.19)$$

$$\Delta G_r = \Delta G_r^o + RT \ln K \quad (19.20)$$

Where,

$$\Delta G_r^o = 2\mu_{CO_2}^o - 2\mu_{CO}^o - \mu_{O_2}^o \quad (19.21)$$

The reaction constant K is given by

$$K = \frac{a_{CO_2}^2}{a_{CO}^2 a_{O_2}} \quad (19.22)$$

Expressing activities in terms of partial pressures,

$$K = \frac{p_{CO_2}^2}{p_{CO}^2 p_{O_2}} \times p_{\text{tot}} \quad (19.23)$$

Only when the total pressure is 1 atm., we can write

$$K = \frac{p_{CO_2}^2}{p_{CO}^2 p_{O_2}} \quad (19.24)$$

Equilibrium requires that $\Delta G_r = 0$. We denote the value of reaction constant K at equilibrium as K_{eq} to differentiate the value of the reaction constant at equilibrium and for any other combination of partial pressures of the species. Thus, at equilibrium, we have,

$$\Delta G_r = 0 = \Delta G_r^o + RT \ln K_{\text{eq}} \implies \Delta G_r^o = -RT \ln K_{\text{eq}} \quad (19.25)$$

Substituting these back, we can write the Gibbs energy change per mole of oxygen for the reaction as

$$\Delta G_r = -RT \ln K_{\text{eq}} + RT \ln K = RT \ln \frac{K}{K_{\text{eq}}} \quad (19.26)$$

We now have the following three possibilities:

1. When the partial pressures of the species are such that $K = K_{\text{eq}}$ then $\Delta G_r = 0$ and the species are at equilibrium.
2. When the partial pressures of the species are such that $K > K_{\text{eq}}$ then $\Delta G_r > 0$. This means that the sum of Gibbs energy of the species on the right hand side of the reaction is **more** than that of the left hand side (per one mole of oxygen). Since the system should tend to lower its total Gibbs energy, the equilibrium should shift towards the left hand side. The product should then dissociate.
3. When the partial pressures of the species are such that $K < K_{\text{eq}}$ then $\Delta G_r < 0$. This means that the sum of Gibbs energy of the species on the right hand side of the reaction is **less** than that of the left hand side (per one mole of oxygen). Since the system should tend to lower its total Gibbs energy, the equilibrium should shift towards the right hand side. The product should then form.




Figure 19.1: Schematic showing changes in reaction constant

19.4.4 Entropy maximization method

Using the definition of chemical potential as a form of work done by the system due to change in composition, we can write the following.

$$dU = T dS - p dV + \sum_i \mu_i dn_i \quad (19.27)$$

Rearranging the terms, we can write the entropy change for the system as:

$$dS = \frac{dU}{T} + \frac{p dV}{T} - \frac{1}{T} \sum_i \mu_i dn_i \quad (19.28)$$

We consider an isolated system consisting of n_{CO_2} , n_{CO} and n_{O_2} moles of the species CO_2 , CO and O_2 , respectively.

The last term in the entropy expression is then elaborated as follows:

$$\sum_i \mu_i dn_i = \mu_{\text{CO}_2} dn_{\text{CO}_2} + \mu_{\text{CO}} dn_{\text{CO}} + \mu_{\text{O}_2} dn_{\text{O}_2} \quad (19.29)$$

From the conservation of number of atoms of each element, we write the change in number of moles of species related as follows:

$$2dn_{\text{O}_2} = -dn_{\text{CO}} - 2dn_{\text{CO}_2} \quad (19.30)$$

$$dn_{\text{CO}} = -dn_{\text{CO}_2} \quad (19.31)$$

We use these expressions to eliminate the variables dn_{CO} and dn_{O_2} from the above equation.

$$\sum_i \mu_i dn_i = \mu_{\text{CO}_2} dn_{\text{CO}_2} + \mu_{\text{CO}} (-dn_{\text{CO}_2}) + \frac{1}{2}\mu_{\text{O}_2} (-2dn_{\text{CO}_2} - dn_{\text{CO}}) \quad (19.32)$$

$$\sum_i \mu_i dn_i = \mu_{\text{CO}_2} dn_{\text{CO}_2} + \mu_{\text{CO}} (-dn_{\text{CO}_2}) + \frac{1}{2}\mu_{\text{O}_2} (-2dn_{\text{CO}_2} + dn_{\text{CO}_2}) \quad (19.33)$$

$$\sum_i \mu_i dn_i = \left(\mu_{\text{CO}_2} - \mu_{\text{CO}} - \frac{1}{2}\mu_{\text{O}_2} \right) dn_{\text{CO}_2} \quad (19.34)$$

$$\sum_i \mu_i dn_i = \frac{1}{2} (2\mu_{\text{CO}_2} - 2\mu_{\text{CO}} - \mu_{\text{O}_2}) dn_{\text{CO}_2} \quad (19.35)$$

Substituting this into the expression for entropy change,

$$dS = \frac{dU}{T} + \frac{p dV}{T} - \frac{1}{2T} (2\mu_{\text{CO}_2} - 2\mu_{\text{CO}} - \mu_{\text{O}_2}) dn_{\text{CO}_2} \quad (19.36)$$

For an isolated system, the change in internal energy and volume are zero. Thus, we can see that entropy maximization with respect to composition is possible when $\partial S / \partial n_{\text{CO}_2} = 0$. Thus, the equilibrium - when entropy is maximum - is when the following condition is satisfied.

$$2\mu_{\text{CO}_2} - 2\mu_{\text{CO}} - \mu_{\text{O}_2} = 0 \quad (19.37)$$

On the lines of earlier method, we define ΔG_r as follows:

$$\Delta G_r \equiv 2\mu_{\text{CO}_2} - 2\mu_{\text{CO}} - \mu_{\text{O}_2} \quad (19.38)$$

$$dS = \frac{-\Delta G_r}{2T} dn_{\text{CO}_2} \quad (19.39)$$

When $\Delta G_r < 0$, the reaction should proceed in the direction dictated by a spontaneous increase in entropy. This is possible only when dn_{CO_2} is positive. This implies that the number of moles of CO_2 must increase. Thus, the reaction proceeds towards RHS.

Similarly, when $\Delta G_r > 0$, the reaction should proceed in the direction dictated by a spontaneous increase in entropy. This is possible only when dn_{CO_2} is negative. This implies that the number of moles of CO_2 must decrease. Thus, the reaction proceeds towards LHS.

The chemical potentials for each phase can now be expanded as $\mu_i = \mu_i^o + RT \ln a_i$ to see the conclusions above extended to a variation in partial pressures of individual species.

19.4.5 Ellingham Diagram

If we would like to express the standard Gibbs energy for any reaction in terms of standard enthalpy and entropy of the reaction, we can say:

$$\Delta G^o(T) = \Delta H^o(T) - T\Delta S^o(T) \quad (19.40)$$

The variation of enthalpy with temperature at a given pressure is given by:

$$\Delta H^o(T) = \Delta H^o(T_o) + \int_{T_o}^T \Delta C_p^o(T) dT \quad (19.41)$$

Where, ΔC_p^o is the heat capacity of the components on RHS minus the heat capacity of the components on the LHS, with the coefficients given as per the stoichiometric equation.

Similarly, we can write the variation of entropy with temperature at a given pressure as:

$$\Delta S^o(T) = \Delta S^o(T_o) + \int_{T_o}^T \frac{\Delta C_p^o(T)}{T} dT \quad (19.42)$$

Compared to the heats of reactions (latent component, usually in hundreds of kilojoules), the heat exchanges for altering the temperatures of reactants or products (sensible component, usually in tens of kilojoules) are much smaller. Thus in both the above equations, the second term on RHS can be taken as negligible.

Thus, ΔG_r^o is expressed as simple linear relationship with temperature as $A + BT$. Here, $A \approx \Delta H^o(T_o) = \sum_{\text{RHS}} n_i H_i - \sum_{\text{LHS}} n_i H_i$. The constants n_i are taken from the stoichiometric reaction. Similarly, $-B \approx \Delta S^o(T_o) = \sum_{\text{RHS}} n_i S_i - \sum_{\text{LHS}} n_i S_i$

The sign of B is negative when the total entropy of the species on the RHS is more than that on the LHS. Remember that the molar entropy of a gaseous phase is always much higher than the corresponding condensed phases. So, we could say the following: If the reaction is written such that the number of moles of gaseous species on the LHS is more, then the constant B is positive. This is the case for most of the oxidation reactions for metals. However, the case of $2\text{C} + \text{O}_2 = 2\text{CO}_2$ will have negative value of B .

The plot of $\Delta G^o(T)$ as a function of T is known as Ellingham diagram.

19.4.6 References

1. Chapter 11 of *Thermodynamics in Materials Science* by Robert DeHoff, Second Edition, CRC Press (2006), ISBN: 9780849340659
2. Chapter 17 of *Materials Thermodynamics* by Y. Austin Chang and W. Alan Oates, Wiley (2010), ISBN: 9780470484142
3. Chapter 10 of *Materials Thermodynamics with emphasis on chemical approach* by Hae-Geon Lee, World Scientific Press (2012), ISBN: 9789814368056

19.5 Species balance equation

The derivation that follows is based on what is found in the first few pages of the book by de Groot and Mazur [de Groot and Mazur, 1984].


The symbols used are as follows:

- ρ_k is the density of species k in kg m^{-3} . This is the default unit of concentration unless otherwise specified in most of the subjects.
- $\vec{u}_k$ is the velocity of the species k .
- N is the total number of species in the domain considered.
- R is the total number of reactions that take place in the domain.
- In j^{th} reaction, the rate of production of species k is given by $\kappa_{jk}Q_j$.
- Q_j is the chemical reaction rate of j^{th} reaction in $\text{kg m}^{-3} \text{s}^{-1}$.
- The coefficients κ_{kj} are taken as positive for the product species and negative for the reacting species in the j^{th} reaction.

The total density ρ at any location is given by:

$$\rho = \sum_{k=1}^N \rho_k$$

As an example, take the reduction of wustite by hydrogen to produce iron. Let this be the j^{th} reaction.



Using the molar weights in g mol^{-1} and a subscript k to indicate the number of the species - total N being 4 here.

$$MW_1 \equiv MW_{\text{FeO}} = 71.84$$


$$MW_2 \equiv MW_{\text{H}_2} = 2$$

$$MW_3 \equiv MW_{\text{Fe}} = 55.84$$

$$MW_4 \equiv MW_{\text{H}_2\text{O}} = 18$$

$$\kappa_{j1} = -\frac{MW_1}{MW_1 + MW_2}$$

We can write the equation with the coefficients as:



So that, $\kappa_{j1} = -0.973$, $\kappa_{j2} = -0.027$, $\kappa_{j3} = 0.756$ and $\kappa_{j4} = 0.244$.

Conservation of mass requires the following:

$$\kappa_{j1} + \kappa_{j2} + \kappa_{j3} + \kappa_{j4} = 0$$

We notice that in the j^{th} reaction the following equation implies conservation of mass.

$$\sum_{k=1}^N \kappa_{jk} = 0$$

Let s_{kj} be the rate of production of k^{th} species due to j^{th} reaction. The total production rate of k^{th} species is given by:

$$q_k = \sum_{j=1}^N s_{kj}$$

We can note that for each reaction j , $s_{jk} = \kappa_{jk} Q_j$. Thus,

$$q_k = \sum_{j=1}^N \kappa_{jk} Q_j$$

Let $\vec{j}_k$ be the flux of species k across the faces of the control volume.

Consider a control volume with dV as the volume and dS as the surface area in the domain fixed in space. $\hat{n}$ is the normal to each surface element. The control volume contains all the N number of species with their respective concentrations given by ρ_k . The change in the concentration of any k^{th} species is either due to an inward flux of that species from the surface of the control volume or due to its generation from any of the R reactions that are possible in the domain. Thus, we can write the balance of mass for every k^{th} species in the domain as follows:

$$\int_V \frac{\partial \rho_k}{\partial t} dV = - \int_S \vec{j}_k \cdot \hat{n} dS + \int_V q_k dV$$

We can express the flux of a species using the velocity of that species as

$$\vec{j}_k = \rho_k \vec{u}_k$$

Substituting,

$$\int_V \frac{\partial \rho_k}{\partial t} dV = - \int_S \rho_k \vec{u}_k \cdot \hat{n} dS + \int_V \sum_{j=1}^R \kappa_{jk} Q_j dV$$

Using the Gauss theorem to convert the surface integral to volume integral, we obtain

$$\int_V \frac{\partial \rho_k}{\partial t} dV = - \int_V \vec{\nabla} \cdot (\rho_k \vec{u}_k) dV + \int_V \sum_{j=1}^R \kappa_{jk} Q_j dV$$

Since this is valid for every control volume at every location in the domain, we can write:

$$\boxed{\frac{\partial \rho_k}{\partial t} = -\vec{\nabla} \cdot (\rho_k \vec{u}_k) + \sum_{j=1}^R \kappa_{jk} Q_j} \quad (19.43)$$

19.5.1 Continuity Equation

We can now retrieve continuity equation that expresses the balance of mass from the above species balance equation.

The above equation is also true for every species. So we can sum it up over all the N species.

$$\sum_{k=1}^N \frac{\partial \rho_k}{\partial t} = - \sum_{k=1}^N \vec{\nabla} \cdot (\rho_k \vec{u}_k) + \sum_{k=1}^N \sum_{j=1}^R \kappa_{jk} Q_j$$

Re-arranging the last term by taking Q_j common and using the definition of total density:

$$\frac{\partial \rho}{\partial t} = - \sum_{k=1}^N \vec{\nabla} \cdot (\rho_k \vec{u}_k) + \sum_{j=1}^R Q_j \sum_{k=1}^N \kappa_{jk}$$

Recognizing that the sum of κ_{jk} over any j^{th} reaction is zero:

$$\frac{\partial \rho}{\partial t} = - \sum_{k=1}^N \vec{\nabla} \cdot (\rho_k \vec{u}_k)$$

We now define the *barycentric velocity* or the *velocity of the centre of mass* as follows:

$$\vec{u} = \frac{\sum_{k=1}^N \rho_k \vec{u}_k}{\sum_{k=1}^N \rho_k} = \frac{1}{\rho} \sum_{k=1}^N \rho_k \vec{u}_k$$

Substituting this definition, the balance of mass comes to a form that is familiar from the continuity equation:

$$\frac{\partial \rho}{\partial t} = - \vec{\nabla} \cdot (\rho \vec{u})$$

Using the definition of substantial / material derivative,

$$\frac{\partial \rho}{\partial t} + (\vec{u} \cdot \vec{\nabla}) \rho = \frac{D}{Dt} \rho = - \rho (\vec{\nabla} \cdot \vec{u})$$

19.5.2 Diffusional flux

We define *Diffusional flux* of a species as due to difference in the velocity of the species from the velocity of the centre of mass.

We revisit equation 19.43 by substituting *diffusional flux* of the k^{th} species as defined below:

$$\boxed{\vec{J}_k = \rho_k (\vec{u}_k - \vec{u}) = \rho_k \vec{u}_k^*} \quad (19.44)$$

Here, $\vec{u}_k^*$ is the velocity of the species **relative** to the centre of mass.

$$\frac{D \rho_k}{Dt} = - \rho_k \vec{\nabla} \cdot \vec{u} - \vec{\nabla} \cdot \vec{J}_k + \sum_{j=1}^M \kappa_{jk} Q_j$$

Defining mass fraction $c_k = \rho_k/\rho$, we can write the following balance of mass for each of the k^{th} species:

$$\boxed{\rho \frac{Dc_k}{Dt} = -\vec{\nabla} \cdot \vec{J}_k + \sum_{j=1}^M \kappa_{jk} Q_j} \quad (19.45)$$

Summing up equation 19.44 over all species, we can conclude that:

$$\sum_{k=1}^N \vec{J}_k = 0$$

In other words, of the N equations for the fluxes, only $N - 1$ are independent.

19.5.3 Ficks Law

We now seek a linear constitutive relation to determine $\vec{J}$. Refer to the section 43.14 of Feynman Lecture Series for more discussion at this point. Flux of a species is usually expressed as a product of composition of that species and the velocity of that species. Diffusional flux, however, is expressed as a product of composition and the velocity of the species relative to the center of mass.

$$\vec{J}_k = (\vec{u}_k - \vec{u})\rho_k = \vec{u}_k^* \rho_k$$

If velocity of a species relative to the centre of mass is the effect, then the cause is a gradient in chemical potential - meaning that atoms move to reduce the free energy of the system. The quantity that connects a cause and effect is a material property and one can use relevant theories to deduce the minimum number of entities necessary to represent that property.

$$\vec{u}^* = -M\vec{\nabla}\mu_k$$

In solid state diffusion, typically one considers that the center of mass is not moving ie., $\vec{u} = 0$ or $\vec{u}_k = \vec{u}_k^*$. Thus the typical form in which the above equation is often seen is:

$$\vec{u}_k = -M\vec{\nabla}\mu_k$$

M is called the **mobility tensor**. Using Onsager's reciprocal relations [Onsager, 1931a, Onsager, 1931b], one can say that M is a symemtric tensor. It is isotropic for isotropic media. For our discussion, we are usually limited to liquids, gases, polycrystalline materials that can be approximated to isotropic media.

$$\vec{J}_k = -M\rho_k\vec{\nabla}\mu_k$$

Using an ideal solution approximation,

$$\mu = \mu_0 + RT \ln X\gamma = \mu_0 + RT (\ln X + \ln \gamma)$$

Where, X is mole fraction and is proportional to C and γ is the activity of the species in the solution. We now look at the form of diffusion equation in one dimension rectangular coordinate system for simplicity.

$$-M\rho_k \frac{\partial \mu}{\partial x} = -M\rho_k \frac{\partial \mu}{\partial \rho_k} \frac{\partial \rho_k}{\partial x} = -M \frac{\partial \mu}{\partial \ln \rho_k} \frac{\partial \rho_k}{\partial x}$$

Since composition can be related to atom fraction X_k as

$$\rho_k \propto \frac{X_k M_w}{V_m}$$

The variation of log of the parameters will be equal as the rest of the parameters that are not function of location will be constants.

$$\frac{\partial \mu}{\partial \ln \rho_k} = \frac{\partial \mu}{\partial \ln X_k}$$

$$M \frac{\partial \mu}{\partial \ln X_k} = MRT \left(1 + \frac{\partial \ln \gamma}{\partial \ln X_k} \right) = D_k$$

Where, D_k is the diffusivity of the solute k in the solution. Thus, the Fick's first law of solute diffusion goes as

$$\boxed{\vec{J}_k = -D_k \frac{\partial \rho_k}{\partial x}} \quad (19.46)$$

19.5.4 Diffusion equation

Substituting the same in the balance equation,

$$\frac{\partial \rho_A}{\partial t} + (\vec{u} \cdot \vec{\nabla}) \rho_A = \vec{\nabla} \cdot \left(D \frac{\partial \rho_A}{\partial x} \right) + \sum_{j=1}^r \kappa_{Aj} Q_j \quad (19.47)$$

Assuming the D is constant over the range of variation of ρ_A , absence of any generation term and that the domain is solid and the species A is dilute enough that ρ_A is very small corresponding to ρ , we get the Fick's second law of solute diffusion

$$\boxed{\frac{\partial \rho_A}{\partial t} = D \nabla^2 \rho_A} \quad (19.48)$$

This is called as the Diffusion equation or Fick's second law of diffusion.

19.5.5 Diffusivity

Unlike the relevant properties for momentum and heat transfer, the kind of diffusivity to be used depends on the situation of mass transfer problem. Following are some examples.

- **Diffusivity in gas:** Using kinetic theory of gases,

$$D_{AA} = \frac{1}{3}\lambda u$$

Where, λ is mean free path and u is the average velocity of the atoms in the gas.

$$\lambda = \frac{k_B T}{\sqrt{2}\pi\sigma_A^2\rho}$$

$$u = \sqrt{\frac{8k_B NT}{\pi M_A}}$$

Thus, the diffusivity in gas goes as $T^{3/2}$.

- **Diffusivity in gas entrapped in a pore:** In case the gas is entrapped in a pore, instead of the mean free path from the kinetic theory of gases, we are supposed to use the pore diameter. This means the temperature dependence of Diffusivity goes as $T^{1/2}$.
- **Liquid Diffusivity:** Using the Einstein equation,

$$k_B T = 6\pi r_A \mu_B D_{AB}$$

- **Solid Diffusivity:** Arrhenius variation

$$D = D_0 e^{\frac{-Q}{RT}}$$

The activation energy for Diffusion in solid Q depends on the way diffusion takes place and following are some situations where they are different:

- Diffusion aided by non-equilibrium defect concentration eg., due to quenched-in vacancies
- Pipe diffusion aided by dislocations
- Grain boundary aided diffusion
- Surface diffusion
- Stress induced diffusion
- Bulk diffusion

Chapter 20

Solute diffusion in solids

20.1 Solid state diffusion

We consider a few simple cases of solid state diffusion.

20.1.1 Steady state diffusion profiles

Consider the phase diagram to arrive at the interface compositions during diffusion couple experiments. The case of intermediate metastable phase with and without the possibility of it's nucleation.

20.1.2 Fixed boundary compositions

In the domain, composition is fixed with the following boundary conditions:

$$C = C_s \text{ at } x = 0 \text{ and } t > 0$$

$$C = C_\infty \text{ at } x = \infty$$

$$C = C_s \text{ at } t = \infty \text{ and } x > 0$$

The governing equation is

$$\frac{\partial C}{\partial t} = D \frac{\partial^2 C}{\partial x^2}$$

By using a variable substitution $\eta = \frac{x}{2\sqrt{Dt}}$, one can integrate the equation subject to the above boundary conditions as:

$$\frac{C - C_\infty}{C_s - C_\infty} = 1 - \operatorname{erf} \frac{x}{2\sqrt{Dt}} = \operatorname{erfc} \frac{x}{2\sqrt{Dt}}$$

20.1.3 Fixed total solute content

In the domain, the total solute is fixed with the following boundary condition:

$$\int_{-\infty}^{\infty} C dx = M$$




Figure 20.1: Fixed Compositions

The governing equation to be solved is same as Fick's second law of solute diffusion. In order to figure out the form of C that will satisfy the governing equation as well as the boundary condition, we use the property of $\text{erf}(x)$.

$$\text{erf}(\infty) = 1 = \frac{2}{\sqrt{\pi}} \int_0^{\infty} \exp\left(-\frac{x^2}{4Dt}\right) \frac{1}{2\sqrt{Dt}} dx$$

Using algebraic manipulations,

$$\int_{-\infty}^{\infty} \frac{M}{2\sqrt{\pi Dt}} \exp\left(-\frac{x^2}{4Dt}\right) dx = M = \int_{-\infty}^{\infty} C dx$$

One can verify that the following form of solution for C will not only satisfy the boundary condition as given above but also the governing equation.

$$C = \frac{M}{2\sqrt{\pi Dt}} \exp\left(-\frac{x^2}{4Dt}\right)$$

20.1.4 Fourier series solution

In this section we describe the Fourier series solution of diffusion equation and its application in Homogenization heat treatment process.

20.1.5 Diffusion during growth of precipitate

Zener's solution, Role of curvature on the interface composition, ...

20.1.6 Solute profile during directional solidification

During directional solidification, one can consider solute balance at the solid-liquid interface as follows. The solute dumped into the liquid by the growing solid due to solute partition effect is taken away into the bulk liquid by diffusion. The liquid composition is then given as a function of distance from the solid-liquid interface as follows:

$$\frac{C_l}{C_0} = 1 + \frac{1-k}{k} \exp\left(-\frac{Vx}{D}\right) \quad (20.1)$$

Here, k is the partition coefficient, V is the velocity of the solid-liquid interface, D is the diffusivity of the solute in the liquid and C_0 is the initial / steady-state solute concentration.

20.1.7 Solute profile during eutectic solidification

Here we talk about Jackson-Hunt's solution

20.2 Diffusion with two species considered

20.2.1 Interdiffusion coefficient

Here we derive the expression for interdiffusion coefficient $\tilde{D}$ for the case of constant density.

20.2.2 Stagnant layer approach




Figure 20.2: Stagnant layer approach

Consider a situation such as in the figure 20.2. At the bottom layer, species A is being generated and we are interested in the net flux of A and its distribution in the layer above. It can be taken that in the stagnant layer, there is no net flux of B. The net flux equations are:

$$j_A = -D_{AB} \frac{\partial \rho_A}{\partial x} + u \rho_A$$

$$j_B = -D_{AB} \frac{\partial \rho_B}{\partial x} + u \rho_B = 0$$

or

$$u = \frac{D_{AB}}{\rho_B} \frac{\partial \rho_B}{\partial x}$$

If only species A and B are present and the total density ρ is constant,

$$\rho_A + \rho_B = \rho$$

such that

$$\frac{\partial \rho_B}{\partial x} = -\frac{\partial \rho_A}{\partial x}$$

Substituting in the equation of net flux of A,

$$j_A = -D_{AB} \frac{\partial \rho_A}{\partial x} - \rho_A \frac{D_{AB}}{(\rho - \rho_A)} \frac{\partial \rho_A}{\partial x}$$

$$j_A = -D_{AB} \frac{\rho}{(\rho - \rho_A)} \frac{\partial \rho_A}{\partial x}$$

At steady state,

$$\vec{\nabla} \cdot \vec{j}_A = 0$$

or

$$\frac{\partial}{\partial x} \left[\frac{\rho}{(\rho - \rho_A)} \frac{\partial \rho_A}{\partial x} \right] = 0$$

Integrating twice with the boundary conditions:

- Considering that species B is being flushed at the top, concentration of species A at $x = L$, the height of the layer can be taken as ρ_{AL} , usually zero.
- At $x = 0$, $\rho_A = \rho_{A0}$

we obtain the solution for distribution of ρ_A in the stagnant layer as:

$$\boxed{\ln \frac{\rho - \rho_A}{\rho - \rho_{A0}} = \frac{x}{L} \ln \frac{\rho - \rho_{AL}}{\rho - \rho_{A0}}}$$

Using the above expression,

$$\frac{\partial \rho_A}{\partial x} = -\frac{(\rho - \rho_A)}{L} \ln \frac{\rho - \rho_{AL}}{\rho - \rho_{A0}}$$

Substituting the same to obtain j_A ,

$$\boxed{j_A = \frac{D_{AB}\rho}{L} \ln \frac{\rho - \rho_{AL}}{\rho - \rho_{A0}}}$$

In the limit of $\rho_{A0} = 0$ and the value of ρ_{AL} being small, the above equation reduces to $j_A = -D_{AB} \frac{\rho_{AL}}{L}$, which is the same as Fick's first law valid for the case of no advection. Thus, the stagnant layer approach with very dilute species can be approximated to the regime where Fick's law is applicable even though the other species is also taking part in the diffusion process.

It is easy to see that instead of concentrations, if one were to use partial pressures of the respective species, one would have the following equations valid:

$$p_A + p_B = p$$

$$p_A = RTC_A$$

$$\ln \frac{p - p_A}{p - p_{A0}} = \frac{x}{L} \ln \frac{p - p_{AL}}{p - p_{A0}}$$

$$j_A = \frac{pD_{AB}}{RTL} \ln \frac{p - p_{AL}}{p - p_{A0}}$$

j_A when expressed in rate of loss of mass can be accurately measured and thus provides an excellent means to obtain D_{AB} by weight loss method using a setup similar to that of figure 20.2.

20.3 Boundary conditions

In most of the cases, the diffusion within the domain can be simplified to be one dimensional and be solved either using the solid state diffusion equation or stagnant layer approach. However, the conditions at the boundary of the domain are required in all cases. Following are few ways to obtain those boundary conditions.

20.3.1 Solubility limits

In situations such as carburising / decarburising and nitriding, the maximum concentration of the corresponding species in the domain at the boundary can be obtained by looking up the phase diagram. The solid solution limits can be used as boundary conditions.

20.3.2 Reaction mass transfer

In a reaction, we are interested in the rate of formation of a particular product, usually a condensed one. It can usually be obtained by knowing the flux of that species by balancing with the flux of a diffusing species and applying appropriate boundary conditions. The compositions of the participating species are related by the equilibrium constant of the reaction. Consider the following example.



$$K = \frac{[B]^n}{[A]} = \frac{p_B^n}{p_A}$$

$$p_A + p_B = p$$

One can solve for p_B by solving the above two equations.

One has to know the value of K at a given temperature and should watch out the units of K to know the convention for the units of $[A]$ and $[B]$.

Once the value of K is known, it is possible to obtain the flux of one of the species, say A, using either the Fick's law or the stagnant layer approach depending on how dilute the system is. The fluxes of the diffusing species A and B are related to as:

$$j_B = nj_A = nj_C$$

If B is a dilute species in a stagnant layer of A of height L and a total pressure p , one can use the following expression for j_B

$$j_B = \frac{pD_{AB}}{RTL} \ln \frac{p - p_{BL}}{p - p_{B0}}$$

The quantity j_C can then be converted to appropriate rate of formation as mass or volume or moles or thickness as desired using the properties of C .

20.3.3 Sieverts Law

Most of the time, one is interested in determining flux of a species as a function of the concentration of that species.

Sievert's Law For absorption of gases in metals, one can use the following expression to obtain the concentration.

$$\frac{1}{2}H_2 \rightarrow [H]$$

Equilibrium constant is given by

$$K = \frac{[H]}{\sqrt{p_{H_2}}}$$

If the concentration of hydrogen is given in ppm and the partial pressure in atm, then K would be in $\text{ppm}/\sqrt{\text{atm}}$. One must watch the units of K to know the convention followed. This is because pressure could be in units such as bar (atm), torr (mmHg), mbar or Pa.

Conversion of partial pressure of a gas into concentration is done by approximating the gas to be an ideal gas.

$$p_A V = n_A RT$$

$$C_A = \frac{n_A}{V} = \frac{p_A}{RT}$$

Here, C_A is given in mol/vol and may need to be converted to mass/vol using molar weight and density.

Chapter 21

Convective mass transfer

21.1 Mass transfer with advection

In a situation where the domain consists of species A and B and we are interested in the flux of species A, there are following possible situations.

- Species B is not present / species A is very dilute in B and thus B can be said to not take part in the diffusion process. In this situation, the flux is given by Fick's first law.
- Species B is present and takes part in the diffusion process. Additionally, an assumption can be made that net flux of B is zero and species B moves only to replace species A. This approach is called **stagnant layer** approach.
- Species B is present and the domain is not stagnant. In such a situation, the influence of bulk velocity on the flux of both species be determined separately.

The first case is simple as discussed in the previous section. For the second case, we can proceed by assuming that the flux is one dimensional and the velocity of the species A is v which is same (but opposite in direction) for species B.

The total flux that takes advection into account can be given as:

$$\boxed{\vec{j}_A = -D_{AB}\vec{\nabla}\rho_A + \vec{u}\rho_A}$$

Where, $\vec{j}_A$ is the **net** flux of species A taking the advection into account.

21.2 Mass transfer with advection

In a situation where the domain consists of species A and B and we are interested in the flux of species A, there are following possible situations.

- Species B is not present / species A is very dilute in B and thus B can be said to not take part in the diffusion process. In this situation, the flux is given by Fick's first law.
- Species B is present and takes part in the diffusion process. Additionally, an assumption can be made that net flux of B is zero and species B moves only to replace species A. This approach is called **stagnant layer** approach.

- Species B is present and the domain is not stagnant. In such a situation, the influence of bulk velocity on the flux of both species be determined separately.

The first case is simple as discussed in the previous section. For the second case, we can proceed by assuming that the flux is one dimensional and the velocity of the species A is v which is same (but opposite in direction) for species B.

The total flux that takes advection into account can be given as:

$$\vec{j}_A = -D_{AB}\vec{\nabla}\rho_A + \vec{u}\rho_A$$

Where, $\vec{j}_A$ is the **net** flux of species A taking the advection into account.

21.2.1 Mass transfer coefficient

In many situations, it may be favourable to define a mass transfer coefficient akin to heat transfer coefficient such that one can experimentally or otherwise determine it. The definition is as given below:

$$j_A = k_A (C_A - C_{A0})$$

If the units of C_A , as used commonly, are mass/vol then the units of k_A are same as those of velocity. Once the mass transfer coefficient is known, flux can be determined using the above equation. In situations such as solid state diffusion, k_A can be determined by evaluating the slope of the species distribution (say, error function) itself.

Eg., for transient diffusion in solid / quiescent liquid whose bulk composition is C_{A0} and is in contact with atmosphere with zero concentration of species A as illustrated in the figure, we can write the following flux balance.




Figure 21.1: Surface Renewal Approach

Writing the composition distribution for species A in the domain,

$$\frac{C_A}{C_{A0}} = \text{erf}\left(\frac{x}{2\sqrt{D_{AB}t}}\right)$$

Evaluating the flux at the interface at time t ,

$$k_{A,t}(C_{A0} - 0) = j_A = \left| -D_{AB} \frac{\partial C_A}{\partial x} \right|_{x \rightarrow 0} = D_{AB} C_{A0} \frac{2}{\sqrt{\pi}} e^{-\left(\frac{x}{2\sqrt{D_{AB}t}}\right)^2} \frac{1}{\sqrt{D_{AB}t}} \Big|_{x \rightarrow 0}$$

$$k_{A,t} = 2\sqrt{\frac{D_{AB}}{\pi t}}$$

This is the instantaneous mass transfer coefficient. The time averaged coefficient will be obtained by averaging the coefficient over the time interval $t = 0$ to $t = t$.

$$k_A = \sqrt{\frac{D_{AB}}{\pi t}}$$

In case of a steadily falling (along z axis) film of liquid, the quantity $\frac{z}{u_{z,\max}}$ plays the role of time. The z averaged mass transfer coefficient will then be given as

$$k_A = \sqrt{\frac{D_{AB} u_{z,\max}}{\pi z}}$$

21.2.2 Film Theory




Figure 21.2: Film Theory

Mass transfer coefficient h_m can be estimated as follows.

$$h_m (C_A^s - C_A^\infty) = |j_A|$$

$$j_A = \left| -D \frac{\partial C_A}{\partial x} \right|_{x \rightarrow 0} = \frac{D (C_A^s - C_A^\infty)}{\delta}$$

$$h_m = \frac{D}{\delta} \tag{21.1}$$

21.2.3 Penetration Theory




Figure 21.3: Schematic of penetration theory. Here, $t_2 > t_1$.

Mass transfer coefficient h_m can be estimated as follows.

$$\begin{aligned}
 h_m (C_A^s - C_A^\infty) &= |j_A| \\
 j_A &= \left| -D \frac{\partial C_A}{\partial x} \right|_{x \rightarrow 0} \\
 \frac{C_A - C_A^\infty}{(C_A^s - C_A^\infty)} &= \operatorname{erf} \left(\frac{x}{2\sqrt{Dt}} \right) \\
 j_A &= D (C_A^s - C_A^\infty) \frac{2}{\sqrt{\pi}} \frac{1}{2\sqrt{Dt}} \\
 \boxed{h_m} &= \sqrt{\frac{D}{\pi t}}
 \end{aligned} \tag{21.2}$$

21.2.4 Surface Renewal Theory

Let τ be the time scale of the process that brings a pocket of fresh liquid to the surface (agitation frequency or residence time of a bubble etc). The probability of a liquid packet uniformly mixed with a concentration of species A of C_A^∞ is given as $1/\tau e^{-t/\tau}$

We can see that the following identity holds for the probability distribution.

$$\int_0^\infty \frac{1}{\tau} e^{-t/\tau} dt = 1$$

The instantaneous heat transfer coefficient for diffusional heat flux at time t is given by the following.




Figure 21.4: Schematic of surface renewal theory.

$$h_m(t) = \sqrt{\frac{D}{\pi t}}$$

The averaged mass transfer coefficient taking the probability of the liquid packet being available at the surface into account,

$$\bar{h}_m = \int_0^\infty \sqrt{\frac{D}{\pi t}} \frac{1}{\tau} e^{-\frac{t}{\tau}} dt = \sqrt{\frac{D}{\tau}}$$

The mass transfer coefficient can be given as follows.

$$\boxed{\bar{h}_m = \sqrt{\frac{D}{\tau}}} \quad (21.3)$$

21.2.5 Sherwood number

Like the heat transfer coefficient is obtained in non-dimensionalized form by encapsulating it with the thermal conductivity and characteristic length scale as Nusselt number, mass transfer coefficient is also obtained in non-dimensionalized form by encapsulating it with the solute diffusivity and characteristic length scale as Sherwood number.

$$Sh = \frac{k_A L_c}{D_{AB}}$$

Sherwood number is determined experimentally as a function of Reynold's number and Schmidt number to obtain correlations for advection aided mass transfer.

$$Sc = \frac{\nu}{D_{AB}}$$

Examples:

Mass transfer from a sphere:

$$Sh_D = 2 + CRe_D^m Sc^{\frac{1}{3}}$$

The constants C and m depend on the range of Re and Sc .

Mass transfer from a plate of length L (for $Re < 2 \times 10^5$):


$$Sh_L = 0.664Re_L^{0.5} Sc^{\frac{1}{3}}$$

21.3 Exercises

1. Suppose that a hollow cylinder of nickel is used to measure the diffusion coefficient of hydrogen through this material. The cylinder has an outer diameter of 2 mm and an inner diameter of 1 mm. A CH_4/H_2 mixture is passed through the base of the cylinder which fixes the hydrogen concentration on the inner wall as 0.01 wt%. Hydrogen diffusing through the cylinder is evacuated so that the hydrogen concentration on the outer wall is effectively zero. If hydrogen is collected under steady-state conditions at a rate of $1.1 \times 10^{-11} \text{ mol s}^{-1}$ from the cylinder, 2 cm long, held at 200°C , what is the diffusion coefficient? Take the density of nickel as 8790 kg m^{-3} . **Ans:** $1.38 \times 10^{-11} \text{ m}^2 \text{ s}^{-1}$
2. A dopant B is sent into a block of metal A of square cross-section. The flux of B is given as a constant. Making suitable assumptions, determine the concentration of B as function of distance from the surface of the bar if it is held at a high temperature for a long duration. What would be a good measure of depth of dopant penetration?
3. Nickel alloys are used in gas turbine engines at temperatures in excess of 1000°C . If pure nickel is exposed to air at 1000°C it will develop a coherent oxide scale. Determine how thick the oxide scale will be after 1, 10, 100 hours. Diffusivity is $2.5 \times 10^{-15} \text{ m}^2 \text{ s}^{-1}$.
Tips: Assume film theory is applicable. It is known that NiO becomes metal deficient to become $Ni_{1-x}O$ as the oxygen potential is increased. In equilibrium with air at 1000°C , $x = 3 \times 10^{-3}$. **Ans:** 232 nm, 735 nm and 2.32 μm . **Check if more data is needed**
4. Develop an expression for the drop in pressure of a steel cylinder that contains hydrogen gas.
5. For an iron melt at 1600°C , determine the maximum rate of iron evaporation and the corresponding thickness of the iron vapour layer. Assume an argon / oxygen atmosphere with a total pressure of 1 bar. Partial pressure of iron is $7.5 \times 10^{-5} \text{ bar}$, diffusivity of iron in argon is $5.6 \times 10^{-4} \text{ m}^2 \text{ s}^{-1}$. **Ans:** $0.1 \text{ mol m}^{-2} \text{ s}^{-1}$, 2.7 μm .
6. A thin sheet of iron at 800°C is subjected to different gaseous atmospheres on both of its surfaces such that the composition of one face is 4 at% carbon and the other is at 0 at% carbon. At steady state, make a plot of the composition profile in the sample indicating clearly compositions and respective distances. The thickness is 1 mm and density changes during experiment may be neglected. At 800°C it is known that the diffusion coefficient


of carbon in iron is given by $10^{-6} \text{ cm}^2 \text{ s}^{-1}$ in ferrite and $10^{-8} \text{ cm}^2 \text{ s}^{-1}$ in austenite. **Ans:** α is 0.845 mm thick, interface is with 0.096 and 2.238 at% carbon, respectively.

7. A thin layer of gold is plated on to the end of a nickel bar. The bar is annealed at 900°C for 10 h. At this temperature, the interdiffusion coefficient of gold in nickel is $1 \times 10^{-11} \text{ cm}^2 \text{ s}^{-1}$. After this treatment, the concentration of gold at a distance of 0.05 cm from the end is 0.1 at fraction of gold. At what distance is the atom fraction of gold equal to 0.01? **Ans:** 5.0033 cm
8. An electronic circuit plate is being protected from corrosion due to atmospheric moisture by a two layer coating of polymers. Assume a small gap between the two layers of polymers. If the two layers have different reaction constants for equilibrium with water vapour and different diffusivities, model how to determine the flux of moisture towards the circuit plate. Assume that the RH in the atmosphere is known. Draw schematically the variation of concentration of water vapour in the polymer layers as function of distance.
9. Silicon can be grown by CVD of silane. Given a system in which silicon grows from the bottom of an inert crucible with the top flushed by pure silane at 1 atm, predict the growth rate of silicon. Assume that the gas/silicon interface equilibrium is established according to the following reaction.



The equilibrium constant is given by $K = 10^{-4} \text{ atm}$. The diffusion coefficient in the gas at the reaction temperature 700 K can be taken as $1 \text{ cm}^2 \text{ s}^{-1}$. **Ans:** $108 \mu\text{m s}^{-1}$

10. When ceramic oxides are used to contain molten metals, they can dissolve and add undesirable impurities to the melt. This is especially true when melting is done under vacuum. For examples, magnesium oxide decomposes slowly according to the following equation.



The square brackets indicate dissolution in the melt. The equilibrium constant for this reaction is $K = C_{\text{Mg}}C_{\text{O}} = 10^{-6}$ where C_{Mg} and C_{O} are concentrations in mol m^{-3} of melt of Mg and O, respectively. For flow parallel to a 3 m long plate of MgO, calculate the average mass transfer coefficient for Mg dissolving in the melt. Assume that $C_{\text{Mg}} = C_{\text{O}}$. For $x < 0$, $C_{\text{Mg}} = 0$ in the melt and $V = 3 \text{ m s}^{-1}$. What is the average flux of MgO dissolving in the melt? **Ans:** $3.15 \times 10^{-4} \text{ m s}^{-1}$, $3.15 \times 10^{-7} \text{ mol m}^{-2} \text{ s}^{-1}$.

Density of the melt is 8000 kg m^{-3} , thermal conductivity is $50 \text{ W m}^{-1} \text{ K}^{-1}$, heat capacity is $840 \text{ J kg}^{-1} \text{ K}^{-1}$, viscosity is $1.24 \times 10^{-3} \text{ N s m}^{-2}$ and diffusivities of both the species are $5 \times 10^{-9} \text{ m}^2 \text{ s}^{-1}$. For turbulent conditions, take

$$Sh_L = 0.037 Re_L^{0.8} Sc^{1/3}$$

.

Chapter 22

Similarity across transport phenomena

22.1 Learning objectives

At the end of this lesson, a student should be able to

1. look up correlations of h-factors to determine unknown parameters of one transport phenomena from known parameters of another transport phenomena

22.2 Reynold's analogy

22.3 Chilton-Colburn analogy

In case the transport properties are known for one quantity (say, heat) and we are interested in the transport of another quantity (say, solute), we can make use of the similarity expressions thanks to the fact that under laminar conditions and when fully developed profiles are present, similarity relations are valid.

The problem is to connect friction factor, heat transfer coefficient and mass transfer coefficient at an interface.

If the velocity, temperature and solute profiles are fully developed, then the following three expressions will all be the same functions (eg., parabolas for a tube):

$$\frac{v}{v_{\infty}} = \frac{T - T_s}{T_{\infty} - T_s} = \frac{C_A - C_{A0}}{C_{A,\infty} - C_{A0}}$$

Equating the slopes at the interface since the profiles are the same:

$$\left. \frac{\partial}{\partial x} \frac{v}{v_{\infty}} \right|_{x \rightarrow 0} = \left. \frac{\partial}{\partial x} \frac{T - T_s}{T_{\infty} - T_s} \right|_{x \rightarrow 0} = \left. \frac{\partial}{\partial x} \frac{C_A - C_{A0}}{C_{A,\infty} - C_{A0}} \right|_{x \rightarrow 0}$$

Take the case of a hypothetical fluid that has $Pr = Sc = 1$ ie.,

$$\frac{\mu C_p}{k} = \frac{\mu}{\rho D_{AB}} = 1$$

or

$$\mu = \frac{k}{C_p} = \rho D_{AB}$$

Multiply these quantities with the respective slopes of the profiles as:

$$\begin{aligned} \mu \frac{\partial}{\partial x} \frac{v}{v_\infty} \Big|_{x \rightarrow 0} &= \frac{k}{C_p} \frac{\partial}{\partial x} \frac{T - T_s}{T_\infty - T_s} \Big|_{x \rightarrow 0} = \rho D_{AB} \frac{\partial}{\partial x} \frac{C_A - C_{A0}}{C_{A,\infty} - C_{A0}} \Big|_{x \rightarrow 0} \\ \frac{\tau}{v_\infty} &= \frac{q}{C_p(T_\infty - T_s)} = \frac{\rho j_A}{(C_{A,\infty} - C_{A0})} \end{aligned}$$

Dividing each quantity with ρv_∞ ,

$$\frac{1}{2} \frac{\tau}{\rho v_\infty^2} = \frac{q}{\rho C_p (T_\infty - T_s) v_\infty} = \frac{j_A}{(C_{A,\infty} - C_{A0}) v_\infty}$$

Recognize the following quantities:

Skin friction coefficient:

$$\frac{\tau}{\frac{1}{2} \rho v_\infty^2} = f$$

Heat transfer coefficient:

$$\frac{q}{(T_\infty - T_s)} = h$$

Mass transfer coefficient:

$$\frac{j_A}{(C_{A,\infty} - C_{A0})} = k_A$$

$$\frac{f}{2} = \frac{h}{\rho C_p v_\infty} = \frac{k_A}{v_\infty}$$

We define Stanton number as:

$$St = \frac{h}{\rho C_p v_\infty}$$

The following analogy is called as Reynold's analogy:

$$\boxed{\frac{f}{2} = St = \frac{k_A}{v_\infty}}$$

Chilton-Colburn realized that the above expression can be made to be applicable even when Pr and Sc are not unity but for a range of $0.6 < Pr < 100$ and $0.6 < Sc < 2500$ provided a correction factor of $Pr^{\frac{2}{3}}$ for heat transfer and $Sc^{\frac{2}{3}}$ for mass transfer are used:

$$\boxed{\frac{f}{2} = St Pr^{\frac{2}{3}} = \frac{k_A}{v_\infty} Sc^{\frac{2}{3}}}$$

Each of the above three quantities are called as **j-factors**.

$$j_H = St Pr^{\frac{2}{3}} = \frac{h}{\rho C_p v_\infty} Pr^{\frac{2}{3}}$$

$$j_D = \frac{k_A}{v_\infty} Sc^{\frac{2}{3}}$$

In situations where the analogy is applicable, one can obtain the mass transfer coefficient from the heat transfer coefficient or the skin friction factor by using the above analogy and the appropriate property values.

Evaporative heat flux

Dry air at 40 °C flows on surface of water. Due to evaporative loss, the surface temperature of water dips. Estimate the drop in temperature of the surface of water.

Properties:

Density of air at 40 °C can be taken as $\rho = 1.133 \text{ kg m}^{-3}$

Molar weight of water vapor: $M = 0.018 \text{ kg mol}^{-1}$

Heat of evaporation : $\Delta H = 3.338 \times 10^5 \text{ J kg}^{-1}$

Heat capacity of air: $C_p = 1005 \text{ J kg}^{-1} \text{ K}^{-1}$

Vapor pressure of air in Pascals: $\ln p^0 = \frac{-6679}{T} - 4.65 \ln T + 56.97$

Lewis number of air under given conditions: $Le = 1.1$

Solution:

$$St = \frac{h}{\rho C_p u_\infty}$$

Taking a ratio of second and third terms of the Chilton-Colburn analogy, we get

$$\frac{h}{k_m} = \rho C_p \left(\frac{Sc}{Pr} \right)^{2/3} = \rho C_p Le^{2/3}$$

We can assume that water vapour behaves like ideal gas here. Assuming the equation of state for ideal gas, the concentration of water vapour in moles per unit volume is given by

$$\dot{n} = \frac{n}{V} = \frac{p}{RT}$$

Evaporative loss of moles of water = difference in concentration of water vapour on surface of water and in the air that is flowing. Since the air is given as dry, we can take the evaporative loss in moles per unit area per unit time using mass transfer coefficient k_m as follows.

$$\dot{N} = k_m [\dot{n}|_{T=T_s} - \dot{n}|_{T=T_\infty}]$$

At the surface of water,

$$\dot{n}|_{T=T_s} = \frac{p^0}{RT} \Big|_{T=T_s} = \frac{1}{RT_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right)$$

Far away from the surface of water, the air is dry.

$$\dot{n}|_{T=T_\infty} = \frac{0}{RT}\bigg|_{T=T_\infty}$$

Combining the equations above,

$$\dot{N} = k_m \left[\frac{1}{RT_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right) - \frac{1}{RT_\infty} 0 \right]$$

Heat loss because of this mass flux is given by

$$M \Delta H \dot{N}$$

This heat loss is same as given by heat transfer coefficient namely

$$h (T_\infty - T_s)$$

Taking these two as equivalent,

$$M \Delta H k_m \left[\frac{1}{RT_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right) \right] = h (T_\infty - T_s)$$

$$M \Delta H \left(\frac{k_m}{h} \right) \frac{1}{RT_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right) = (313 - T_s)$$

$$T_s = 313 - M \Delta H \frac{1}{\rho C_p L e^{2/3}} \frac{1}{RT_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right)$$

$$T_s = 313 - \frac{0.595}{T_s} \exp \left(\frac{-6679}{T_s} - 4.65 \ln T_s + 56.97 \right)$$

Using initial guess as $T_s = 300$, we can apply single point iteration scheme to find out the answer as 304.1 K.

22.4 Summary

Expressions that convey similarity relations of relevance to Metallurgical and Materials Engineering.

22.5 Exercises

Mapping of Questions to Learning Objectives

Question : Learning Objectives : Exams : References

Q 2.2.1 : LO ?? : Exams ?? : References ??
Q 2.2.2 : LO ?? : Exams ?? : References ??
Q 2.2.3 : LO ?? : Exams ?? : References ??
Q 2.2.4 : LO ?? : Exams ?? : References ??
Q 2.2.5 : LO 2.2 : Exams ?? : References ??
Q 2.3.6 : LO ?? : Exams ?? : References ??
Q 2.4.7 : LO ?? : Exams ?? : References ??
Q 2.4.8 : LO ?? : Exams ?? : References ??
Q 2.5.9 : LO ?? : Exams ?? : References ??
Q 2.5.10 : LO ?? : Exams ?? : References ??
Q 2.5.11 : LO ?? : Exams ?? : References ??
Q 3.1.12 : LO ?? : Exams ?? : References ??
Q 3.2.13 : LO ?? : Exams ?? : References ??
Q 3.2.14 : LO ?? : Exams ?? : References ??
Q 3.2.15 : LO ?? : Exams ?? : References ??
Q 3.2.16 : LO ?? : Exams ?? : References ??
Q 3.2.17 : LO ?? : Exams ?? : References ??
Q 3.2.18 : LO ?? : Exams ?? : References ??
Q 3.2.19 : LO ?? : Exams ?? : References ??
Q 3.2.20 : LO ?? : Exams ?? : References ??
Q 3.2.21 : LO ?? : Exams ?? : References ??
Q 3.2.22 : LO ?? : Exams ?? : References ??
Q 3.2.23 : LO ?? : Exams ?? : References ??
Q 3.2.24 : LO ?? : Exams ?? : References ??
Q 3.2.25 : LO ?? : Exams ?? : References ??
Q 3.2.26 : LO ?? : Exams ?? : References ??
Q 3.2.27 : LO ?? : Exams ?? : References ??
Q 3.2.28 : LO ?? : Exams ?? : References ??
Q 3.2.29 : LO ?? : Exams ?? : References ??
Q 3.2.30 : LO ?? : Exams ?? : References ??
Q 3.2.31 : LO ?? : Exams ?? : References ??
Q 3.2.32 : LO ?? : Exams ?? : References ??
Q 4.3.33 : LO ?? : Exams ?? : References ??
Q 4.3.34 : LO ?? : Exams ?? : References ??
Q 5.3.35 : LO ?? : Exams ?? : References ??
Q 5.3.36 : LO ?? : Exams ?? : References ??
Q 5.3.37 : LO ?? : Exams ?? : References ??

Q 5.3.38 : LO ?? : Exams ?? : References ??
Q 5.3.39 : LO ?? : Exams ?? : References ??
Q 5.3.40 : LO ?? : Exams ?? : References ??
Q 5.3.41 : LO ?? : Exams ?? : References ??
Q 5.3.42 : LO ?? : Exams ?? : References ??
Q 5.3.43 : LO ?? : Exams ?? : References ??
Q 5.3.44 : LO ?? : Exams ?? : References ??
Q 5.3.45 : LO ?? : Exams ?? : References ??
Q 5.3.46 : LO ?? : Exams ?? : References ??
Q 5.3.47 : LO ?? : Exams ?? : References ??
Q 5.3.48 : LO ?? : Exams ?? : References ??
Q 7.12.49 : LO ?? : Exams ?? : References ??
Q 7.12.50 : LO ?? : Exams ?? : References ??
Q 7.12.51 : LO ?? : Exams ?? : References ??
Q 7.12.52 : LO ?? : Exams ?? : References ??
Q 11.5.53 : LO ?? : Exams ?? : References ??
Q 11.5.54 : LO ?? : Exams ?? : References ??
Q 11.5.55 : LO ?? : Exams ?? : References ??
Q 12.1.56 : LO ?? : Exams ?? : References ??
Q 12.1.57 : LO ?? : Exams ?? : References ??
Q 12.1.58 : LO ?? : Exams ?? : References ??
Q 12.1.59 : LO ?? : Exams ?? : References ??
Q 12.1.60 : LO ?? : Exams ?? : References ??
Q 12.1.61 : LO ?? : Exams ?? : References ??
Q 12.1.62 : LO ?? : Exams ?? : References ??
Q 12.1.63 : LO ?? : Exams ?? : References ??
Q 12.1.64 : LO ?? : Exams ?? : References ??
Q 13.7.65 : LO ?? : Exams ?? : References ??
Q 13.7.66 : LO ?? : Exams ?? : References ??
Q 13.7.67 : LO ?? : Exams ?? : References ??
Q 13.7.68 : LO ?? : Exams ?? : References ??
Q 14.9.69 : LO ?? : Exams ?? : References ??
Q 14.9.70 : LO ?? : Exams ?? : References ??
Q 14.9.71 : LO ?? : Exams ?? : References ??
Q 14.9.72 : LO ?? : Exams ?? : References ??
Q 14.9.73 : LO ?? : Exams ?? : References ??
Q 14.9.74 : LO ?? : Exams ?? : References ??
Q 14.9.75 : LO ?? : Exams ?? : References ??
Q 14.9.76 : LO ?? : Exams ?? : References ??
Q 14.9.77 : LO ?? : Exams ?? : References ??
Q 14.9.78 : LO ?? : Exams ?? : References ??
Q 14.9.79 : LO ?? : Exams ?? : References ??
Q 14.9.80 : LO ?? : Exams ?? : References ??

Appendix A

Derivations

A.1 The quotient rule

Adapted from section 2.62 of [Aris, 1962].

Let b_i be **any** vector and a_{ij} be a matrix of nine numbers ($i, j = 1, 2, 3$). If a relation could be found such that $a_{ij}b_i = c_j$ is vector, then a_{ij} is a tensor of order 2.

Consider a co-ordinate transformation with the tranformation matrix T_{ij} . Since b and c are vectors,

$$b_p^* = T_{pi}b_i \quad \text{or} \quad b_i = T_{pi}b_p^* \quad (\text{A.1})$$

$$c_q^* = T_{qj}c_j$$

In the new co-ordinate system:

$$a_{pq}^*b_p^* = c_q^* = T_{qj}c_j = T_{qj}a_{ij}b_i = T_{qj}a_{ij}T_{pi}b_p^*$$

$$(a_{pq}^* - T_{pi}T_{qj}a_{ij})b_p^* = 0$$

Since b_p^* is only the arbitrary vector b_i in new co-ordinate system which is independent of a_{ij} the only way the above equation can hold is if

$$a_{pq}^* = T_{pi}T_{qj}a_{ij}$$

which is the definition for the entity a_{ij} to be a tensor of order two.

A.2 Symmetric tensors are diagonalisable

Adapted from section 2.5 of [Aris, 1962].

If a_{ij} is a tensor and b_i is an arbitrary vector then by quotient rule, $c_j = a_{ij}b_i$ is a vector. For some b_i , the vector c_i could be in the same orientation such that if λ is the ratio of their magnitudes, $a_{ij}b_i = \lambda b_j = \lambda \delta_{ij}b_i$.

$$(a_{ij} - \lambda \delta_{ij}) b_i = 0$$

This is a set of three unknowns (a_1 , a_2 and a_3) and for a solution to exist, λ must satisfy the following equation:

$$\det(a_{ij} - \lambda \delta_{ij}) = 0$$

$$\lambda^3 - X\lambda^2 + Y\lambda - Z = 0$$

$$X = a_{ii} = \text{Trace}(a_{ij})$$

$$Y = a_{22}a_{33} - a_{23}a_{32} + a_{11}a_{33} - a_{13}a_{31} + a_{22}a_{11} - a_{12}a_{21}$$

$$Z = \det(a_{ij})$$

X , Y and Z are three invariants of a_{ij} under rotation of co-ordinate system.

The above is called the characteristic equation of the tensor a_{ij} and the three values of λ its characteristic values / latent roots / eigen values.

For the three eigen values $\lambda_{(p)}$, $p = 1 : 3$, the corresponding characteristic vectors ($b_{i(p)}$), $p = 1 : 3$ be denoted as T_{j1} , T_{j2} and T_{j3} .

$$T = \begin{pmatrix} b_{1(1)} & b_{1(2)} & b_{1(3)} \\ b_{2(1)} & b_{2(2)} & b_{2(3)} \\ b_{3(1)} & b_{3(2)} & b_{3(3)} \end{pmatrix} = \begin{pmatrix} T_{11} & T_{12} & T_{13} \\ T_{21} & T_{22} & T_{23} \\ T_{31} & T_{32} & T_{33} \end{pmatrix} \quad (\text{A.2})$$

$$\begin{aligned} a_{ij}T_{j1} &= \lambda_1 T_{i1} \\ a_{ij}T_{j2} &= \lambda_2 T_{i2} \end{aligned} \quad (\text{A.3})$$

Multiply the first equation with T_{i2} and the second equation with T_{i1} .

$$\begin{aligned} a_{ij}T_{j1}T_{i2} &= \lambda_1 T_{i1}T_{i2} \\ a_{ij}T_{j2}T_{i1} &= \lambda_2 T_{i2}T_{i1} \end{aligned} \quad (\text{A.4})$$

Transpose the second equation (swap the indices i and j in second equation):

$$\begin{aligned} a_{ij}T_{j1}T_{i2} &= \lambda_1 T_{i1}T_{i2} \\ a_{ji}T_{i2}T_{j1} &= \lambda_2 T_{j2}T_{j1} \end{aligned} \quad (\text{A.5})$$

If a_{ij} is **symmetric**, then

$$\begin{aligned} a_{ij}T_{j1}T_{i2} &= \lambda_1 T_{i1}T_{i2} \\ a_{ij}T_{i2}T_{j1} &= \lambda_2 T_{j2}T_{j1} \end{aligned} \tag{A.6}$$

ie.,

$$a_{ij}T_{j1}T_{i2} = \lambda_1 T_{i1}T_{i2} = \lambda_2 T_{j2}T_{j1}$$

Since λ_1 and λ_2 are distinct, the above equation can be true only if

$$T_{i1}T_{i2} = \delta_{ij} \tag{A.7}$$

If we choose a co-ordinate transformation with the transformation matrix to contain the elements of T_{ij} made out of the three eigen vectors,

$$a_{pq}^* = T_{ip}T_{jq}a_{ij} = \lambda_p T_{ip}T_{iq} = \lambda_p \delta_{pq}$$

ie., a_{pq} is diagonal.

A.3 Levi-Civita tensor is isotropic

Adapted from section 2.7 of [Aris, 1962].

Since ϵ_{ijk} is a tensor of order 3, for an arbitrary co-ordinate transformation T_{ij} ,

$$T_{ip}T_{jq}T_{kr}\epsilon_{ijk} = \begin{vmatrix} T_{1p} & T_{1q} & T_{1r} \\ T_{2p} & T_{2q} & T_{2r} \\ T_{3p} & T_{3q} & T_{3r} \end{vmatrix} \quad (\text{A.8})$$

In the above determinant, if $p = q$ or $p = r$ or $q = r$, two columns being same will make the R.H.S. go to 0. If p, q and r are cyclic (e.g., 1, 2, 3) then the R.H.S. is the determinant of the transformation matrix itself which is 1. If p, q and r are anti-cyclic (e.g., 1, 3, 2), then the R.H.S. is the determinant of the transformation matrix (with two rows interchanged) which is -1.

These are the values defined for ϵ_{pqr} . Hence the R.H.S. can be equated to ϵ_{pqr}^* . Thus,

$$\epsilon_{pqr}^* = T_{ip}T_{jq}T_{kr}\epsilon_{ijk}$$

Since the above result is applicable for **any** T_{ij} , ϵ_{ijk} is isotropic.

A.4 General form of isotropic tensor of order four

Adapted from section 2.7 of [Aris, 1962].

An isotropic tensor a_{ijkl} of order 4 should be invariant under **any** co-ordinate transformation T_{ij} .

$$a_{pqrs} = T_{ip}T_{jq}T_{kr}T_{ls}a_{ijkl}$$

We categorise the 81 components of $a_{ijkl} : i, j, k, l = 1, 2, 3$ in to classes to figure out the non-zero (independent) components.

Class	component	remark
I	T_{1111}	All suffixes are same (nnnn)
II	T_{1112}	Three suffixes are same (nnnm)
III(i)	T_{1122}	Two suffixes are same (nnmm)
III(ii)	T_{1221}	Two suffixes are same (nmmn)
III(iii)	T_{1212}	Two suffixes are same (nmnm)
IV	T_{1123}	Only two suffixes are same (mmno)

Since class II doesnot include the elements of class I, introduce a tensor X_{ijkl} defined as below:

$$\begin{aligned} &\text{if } i = j = k = l \quad X_{ijkl} = 1 \\ &\text{else} \quad X_{ijkl} = 0 \end{aligned} \tag{A.9}$$

We now choose co-ordinate rotation operations so that T_{ij} can take such values that will make a conclusion about the relation between components in each of the above mentioned classes is clear.

Operation	Description	form of T_{ij}
A	Rotation about [111] axis by 120°	$T_{12} = T_{31} = T_{23} = 1$
B	Rotation about [001] axis by 90°	$T_{12} = -T_{21} = T_{33} = 1$
C	Rotation to inverse the direction of [111]	$T_{13} = -T_{22} = T_{31} = -1$

Class	conclusion	operation
I	$T_{1111} = T_{2222}$ $T_{1111} = T_{2222}$ $T_{1111} = T_{3333}$ all equal X_{ijkl}	A B C Overall conclusion Representation
II	$T_{1112} = T_{2223}$ $T_{1112} = -T_{2221}$ $T_{1112} = T_{3332}$ $T_{2223} = T_{2221}$ all zero	A B C C Overall conclusion
III(i)	$T_{1122} = T_{2233}$ $T_{1122} = T_{2211}$ $T_{1122} = T_{3322}$ all equal $\delta_{ij}\delta_{kl} - X_{ijkl}$	A B C Overall conclusion Representation
III(ii)	$T_{1221} = T_{2332}$ $T_{1221} = T_{2112}$ $T_{1221} = T_{3223}$ all equal $\delta_{il}\delta_{jk} - X_{iljk}$	A B C Overall conclusion Representation
III(iii)	$T_{1212} = T_{2323}$ $T_{1212} = T_{2112}$ $T_{1212} = T_{3232}$ all equal $\delta_{ik}\delta_{jl} - X_{ikjl}$	A B C Overall conclusion Representation
IV	$T_{1123} = T_{2231}$ $T_{1123} = -T_{2213}$ $T_{1123} = T_{3321}$ $T_{2231} = T_{2213}$ all zero	A B C C Overall conclusion

Since there is no obvious relation between the components of classes I, III(i), III(ii) and III(iii), we can represent a_{ijkl} by a linear combination of each class:

$$a_{ijkl} = \mu_1(\delta_{ij}\delta_{kl} - X_{ijkl}) + \mu_2(\delta_{ik}\delta_{jl} - X_{ikjl}) + \mu_3(\delta_{il}\delta_{jk} - X_{iljk}) + \mu_4 X_{ijkl}$$

or

$$a_{ijkl} = \mu_1\delta_{ij}\delta_{kl} + \mu_2\delta_{ik}\delta_{jl} + \mu_3\delta_{il}\delta_{jk} + (\mu_4 - \mu_1 - \mu_2 - \mu_3)X_{ijkl}$$

Choose an operation D : arbitrary rotation by some angle. Given the form of X_{ijkl} , the elements will not remain the same under such a transformation. Hence the last term in the above equation drops off giving the most general form of a fourth order **isotropic** tensor as:

$$a_{ijkl} = \mu_1\delta_{ij}\delta_{kl} + \mu_2\delta_{ik}\delta_{jl} + \mu_3\delta_{il}\delta_{jk}$$

A.5 Simplification of tensor properties for crystals

Lars Onsager has proved ([Onsager, 1931a],[Onsager, 1931b]) using *microscopic reversibility* that for crystals with symmetries of order 3,4,6 etc., the thermal conductivity tensor is symmetric.

$$k_{ij} = \begin{pmatrix} k_{11} & k_{12} & k_{13} \\ k_{12} & k_{22} & k_{23} \\ k_{13} & k_{23} & k_{33} \end{pmatrix} \quad (\text{A.10})$$

For cubic crystals, the form of the tensors simplifies even further. Take co-ordinate system rotations about $\hat{x}_3$ by 90° for which the transformation matrix is:

$$T = \begin{pmatrix} 0 & 1 & 0 \\ -1 & 0 & 0 \\ 0 & 0 & 1 \end{pmatrix} \quad (\text{A.11})$$

By definition, if T is the transformation matrix of a co-ordinate axes rotation,

$$k_{ij}^* = T_{pi} T_{qj} k_{pq}$$

Since the tensor in discussion is a property that should not change upon co-ordinate rotations that leave the crystal identical,

$$k^* = k$$

Take k_{11} and expand the above definition of tensor:

$$k_{11} = T_{i1} T_{j2} k_{ij} = T_{21} T_{21} k_{22} = k_{22}$$

or

$$k_{11} = k_{22}$$

Similarly,

$$k_{21} = T_{i2} T_{j1} k_{ij} = T_{12} T_{21} k_{12} = -k_{12} = -k_{21}$$

or

$$k_{21} = k_{12} = 0$$

Similarly rotating the co-ordinate system about the other two axes will show that all off diagonal terms of k_{ij} vanish and all diagonal terms are same.

$$k_{ij} = \begin{pmatrix} k_{11} & 0 & 0 \\ 0 & k_{11} & 0 \\ 0 & 0 & k_{11} \end{pmatrix} = k \delta_{ij} \quad (\text{A.12})$$

Thus, only one value of k is needed to completely specify the second order symmetric tensor property such as thermal conductivity of a cubic crystal.

A.6 Change of variable with multiple integrals

This section is adapted from section 3.16 of [Aris, 1962]. In cartesian co-ordinates the element of volume dV is the volume of rectangular parallelepiped of sides dx_1 , dx_2 and dx_3 :

$$dV = dx_1 dx_2 dx_3$$

It is sometimes convenient to describe position by some other co-ordinates, say, ξ_1 , ξ_2 and ξ_3 which are fixed to the control volume as it is moving along with the fluid. These coordinates are called as *convected* coordinates. These coordinates are such that the initial volume of the fluid element is given by

$$dV_0 = d\xi_1 d\xi_2 d\xi_3$$

The change of co-ordinate system must be given by fixing a point x such that

$$x_i = x_i(\xi_1, \xi_2, \xi_3)$$

Small differences in the new co-ordinate system are given by

$$dx_i = \frac{\partial x_i}{\partial \xi_j} d\xi_j$$

If $dx^{(j)}$ are three vectors with components $(\frac{\partial x_i}{\partial \xi_j} d\xi_j)$ for $j = 1, 2, 3$ then the volume of the element enclosed by these vectors is given by:

$$dV = dx^{(1)} \cdot (dx^{(2)} \times dx^{(3)})$$

Using ϵ_{ijk} to write the short form of determinant (triple product),

$$dV = \epsilon_{ijk} \frac{\partial x_i}{\partial \xi_1} d\xi_1 \frac{\partial x_j}{\partial \xi_2} d\xi_2 \frac{\partial x_k}{\partial \xi_3} d\xi_3$$

$$dV = J d\xi_1 d\xi_2 d\xi_3 = J dV_0$$

where J is the Jacobian of the transformation of variables.

$$J = \frac{\partial(x_1, x_2, x_3)}{\partial(\xi_1, \xi_2, \xi_3)} = \epsilon_{ijk} \frac{\partial x_i}{\partial \xi_1} \frac{\partial x_j}{\partial \xi_2} \frac{\partial x_k}{\partial \xi_3}$$

In determinant form, it is

$$J = \begin{vmatrix} \frac{\partial x_1}{\partial \xi_1} & \frac{\partial x_1}{\partial \xi_2} & \frac{\partial x_1}{\partial \xi_3} \\ \frac{\partial x_2}{\partial \xi_1} & \frac{\partial x_2}{\partial \xi_2} & \frac{\partial x_2}{\partial \xi_3} \\ \frac{\partial x_3}{\partial \xi_1} & \frac{\partial x_3}{\partial \xi_2} & \frac{\partial x_3}{\partial \xi_3} \end{vmatrix} \quad (\text{A.13})$$

Evidently, when two of the rows are same, the determinant is zero.

A.7 Dilation

This section is adapted from section 4.21 of [Aris, 1962]. Consider the following process to arrive at differentiation noting that (ξ_1, ξ_2, ξ_3) refers to *convected* coordinates:

$$\frac{d}{dt} \left(\frac{\partial x_i}{\partial \xi_j} \right) = \frac{\partial}{\partial \xi_j} \left(\frac{dx_i}{dt} \right) = \frac{\partial u_i}{\partial \xi_j}$$

Since u_i is a function of x_1, x_2 and x_3 ,

$$\frac{\partial u_i}{\partial \xi_j} = \frac{\partial u_i}{\partial x_1} \frac{\partial x_1}{\partial \xi_j} + \frac{\partial u_i}{\partial x_2} \frac{\partial x_2}{\partial \xi_j} + \frac{\partial u_i}{\partial x_3} \frac{\partial x_3}{\partial \xi_j} = \frac{\partial u_i}{\partial x_l} \frac{\partial x_l}{\partial \xi_j}$$

The rate of dilation as we follow the motion is given by the material derivative $\frac{DJ}{Dt}$.

Write the Jacobian using subscript notation:

$$J = \epsilon_{ijk} \frac{\partial x_i}{\partial \xi_1} \frac{\partial x_j}{\partial \xi_2} \frac{\partial x_k}{\partial \xi_3}$$

Differentiate by parts:

$$\begin{aligned} \frac{DJ}{Dt} &= \epsilon_{ijk} \left[\left(\frac{\partial u_i}{\partial \xi_1} \right) \frac{\partial x_j}{\partial \xi_2} \frac{\partial x_k}{\partial \xi_3} + \frac{\partial x_i}{\partial \xi_1} \left(\frac{\partial u_j}{\partial \xi_2} \right) \frac{\partial x_k}{\partial \xi_3} + \frac{\partial x_i}{\partial \xi_1} \frac{\partial x_j}{\partial \xi_2} \left(\frac{\partial u_k}{\partial \xi_3} \right) \right] \\ \frac{DJ}{Dt} &= \epsilon_{ijk} \left[\left(\frac{\partial u_i}{\partial x_l} \frac{\partial x_l}{\partial \xi_1} \right) \frac{\partial x_j}{\partial \xi_2} \frac{\partial x_k}{\partial \xi_3} + \frac{\partial x_i}{\partial \xi_1} \left(\frac{\partial u_j}{\partial x_l} \frac{\partial x_l}{\partial \xi_2} \right) \frac{\partial x_k}{\partial \xi_3} + \frac{\partial x_i}{\partial \xi_1} \frac{\partial x_j}{\partial \xi_2} \left(\frac{\partial u_k}{\partial x_l} \frac{\partial x_l}{\partial \xi_3} \right) \right] \end{aligned}$$

Each of the terms in the above equation is expressible as a determinant shown in the previous section. The dummy index l can take values from 1 to 3. The first term is non zero only when $l = i$ and the second when $l = j$ and the third when $l = k$ as the determinant goes to zero when two of its rows are same. Hence,

$$\frac{DJ}{Dt} = \epsilon_{ijk} \left[\frac{\partial u_i}{\partial x_i} + \frac{\partial u_j}{\partial x_j} + \frac{\partial u_k}{\partial x_k} \right] \left(\frac{\partial x_i}{\partial \xi_1} \frac{\partial x_j}{\partial \xi_2} \frac{\partial x_k}{\partial \xi_3} \right)$$

$$\frac{DJ}{Dt} = J [\nabla_i u_i]$$

Divergence of a velocity field $\nabla_i u_i$ can now be interpreted as the rate of dilation or rate of change of elemental volume following the flow path. Since **incompressible** fluids are defined as those with no dilatation during flow, $\nabla_i u_i = 0$ or $\vec{\nabla} \cdot \vec{u} = 0$ is the condition for incompressible fluid flow.

A.8 Reynold's transport theorem

Adapted from section 4.22 of [Aris, 1962].

Let $f(\hat{x}, t)$ be any function and $V(t)$ be a closed volume moving with the fluid ie., consisting of the same fluid particles.

$$F(t) = \int_{V(t)} f(\hat{x}, t) dV$$

is a function of t that can be calculated. We are interested in the material derivative $\frac{DF}{Dt}$. Since the integral is varying over $V(t)$, differentiation cannot be taken through the integral sign. If the differentiation is with respect to a volume in the material co-ordinate system (ξ_1, ξ_2, ξ_3) , it would be possible to interchange differentiation and integration since $\frac{D}{Dt}$ is differentiation with respect to time keeping ξ constant.

The transformation $\hat{x} = x(\xi, t)$ with $V = JdV_0$ allows us to this, for $V(t)$ has been defined as a moving material volume and so came from some fixed V_0 at time $t = 0$.

$$\frac{D}{Dt} \int_{V(t)} f(x, t) dV = \frac{D}{Dt} \int_{V_0} f(x(\xi, t), t) J dV_0$$

Since the integral is over the same volume V_0 , we can take the differentiation operator inside the integral.

$$\begin{aligned} \frac{D}{Dt} \int_V f(x, t) dV &= \int_{V_0} \left(\frac{Df}{Dt} J + f \frac{DJ}{Dt} \right) dV_0 \\ &= \int_{V_0} \left(\frac{Df}{Dt} + f(\nabla \cdot \vec{u}) \right) J dV_0 \\ &= \int_V \left(\frac{Df}{Dt} + f(\nabla \cdot \vec{u}) \right) dV \end{aligned} \tag{A.14}$$

Knowing that the expression for material derivative operator is:

$$\frac{D}{Dt} \equiv \frac{\partial}{\partial t} + (\vec{u} \cdot \nabla)$$

$$\frac{D}{Dt} \int_{V(t)} f(x, t) dV = \int_V \left(\frac{\partial f}{\partial t} + \nabla \cdot (f \vec{u}) \right) dV$$

Apply Green's theorem to the second term, with $S(t)$ as the surface of the element following the fluid flow and $\hat{n}$ as the unit normal to $S(t)$:

$$\boxed{\frac{D}{Dt} \int_{V(t)} f(x, t) dV = \int_{V(t)} \frac{\partial f}{\partial t} dV + \int_{S(t)} f \vec{u} \cdot \hat{n} dS}$$

Rate of change of the integral of any function f within a moving element is the sum of integral of rate of change at a location and the net flow of f over the surface enclosing the element.

A.9 RTT and Continuity Equation

Using $f = \rho$ in the Reynold's Transport Theorem given in section A.8, one recovers continuity equation.

Using $f = \rho G$ in RTT given in section A.8 where G is any dynamical property per unit mass (such as $G = u_i$, momentum per unit mass) one can bring the material derivative inside the integration.

$$\frac{D}{Dt} \int_V \rho G dV = \int_V \frac{\partial \rho G}{\partial t} dV + \int_S \rho G \vec{u} \cdot \hat{n} dS$$

Using Gauss theorem to convert a surface integral to volume integral,

$$\frac{D}{Dt} \int_V \rho G dV = \int_V \left(G \frac{\partial \rho}{\partial t} + \rho \frac{\partial G}{\partial t} \right) dV + \int_V \vec{\nabla} \cdot (\rho u_i G) dV$$

Keeping ρu_i together and expanding the integrand of the second integral,

$$\frac{D}{Dt} \int_V \rho G dV = \int_V \left[G \frac{\partial \rho}{\partial t} + \rho \frac{\partial G}{\partial t} \right] dV + \int_V \left[G \vec{\nabla} \cdot (\rho u_i) + (\rho u_i) \cdot \vec{\nabla} G \right] dV$$

Regrouping,

$$\frac{D}{Dt} \int_V \rho G dV = \int_V G \left[\frac{\partial \rho}{\partial t} + \vec{\nabla} \cdot (\rho u_i) \right] dV + \int_V \rho \left[\frac{\partial G}{\partial t} + (u_i \cdot \vec{\nabla}) G \right] dV$$

Recognising that the term in square brackets in the first integral is zero because of continuity equation and the integrand of the second integral could be simplified using the material derivative,

$$\boxed{\frac{D}{Dt} \int_V \rho G dV = \int_V \rho \frac{DG}{Dt} dV}$$

A.10 Cauchy's stress principle

Adapted from section 5.11 of [Aris, 1962].

Let $\hat{n}$ be the unit outward normal at a point of the surface S and $\sigma(\hat{n})$ the force per unit area exerted there by the material outside S . Then Cauchy's principle asserts that $\sigma(\hat{n})$ is a function of the position x , the time t and the orientation n of the surface element. Thus the total internal force exerted on the volume V through its bounding surface S is

$$\int_S \sigma(\hat{n}) dS$$

If f is the external force per unit mass (e.g., $f = -g\hat{x}_3$), the total external force will be

$$\int_V \rho f dV$$

The principle of conservation of linear momentum asserts that the sum of these two forces equals the rate of change of linear momentum of the volume.

$$\frac{d}{dt} \int_V \rho v dV = \int_V \rho f dV + \int_S \sigma(\hat{n}) dS$$

If V is a volume of a given shape with a characteristic dimension d then $V \sim d^3$ and $S \sim d^2$. As we let V shrink on a point but preserve the shape, the first two integrals decrease as d^3 where as the last will as d^2 . So,

$$\lim_{d \rightarrow 0} \frac{1}{d^2} \int_S \sigma(\hat{n}) dS = 0$$

ie., the stresses are locally in equilibrium.

A.11 Stress is a tensor

Adapted from section 5.12 of [Aris, 1962] and section 1.3, pg.9 of [Batchelor, 1967].

Stress σ is defined as force per unit area. Consider all the forces acting instantaneously on the fluid within an element of volume δV in the shape of a tetrahedron. The three orthogonal faces have areas δA_1 , δA_2 and δA_3 and unit outward normals as $-\hat{a}$, $-\hat{b}$ and $-\hat{c}$. The fourth inclined face has area δA and unit normal $\hat{n}$. The resultant of surface forces is

$$\sigma(\hat{n})\delta A + \sigma(-\hat{a})\delta A_1 + \sigma(-\hat{b})\delta A_2 + \sigma(-\hat{c})\delta A_3$$

In view of the orthogonality of three of the faces,

$$\delta A_1 = \hat{a} \cdot \hat{n} \delta A$$

$$\delta A_2 = \hat{b} \cdot \hat{n} \delta A$$

$$\delta A_3 = \hat{c} \cdot \hat{n} \delta A$$

Thus the balance of forces along direction i can be written as

$$\delta A \left[\sigma_i(\hat{n}) - \left\{ \hat{a}_j \sigma_i(\hat{x}_1) + \hat{b}_j \sigma_i(\hat{x}_2) + \hat{c}_j \sigma_i(\hat{x}_3) \right\} \hat{n}_j \right]$$

As we shrink the volume ($V \sim d^3$), since the area shrinks only as $S \sim d^2$, the quantity in square brackets must go to zero for local equilibrium. ie.,

$$\sigma_i(\hat{n}) = \left\{ \hat{a}_j \sigma_i(\hat{x}_1) + \hat{b}_j \sigma_i(\hat{x}_2) + \hat{c}_j \sigma_i(\hat{x}_3) \right\} \hat{n}_j$$

If we represent the quantity in the flower brackets on R.H.S. as σ_{ij} ,

$$\sigma_i(\hat{n}) = \sigma_{ij} \hat{n}_j$$

Since the **vectors** σ_i (surface force per unit area) and $\hat{n}$ (unit normal to the surface) donot depend on the choice of co-ordinate axes, the quantity connecting them σ_{ij} must represent (i, j) -component of a axes-independent entity namely, a tensor of order 2. This is also true by the quotient rule of tensors.

A.12 Stress tensor is symmetric

Adapted from section 2.7 pg. 57 of [Sabersky et al., 1989].

Consider stress at the center of a control volume of size $\delta x_1 \times \delta x_2 \times \delta x_3$ as shown in the figure. The torque produced by the forces about an axis along $\hat{x}_3$ and through the center of gravity of the CV is

$$T = \sigma_{12}\delta x_1\delta x_3\delta x_2 - \sigma_{21}\delta x_2\delta x_3\delta x_1$$

or

$$T = (\sigma_{12} - \sigma_{21})\delta x_1\delta x_2\delta x_3$$

The torque may be equated to the product of angular acceleration ($\ddot{\alpha}_3$) and the moment of inertia taken about the previously mentioned axis ($\hat{x}_3$):

$$(\sigma_{12} - \sigma_{21})\delta x_1\delta x_2\delta x_3 = \frac{\rho}{12}\delta x_1\delta x_2\delta x_3(\delta x_1^2 + \delta x_2^2)\ddot{\alpha}_3$$

or

$$(\sigma_{12} - \sigma_{21}) = \frac{\rho}{12}(\delta x_1^2 + \delta x_2^2)\ddot{\alpha}_3$$

As we shrink the CV to infinitesimal size, since the term in the bracket on the right goes to zero, if the L.H.S. were to remain finite $\ddot{\alpha}_3$ must blow up. It can be prevented only if L.H.S. is zero. ie.,

$$\sigma_{12} = \sigma_{21}$$

or

The tensor σ_{ij} is **symmetric**.

A.13 Meaning of terms in strain rate tensor

Figure A.1 shows how a fluid element deforms during its motion. The deformation can be analysed into different modes and the respective strains and strain rates can be expressed in terms of the velocity gradients as shown below.




Figure A.1: Analysis of deformation of a fluid element

In this handout, the geometry is restricted to 2D and the symbols used are x, y for axes, u, v for velocity components along those axes, respectively, for easy observation. The results can be extended to 3D using subscript notation.

Initial Positions:

A	x_0	y_0
B	$(x_0 + \Delta x)$	y_0
C	$(x_0 + \Delta x)$	$(y_0 + \Delta y)$
D	x_0	$(y_0 + \Delta y)$

Velocities:

A	u	v
B	$(u + \frac{\partial u}{\partial x} \Delta x)$	$(v + \frac{\partial v}{\partial x} \Delta x)$
C	$(u + \frac{\partial u}{\partial x} \Delta x + \frac{\partial u}{\partial y} \Delta y)$	$(v + \frac{\partial v}{\partial x} \Delta x + \frac{\partial v}{\partial y} \Delta y)$
D	$(u + \frac{\partial u}{\partial y} \Delta y)$	$(v + \frac{\partial v}{\partial y} \Delta y)$

Positions after dt :

P	$x_0 + udt$	$y_0 + vdt$
Q	$(x_0 + \Delta x) + (u + \frac{\partial u}{\partial x} \Delta x)dt$	$y_0 + (v + \frac{\partial v}{\partial x} \Delta x)dt$
R	$(x_0 + \Delta x) + (u + \frac{\partial u}{\partial x} \Delta x + \frac{\partial u}{\partial y} \Delta y)dt$	$(y_0 + \Delta y) + (v + \frac{\partial v}{\partial x} \Delta x + \frac{\partial v}{\partial y} \Delta y)dt$
S	$x_0 + (u + \frac{\partial u}{\partial y} \Delta y)dt$	$(y_0 + \Delta y) + (v + \frac{\partial v}{\partial y} \Delta y)dt$

Dilational strain along x , s_{11} is $\frac{PQ_x - AB}{AB}$. Shear strain along y , s_{12} is $\frac{PQ_y}{AB}$.

Dilational strain along y , s_{22} is $\frac{PS_y - AD}{AD}$. Shear strain along x , s_{21} is $\frac{PS_x}{AD}$.

Dilational Strain rate:

$$e_{11} = \frac{\frac{\partial u}{\partial x} \Delta x dt}{\Delta x} \frac{1}{dt} = \frac{\partial u}{\partial x}$$

$$e_{22} = \frac{\frac{\partial v}{\partial y} \Delta y dt}{\Delta y} \frac{1}{dt} = \frac{\partial v}{\partial y}$$

Shear Strains:

$$\alpha = \frac{\frac{\partial v}{\partial x} \Delta x dt}{\Delta x} = \frac{\partial v}{\partial x} dt$$

$$\beta = \frac{\frac{\partial u}{\partial y} \Delta y dt}{\Delta y} = \frac{\partial u}{\partial y} dt$$

Pure shear strain rate:

$$e_{12} = e_{21} = \frac{1}{2}(\alpha + \beta) \frac{1}{dt} = \frac{1}{2} \left(\frac{\partial v}{\partial x} + \frac{\partial u}{\partial y} \right)$$

Pure rotational rate:

$$\Omega_{12} = -\Omega_{21} = \frac{1}{2}(\alpha - \beta) \frac{1}{dt} = \frac{1}{2} \left(\frac{\partial v}{\partial x} - \frac{\partial u}{\partial y} \right)$$

One can say generalize the above expressions using the subscript notation in the following way:

General strain rate tensor:

$$s_{ij} = \frac{\partial u_i}{\partial x_j}$$

Expressing it as a sum of symmetric (e_{ij}) and anti-symmetric (Ω_{ij}) tensors:

$$s_{ij} = e_{ij} + \Omega_{ij}$$

Dilation:

$$s_{ij} \delta_{ij} = s_{ii} = e_{ii} = \frac{\partial u_i}{\partial x_i}$$

Shear:

$$\frac{1}{2} (s_{ij} + s_{ji}) = \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i}$$

Rotation:

$$\frac{1}{2} (s_{ij} - s_{ji}) = \frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i}$$

A.14 Strain rate tensor

Adapted from section 4.41 of [Aris, 1962]

Consider two points P and Q at co-ordinates ξ and $\xi + d\xi$. At time t they are to be found at $x(\xi, t)$ and $x(\xi + d\xi, t)$.

Using only the first term of Taylor's expansion,

$$x_i(\xi + d\xi, t) = x_i(\xi, t) + \frac{\partial x_i}{\partial \xi_j} d\xi_j$$

So the displacement vector is

$$dx = x(\xi + d\xi, t) - x(\xi, t)$$

where

$$dx_i = \frac{\partial x_i}{\partial \xi_j} d\xi_j$$

Since dx and $d\xi$ are vectors, by quotient rule, the nine quantities $\frac{\partial x_i}{\partial \xi_j}$ form the components of a tensor of order 2.

Since we define velocity v as $v = \frac{dx}{dt}$, the relative velocity of two fluid particles at ξ and $\xi + d\xi$ is

$$du_i = \frac{\partial u_i}{\partial \xi_k} d\xi_k = \frac{d}{dt} \frac{\partial x_i}{\partial \xi_j} d\xi_j$$

Using the inverse of the relation given above,

$$du_i = \frac{\partial u_i}{\partial \xi_k} \frac{\partial \xi_k}{\partial x_j} dx_j = \frac{\partial u_i}{\partial x_j} dx_j$$

Once again, by quotient rule, the components of $\frac{\partial u_i}{\partial x_j}$ form a tensor of order 2. This is called velocity gradient tensor. Like any tensor of order two, velocity gradient tensor can be split into two tensors, one symmetric and one anti-symmetric.

$$\frac{\partial u_i}{\partial x_j} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) + \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right)$$

We denote the symmetric part of the velocity gradient tensor as e_{ij} (strain rate tensor) and the anti-symmetric part as Ω_{ij} (vorticity tensor).

$$\frac{\partial u_i}{\partial x_j} = e_{ij} + \Omega_{ij}$$

As shown in the section A.13, we can recognise that e_{ij} represents rate of strain (both dilational and shear) and Ω_{ij} represents rigid body rotation.

Bibliography

- [Anderson and Krathwohl, 2001] Anderson, L. W. and Krathwohl, D. R. (2001). *A Taxonomy for Learning, Teaching and Assessing: a Revision of Bloom's Taxonomy*. Longman Publishing.
- [Aris, 1962] Aris, R. (1962). *Vectors, Tensors and the Basic Equations of Fluid Mechanics*. Prentice Hall Inc, Eaglewood Cliffs, N.J.
- [Batchelor, 1967] Batchelor, G. (1967). *An Introduction to Fluid Dynamics*. Cambridge University Press, Eaglewood Cliffs, N.J.
- [Bird et al., 2002] Bird, R. B., Stewart, W. E., and Lightfoot, E. N. (2002). *Transport Phenomena*. John Wiley and Sons.
- [Bourne and Kendall, 1992] Bourne, D. and Kendall, P. (1992). *Vector analysis and cartesian tensors*. CRC Press, third edition.
- [de Groot and Mazur, 1984] de Groot, S. and Mazur, P. (1984). *Non-equilibrium thermodynamics*. Dover Publications Inc., New York.
- [Gaskell, 1992] Gaskell, D. R. (1992). *An Introduction to Transport Phenomena in Materials Engineering*. Macmillan Publishing Company, New York 10022.
- [Geiger and Poirier, 1994] Geiger, D. and Poirier, G. (1994). *Transport Phenomena in Materials Processing*. TMS, Warrendale, PA, USA.
- [Newnham, 2005] Newnham, R. E. (2005). *Properties of materials : Anisotropy, Symmetry, Structure*. Oxford University Press.
- [Onsager, 1931a] Onsager, L. (1931a). Reciprocal relations in irreversible processes - i. *Physical Review*, 37:405–426.
- [Onsager, 1931b] Onsager, L. (1931b). Reciprocal relations in irreversible processes - ii. *Physical Review*, 38:2265–2279.
- [Perelomova and Tagieva, 1983] Perelomova, N. and Tagieva, M. (1983). *Problems in Crystal Physics with solutions*. Mir Publishers, Moscow.
- [Riley et al., 2006] Riley, K., Hobson, M. P., and Bence, S. (2006). *Mathematical methods for physics and engineering*. Cambridge University Press, London, third edition.
- [Sabersky et al., 1989] Sabersky, R. H., Acosta, A. J., and Hauptmann, E. G. (1989). *Fluid Flow : A first course in Fluid Mechanics*. Macmillan Publishing Company, New York, 3 edition.

- [Tinder, 2008] Tinder, R. F. (2008). *Tensor Properties of Solids : Phenomenological development of the tensor properties of crystals*. Morgan and Claypool Publishers.

Index

- Cartesian summation convention, 15
- Characteristic equation, 53
- Compressibility, 70, 96
- Concept map, friction factors, 136
- Concept map, heat transfer solutions, 153
- Concept map, material derivative, 64
- Concept map, Stokes law, 123
- Concept map, subscript notation, 14
- Constitutive relation, 54
- Contraction theorem, 48
- Coordinate transformation, 34
- Creeping flow, 126
- Cross product, 22
- Curie principle, 54
- Determinant, 22
- Deviatoric stress, 93
- Dual tensors, 49
- Dyadic product, 48
- Eulerian specification, 66
- Form drag, 130
- Friction drag, 131
- Gauss Divergence theorem, 92
- Incompressible fluid, 70
- Inner product, 15
- Inviscid fluid, 100
- Kronecker delta, 19
- Lagrangian specification, 66
- Levi-Civita symbol, 20
- Navier-Stokes equation, 90, 96
- Neumann principle, 54
- Newtonian fluid, 99
- Orthogonality, 42
- Outer product, 16
- Permutation matrix, 20
- Pressure, 93
- Quotient law, 48
- Rate of dilation, 70, 96
- Rate of expansion, 70, 96
- Reynolds number, 101
- Reynolds transport theorem, 92
- Secular equation, 53
- Stokes assumption, 96
- Stokes law, 131
- Strain rate tensor, 93
- Stream function, 78
- Subscript notation, 15
- Tensor, 47
- Tensor operations, 48
- Tensor, anti-symmetric, 49
- Tensor, isotropic, 58
- Tensor, symmetric, 48
- Transformation matrix, 42
- Viscosity, 100