# General Platform/Repository Configuration

For the alfresco.war

# Storage location

- Configuration file: alfresco-global.properties
- Property: dir.root=/opt/alfresco5.2GA/alf\_data
- **Description**: Points to the base directory for Alfresco content, index, and sometimes meta-data (DB)
- Dependent properties:
  - dir.contentstore=\${dir.root}/contentstore
  - dir.contentstore.deleted=\${dir.root}/contentstore.deleted
  - dir.cachedcontent=\${dir.root}/cachedcontent
  - dir.auditcontentstore=\${dir.root}/audit.contentstore
  - o dir.keystore=\${dir.root}/keystore
  - ooo.user=\${dir.root}/oouser
- Default config: webapps/alfresco/WEB-INF/classes/alfresco/repository.properties

#### **URLs**

- alfresco.context=alfresco alfresco.host=arenadocs.wwf.org.uk alfresco.port=443 alfresco.protocol=https
- share.context=share share.host=arenadocs.wwf.org.uk share.port=443 share.protocol=https

- Configuration file: alfresco-global.properties
- Properties:
  - o alfresco.context=alfresco, alfresco.host=127.0.0.1, alfresco.port=8080, alfresco.protocol=http
  - o share.context=share, share.host=127.0.0.1, share.port=8080, share.protocol=http
- Description: Specifies the parameters that control how Alfresco generates
   URLs to the repository and Share. Used for example to generate URL links in
   notification emails
- Default config:
  - webapps/alfresco/WEB-INF/classes/alfresco/repository.properties

## Database

- Configuration file: alfresco-global.properties
- Properties:
  - db.driver=org.postgresgl.Driver
  - o db.username=alfresco
  - o db.password=admin
  - db.name=alfresco
  - o db.url=jdbc:postgresql://localhost:5432/\${db.name}
  - o db.pool.max=275
  - o db.pool.validate.query=SELECT 1
- Description: Specifies the parameters that control how Alfresco connects to the database for storing meta-data
- **Default config**: webapps/alfresco/WEB-INF/classes/alfresco/repository.properties

### Document converters

- Configuration file: alfresco-global.properties
- Properties:
  - ooo.exe=/opt/alfresco5.2GA/libreoffice/program/soffice.bin
  - ooo.enabled=false, ooo.port=8100
  - o jodconverter.enabled=true
  - o jodconverter.officeHome=/opt/alfresco5.2GA/libreoffice
  - o jodconverter.portNumbers=8100
- Description: Specifies what tool Alfresco should be using for document transformations. LibreOffice is used by 5.2. The JODConverter automates conversions between office document formats using LibreOffice.
- **Default config**: webapps/alfresco/WEB-INF/classes/alfresco/repository.properties

## Image converters

- Configuration file: alfresco-global.properties
- Properties:
  - img.root=/opt/alfresco52GA/common
  - o img.dyn=\${img.root}/lib
  - o img.exe=\${img.root}/bin/convert
  - o img.coders=\${img.root}/modules/coders, img.config=\${img.root}/config, img.gslib=\${img.root}/lib
  - **Description**: Specifies what tool Alfresco should use for image manipulation.

Alfresco uses ImageMagick to manipulate images for previewing (i.e. convert

• Default config:

shell script).

webapps/alfresco/WEB-INF/lib/alfresco-repository-<version>.jar/alfresco/subsyste ms/thirdparty/default/imagemagick-transform.properties