In-app checklist

In-app check list (written 2026-10-14, merged 2026-10-22, updated 2026-10-29)

Everything here is code that exists and has passing tests but that nobody has looked at in the running app or on hardware. Tick a box when it works. Write what you saw next to anything that doesn't.

The 2026-10-22 merge added the Browse/Library/Edit review, the Clock row rework, the Super Knob / Metaknob review, the FX review and the sources review, plus everything else since 2026-10-17. It rewrote items the later work had made stale (the pair list, Metaknob "link modes", the crossfader's place, the Maps tab, the open gaps that have since been closed) and dropped three that no longer apply: the inline picker, the XF+CLK pair, and *Retarget Metaknob*.

Before starting: a build from current `main`, a fresh run, and a note of the screen size (min supported 1280x720). Do the whole list once in the dark theme, then the Light theme section. The title bar's `GPU buffers: n (MB)` readout is the quickest leak check.

---

1. Library and browser

Library tabs are now Sources, FX, Transitions, Queues, Macros.

- [ ] Ctrl+F opens the Library on the current tab; Esc goes back to where you were (from Edit or a pair view: the same view, with the same slot still bound). !!needs ESC pressed twice. first time exits text box, second closes (could be by design)
- [ ]

- [x] Sources, FX and Transitions tabs: list scrolls, search works, typing a letter while the list has the keyboard starts a search (shortcut keys such as `Q` keep their shortcut). !!tooltip on transitions: "add to a/b queue" should be "add to transitions queue" right?
- [x] Rows: no empty box on stock items, long names end in "..." with the full name on hover, `hyperspace_crash_zoom` reads "Hyperspace crash zoom", heavy shaders show a muted gauge with an explanation on hover.
- [x] Loaded-where chips: `A`/`B`/`BG`/`PV`/`M` on sources; `A2`/`M1` on effects; a deck playing a saved preset marks the preset row, not the generator; many slots collapse to `×n` with the full list on hover. !!loading the same source to all 4 decks was fine up to A+B+BG but then when I added PV also, I had 4 colored chips with no text in them. same with effects. no xn, nothing on hover
- [x] Recent folder in Sources, FX and Transitions: last 20 loads, newest first, still there after a restart.
- [x] Menus match across tabs (right-click works on FX and transition rows too): Rename..., Clone, Delete..., Add to playlist, **Reveal in File Manager**. !!we should make "add to playlist"" open a side menu with the playlists and the subfolders of playlists
- [x] Deleting a saved effect or transition also removes it from queues and playlists.
- [ ] Rename a saved FX single, an FX chain and a transition that are in a playlist and a queue: the playlist and queue rows still play, Favorites/Recent still list it. Rename a preset loaded on Deck A, then Save: it writes the renamed file (no old-name file reappears) and the preset's garden thumbnail is still shown.
- [ ] Delete a preset loaded on a deck: it drops out of Recent/Favorites; Save on that deck asks for a name. Delete an FX chain loaded on Master: Master's chain header no longer offers overwrite.
- [ ] Folders: folder-plus button and right-click New/Rename/Delete Folder on Saved presets, Saved single FX, Saved chains, Saved transitions (not on stock sections); an empty folder shows in the tree; with FX and no saved section selected the button is greyed with a tooltip.
- [ ]

- [ ] Drag rows (one, and a multi-selection) onto a folder, and use Move to: they move, playlists/queues still play them, a loaded deck still saves back. Moving onto a same-named item asks Keep both / Skip.
- [ ] Drag a folder onto another folder and onto its section; renaming a folder you're inside keeps it selected; deleting it selects its parent. Delete Folder shows the item count and the playlists/queues they're in.
- [ ] Delete (file or folder) lands in the system trash on this desktop (Linux: `gio trash`); the dialog says so.
- [ ] Save As (deck, FX slot, chain, transition): the Folder dropdown starts in the loaded item's folder, else the selected tree folder, else top level, and the file lands where it says.
- [ ] Tags group (folded at first) on Sources, FX and Transitions: counts right, picking a tag lists its items, stock categories don't show. Add Tag on one row and on a multi-selection (existing-tag buttons fill the field), Remove Tag submenu, drag rows onto a tag, Rename Tag / Delete Tag on a tag row.
- [ ] Tag a preset loaded on a deck, then Ctrl+S: the new tags survive. Star a saved single FX and a chain: ★ in the list, listed under Favorites; slot ◀ / ▶ still steps stock filters only.
- [ ] Missing items: move a preset in the file manager, open a playlist that has it: ⚠ row with Find (pick the moved file), Locate..., Remove; Find all fixes the unique ones and the queue/other playlists follow.
- [ ] Playlist folders on all three tabs: New Folder on Playlists, drag a playlist onto a folder (stays selected), rename/delete/nest folders.
- [ ] Enter runs the row's default action on every tab; Delete follows Preferences > Shortcuts (Backspace works too); Alt+click a Sources row previews it on PV.
- [ ] Rename, Delete, New Playlist and Export dialogs: field focused, Enter confirms, Esc cancels without leaving the Library. Esc that closes a menu doesn't also go back.
- [ ] Queues tab: an empty queue says how to fill it, five matching button strips (FX queues' Auto greyed), Export / Clear under each

column's , no dead play button on the FX queues. The controller steps the columns left to right.

- [ ] Queues under the browser (Library maximized, Sources/FX/Transitions tabs): both halves usable at 1280x720; the divider drags, clamps, double-click resets, the ratio and the rows-icon toggle survive a restart; toggle off looks like before; Perform view's Library unchanged.
- [ ] Drag a source between two A/B queue items: lands at the line, the playing marker stays on its row. Drag it over the FX queues: dimmed, no drop. Drag a mixed selection: right ones go in, toast counts the skipped. Drag a playlist from the tree into a queue: its items go in at the line.
- [ ] Drag to the bottom edge of a long queue (and of the browser list/tree): it scrolls. `Q` / `Shift+Q` and drops flash the receiving queue's border (dark and light theme).
- [ ] Arrow keys / controller cursor on the split: tree, list, then the five queues; `Q` with the cursor in a queue does nothing.
- [ ] Queue edits undo: drag-reorder, row-menu Remove and Delete in each of the five queues, then Ctrl+Z: items, playing marker and shuffle order come back; Remove toasts what went. Drag a BG queue item down: it lands where the line was.
- [ ] Macros tab: macro banks and Perform pages are listed; loading one works.
- [ ] Transitions view: the Q key queues.
- [ ] Double-click a preset in the queue: auto-fades and advances. Accept from MIDI/keyboard: same.
- [ ] Load a single `.lsdfx` into a full chain by double-click, by audition latch, and from the FX queue / FX playlist: one consistent placement rule.
- [ ] Drop targets: deck badge takes presets, stock sources, external video, `.lsdfxchain` and `.lsdfx`. Monitor takes FX. Slot drop in Edit accepts the same drags as the slot cell.
- [ ] A failed FX or transition load shows a toast.

- [ ] Queue jumps of more than one step from MIDI/CV (+3) move three items. The keyboard queue keys still step once per press (they now run separately from MIDI/CV).
- [ ] Unsaved-changes prompt: Enter saves, Esc cancels (Esc did nothing there before 2026-10-23), buttons the same width, "Don't ask again" says loads are undoable. Eject and Copy/Move/Swap are not undoable and the Preferences tooltip says so.
- [ ] Closing Video Export while it waits on the unsaved-changes prompt does NOT start the export.
- [ ] Click a preset then a source on the same deck within a blink: the last click wins.
- [ ] Save a transition from the Transitions row's Save, from Edit OUT > TRANS and from the Library.
- [ ] Star an FX in the Library: it's in your favorites, and the slot shortlist arrows land on it.
- [ ] Multi-select (2026-10-27) in Sources, FX and Transitions: Ctrl+click toggles, Shift+click ranges, Ctrl+A selects all shown rows (not while typing in search). Right-click inside the selection: Add N to queue / playlist, Delete N. `Q`/`Shift+Q` and Delete act on all. Drag several FX or transitions into a playlist and into their queues: all land, in order. A bound list (picking for a slot) stays single-select.

2. Slots bound in place, pair view and Edit

- [ ] With the rows on the current page, click a source name, a chain name, an FX slot and the transition name: nothing moves, the slot is outlined, the Library's tab line shows its name, buttons and ✕, the list border takes the row's colour.
- [ ] Breathing (2026-10-28): the bound slot's outline (source badge, chain name, FX slot, transition name) breathes slowly and never vanishes; the Library tab-line name and the Edit view header sit in a row-coloured pill breathing in step with it. Easy to spot on a busy screen, not mistakable for the amber OSC-learn pulse, not annoying over a long browse. Paused binding: grey, no pill.

- [ ] In a bound list: a click applies (Ctrl+Z undoes), a double-click applies and returns to the plain Library; Esc, ✕ or clicking the slot again stops without applying; changing page stops.
- [ ] Deck monitors, the main output monitor and the Master `M` badge bind their default half (a deck's source, the Master FX chain).
- [ ] Space or maximizing the Library pauses the binding; Esc or Space again resumes.
- [ ] The pair view opens only for rows off the page (e.g. the BG monitor from the A/B page, or a Twister send to such a deck).
- [ ] Pairs: each deck's SRC + FX; the Master pair is Transitions + Master FX and browses the Master FX chain until you touch the transition. MST + Clock pair only in Edit (Browse greyed with a tooltip).
- [ ] Pair view and Edit share one header line: Back, `Browse | Params`, target and its buttons, queue next-up; switching moves nothing. On the Transitions pair, Params opens the transition editor.
- [ ] Trying sources on a deck with unsaved changes asks once while it stays bound; Ctrl+Z still undoes each load.
- [ ] Saved presets, effects and transitions show as applied (row tint) in a bound list.
- [ ] Touching a controller knob doesn't pull the browser off the Queues or Macros tab unless it moves the binding.
- [ ] Learn inside a pair view drops to the 4-row layout (accepted for now). Learn finishes, state sane.
- [ ] Page tabs close the pair view. Esc leaves it and drops the dock selection.
- [ ] Scope, search and cursor memory are kept per kind (FX, then Sources, then back to FX).
- [ ] Badge, slot and monitor tooltips say the list below applies and a second click stops.
- [ ]

- [ ] Edit shows the open unit's pair of rows (deck SRC + FX; OUT: Transitions + Master FX; MST: MST + Clock). Switching SRC/FX doesn't redraw the rows. The lit gear marks the editor's row; the other row's gear moves the editor; the lit gear closes Edit.
- [ ] Edit side rail reads `MST OUT A B BG PV`, nothing clipped. MST has LEVELS and CTRL; OUT has FX and TRANS and returns to the last one. Gears: MST row → MST > LEVELS, Master FX → OUT > FX, Transitions → OUT > TRANS.
- [ ] Edit FX tab: one slot open at a time (the first filled slot opens first), collapsed slots show Dry/Wet, the SUPER KNOB & METAKNOBS block folds on its own chevron.
- [ ] Edit shows readable names ("Cell scale", the shader's LABEL); Properties is never empty when you open a deck or switch tabs; CTRL/TRANS labels in sentence case; the transition selector fits its name; Max isn't cut off in the binding editors.
- [ ] Ctrl+Z after picking an FX and after picking a transition in Edit.
- [ ] Library loads, queues and macro changes are not undoable (as designed); nothing odd happens.
- [ ] Edit gear exits (Esc, gear, menu Close Edit, Ctrl+F) keep each row's sub-tab and selected cell. The Edit module survives a restart.

3. Perform rows, Transitions row and Clock row

- [ ] Two-line deck rows with the two-tone SRC/FX badge, readable at 1280x720. Switching modes changes content, never geometry.
- [ ] Button chrome / bevel looks fine on every button type.
- [ ] Knob captions carry whole readable names ("TRACKING JITTER"), "..." only when too narrow.
- [ ] Transitions row: picker and gear on line 1; `[⋮] [Save] [◂] [▸] [A] [B] [AUTO] [time]` in equal cells on line 2; Save turns amber when changed; queue position in the ◀ ▶ tooltips.

- [ ] Transitions at rest (2026-10-27): with the crossfader fully on A (then B), switch through all 8 transitions: the picture does not change at all. Start a slow fade from rest on each: no jump on the first frame of the fade.
- [ ] Cyber Datamosh at rest (2026-10-27 fix): select it, push the crossfader fully to B (and let an auto fade land on B): B's colours look normal, no red/blue smear. Same on A. Check on the web TV too if you test it.
- [ ] MIXER page order: Transitions, Master FX, Master MST, Clock. The crossfader is Transitions knob 1 (and the Mixer panel), not on the MST row. MST pill reads `MST`.
- [ ] Clock row at 1280 px: tempo grid `MAN AUDIO LINK` over `TAP SNAP [-|+]`, BPM and beat dots beside it, LINK dim while off.
- [x] Tempo tracking (2026-11-04, clock source Audio): play techno, rock, reggae and drum and bass, and watch the BPM readout. It should lock in about 2 s and hold steady through a track, at the right tempo or an octave off. Try a low JACK buffer (64 or 128) if you can: the tempo should be the same as at 512, with no new xruns. Watch beat-synced LFOs for a jump when a track changes. Downbeat Auto should behave as before.
- [ ] Bar & Downbeat (2026-10-23, Preferences > Tempo & Sync): Beats per bar 2..8 changes the bar dots (still fit the cell at 8) and the Twister clock knob's orange flash; with Link on it also changes the quantum. SNAP: the cyan dot lands on the beat you pressed on, with a jump of at most half a bar; the first TAP of a run does the same, later taps leave the bar line alone. Downbeat Auto with the Audio Beat Tracker on real dance music: confidence rises over ~4-8 bars, the bar line moves onto the kick/bass accent once and stays; a breakdown does not wander it; SNAP then holds for 16 bars. Note which genres it fails on (flat four-on-the-floor stays undecided by design). Bar-length LFO/sequence jump once when the bar line moves, nothing else.
- [ ] Clock QUEUE block: `A/B | A/B FX | BG | BG FX | TRN` captions over ◀ ▶ pairs; play/pause on A/B, BG and TRN toggles auto-advance (lit while running); faint group tints show which go together.
- [ ]

Clock RAND block at the right edge (randomization on): `A B ALL` over `BG PV`; Ctrl+Z undoes.

- [ ]

Every Clock button is also on MST > CTRL; right-click Learn MIDI/OSC works from both. A MIDI CC drives the FX queue steps.

- [ ]

Narrow the window: a block that doesn't fit is left out, nothing overlaps.

- [ ]

FX slot rows (2026-10-27, Chain view part 1): in Preferences > MIDI Controls > Perform Pages make a page of `deck.A.fx1`, `deck.A.fx2`, `deck.A.fx3`, `deck.A.src`. Badges read FX1/FX2/FX3; each row's knob 1 is its slot (name + bypass), knobs 2-4 its parameters, whatever the Deck A FX row's focus. Left block: effect name (click = Browse that slot), `[:] [Wet] [◄ Px/y ►]`; die + FX ON only on the FX1 row. Drop an effect on an FX2 badge: it lands in slot 2. Page arrows page only their own slot; focusing that slot on the FX row opens on the same page. Geometry matches the other rows at 1280x720. On a Twister: the three slot rows are three distinct shades.

- [ ]

Chain view (2026-10-27): menu of Deck A's FX row > Chain View: rows read `FX1`, `FX2`, `FX3`, `A SRC` over the Browse list (source row at the bottom since 2026-10-28), same knob size as Perform, nothing clipped at 1280x720. Touch a knob on FX2: the list targets slot 2. **Load** on the Browse header: row 4 becomes the load row (highlighted effect's name, → FX1/→ FX2/→ FX3, LIST); rows 1-3 don't move. Highlight an effect and click → FX3: it loads into slot 3 with the fade, Ctrl+Z undoes it, the list now targets slot 3. Load again brings the SRC row back. Chain toggle and Esc both leave in one press (Esc even with a slot focused on the FX row). Master: Chain View from the Master FX menu shows Transitions at the bottom. A page tab click leaves Chain view.

- [ ]

Chain view on the Twister (2026-10-27): on A/B, shift + tap a Deck A SRC knob: Chain view opens, all 16 knobs move the four rows (FX1-3, then SRC on 13-16), FX rows in three shades. Right-bottom: Load on, knobs 13-15 glow in the slot colours (dark with nothing highlighted), knob 16's ring is the list position; turning knob 16 moves the list, tapping knob 14 loads the highlighted effect into slot 2 and knobs 5-8 then play it straight away. Right-bottom again: SRC row back. Bank buttons: Deck B's Chain view, Load state kept. Left-top or shift + tap on the SRC row (13-16) leaves. Does the source row at the bottom read OK?

- [ ]

Monitor drag onto another monitor: nine-choice menu (Move / Copy / Swap × Source / FX / Source + FX), each does what it says.

4. Sources (2026-10-22 review)

- [ ] Load a curated flame (garden): no `*`, Save not red. Load something else over it: no unsaved-changes prompt.
- [ ] Badge with a preset reads `curated-0001 · Fractal Flame` (source dimmed); a bare source shows just its name; narrow the window and the source part goes first. The tooltip always names both.
- [ ] Browse, saved presets: the info column starts with the source (`Fractal Flame · curated, flame`); hover shows "Plays: ...".
- [ ] Load a preset from `garden/` or `imported-flames/`, change a knob, Save: that file changes, and no new copy appears at the top of `presets/`. Save As with a new name goes to `presets/`.
- [ ] Missing source: rename a user shader that a saved preset uses, Rescan. The preset's row shows ⚠ "... missing" with a tooltip; loading it gives a toast and the deck keeps what it had. A session saved with that source restores the deck empty and lists it under missing items.
- [ ] Click the stock source of the preset you're playing: its defaults load. Click it again: nothing happens.
- [ ] SRC tab rows: Gain, **Deck Zoom**, **Deck Rotate**, then the source's own. On Reaction Diffusion / Escape Time the two Zooms are clearly different; 3D sources (KIFS, Gyroid) hide Deck Zoom / Rotate. Tooltips explain them.
- [ ] Set Deck Zoom, pick another source: it resets. Load a preset: it keeps its saved framing.
- [ ] Deck Zoom and Deck Rotate now move Isometric Voxels and Wave Ripples.
- [ ] MIDI-learn Gain on Deck A, change source several times: the mapping still drives Gain. A mapping saved before (path `Deck A/<Source>/Gain`) still works. MST > LEVELS shows only level faders.

- [ ] Leak check: load ~30 sources and flame presets in a row on one deck (or run an A/B queue of flames for a while); `GPU buffers` in the title bar stays roughly flat.
- [ ] Ctrl+Z after a source change brings the old one back (a flame or simulation restarts fresh; expected).
- [ ] Eject empties the deck and keeps its FX chain; tooltip says so. Empty-deck card in Edit: one **Add Source** button that opens Browse.
- [ ] External video deck: Save greyed with a tooltip. Switch the deck to a generator: the stream is released (the sending app's receiver count drops, if it shows one).
- [ ] Preferences > Shader Locations: Add Folder and Rescan Now with a new `.fs` in it. No crash, the new source appears, its presets load, FX and transitions in use keep working.
- [ ] A shader with a syntax error: red checkerboard on the deck, ⚠ "failed to compile" in Browse, the first compiler error on hover.
- [ ] Two user shaders with the same file name: one loads, the log warns about the other.
- [ ] A shader that reads `iMouse` doesn't follow the cursor.
- [ ] Queue ◀ ▶ tooltips on the A and B rows name the off-air deck the item goes to. The die's tooltip lists what it randomizes.
- [ ] Old presets and sessions still load (they carry the removed deck feedback and 3D-view values, which are now ignored).
- [ ] On a packaged install over an older version: unedited bundled shaders are updated, an edited one is kept (log line). Needs a real install to test.

5. Off-air decks (2026-10-22)

- [ ] Crossfade fully to A: B's monitor runs at half rate; frame time drops with two heavy sources. Fade back: no hitch.

- [ ] A deck at level 0, and the master at 0: half rate. BG at level 0: half rate.
- [ ] PV renders at half size and still looks fine in its monitor; send PV out over Spout/Syphon/PipeWire and it goes to full size and full rate.
- [ ] Preferences > General **Off-air decks at half frame rate** off: everything renders every frame.
- [ ] A simulation (Reaction Diffusion, Lenia) cued off-air runs at half speed, then normal speed on air. Decide whether that's acceptable.

6. FX chains (2026-10-22 review)

- [ ] `FX ON` (lit = on) instead of BYPASS; its state survives a restart.
- [ ] No chain shows the unsaved • at launch. It lights for a slot, parameter, Dry/Wet, link or Metaknob-target change, not for turning the Super Knob or a Metaknob.
- [ ] Revert to Saved undoes parameter tweaks.
- [ ] One chain menu on the FX row and the Edit tab: Focus, Save As, Revert to Saved, Clear All Slots (a new Untitled chain), Copy / Paste Chain. Save As starts in the chain's folder.
- [ ] Saving over a chain keeps its tags; the chain takes the saved name. A failed save (read-only file) shows a message and stays unsaved.
- [ ] Ctrl+Z undoes slot drags (swap / Ctrl copy), drops, Paste, Reset Parameters, Clear, Revert, Library loads and the FX browser's right-click "Load to ...".
- [ ] Slot name tooltip shows the shortlist position (`★ 3/8`, `Blur 4/12`); stepping off a category's end lands in favorites.
- [ ] A plain mouse wheel over a slot scrolls; Ctrl + wheel steps the effect.
- [ ]

- [ ] Middle-click: Super Knob does nothing; a focused parameter's knob goes to its default.
- [ ] A chain at Chain Dry/Wet below 100% shows `Wet 40%` in its name; at 0% the name is dimmed.
- [ ] Feedback / trail effects don't flash an old frame when a slot comes back from bypass, 0% wet or FX off.
- [ ] Eject leaves the deck's FX chain untouched; Clear with FX refreshes the FX row's knobs.
- [ ] Replace the focused effect with one that has fewer parameters: the focus page follows, knobs 2-4 not blank.
- [ ] FX queue arrow tooltips name the deck and say A and B share one position.
- [ ] A MIDI/OSC mapping to `Deck X/FXChain/DryWet` needs relearning on `Deck X/FX/DryWet` (expected).

7. Super Knob and Metaknobs

- [ ] A linked slot's knob 2-4 moves its Metaknob (not dead); in Focus Mode a linked slot's knob 1 works.
- [ ] Preferences: **Super Knob response** Relative (default): linked slots at 20% and 90% both rise, stay apart, reach 100% / 0% together. Pickup: a slot waits for the Super Knob, amber link button with both values in its tooltip.
- [ ] Moving a linked Metaknob by hand (Edit row, MIDI, editing a target) isn't yanked back by the Super Knob.
- [ ] Default FX chain linking is Linked / Unlinked (an old Auto setting reads Linked).
- [ ] Metaknob editor: add targets, try each zone (Full, First Half, Second Half, Triangle, Bipolar), Invert Direction and each curve; Remove Target. A parameter's row menu in Edit has one **Metaknob Target** check. *Replace all links* is gone.
- [ ]

- [ ] Remove every target: the knob reads `NO TARGET` (slot tooltip explains), and it's still empty after save and reload (not Dry/Wet).
- [ ] A target naming a missing parameter shows `(missing)` and drives nothing.
- [ ] A Metaknob on Dry/Wet owns it: the focus header's Wet slider moves the Metaknob; macro/MIDI/OSC writes are suspended.
- [ ] Focus from Edit's SUPER KNOB & METAKNOBS block focuses the chain everywhere; the block shows knobs 2-4, page arrows and Group Mode.
- [ ] Swap effects between slots: each slot keeps its own link setting.
- [ ] Tap on the Super Knob's switch does nothing; Shift + tap is Chain Link.
- [ ] Rate / speed / decay parameters respond exponentially on focus knobs 2-4; turning focus on doesn't change a value. ⟲ and the Twister tap land on the default.
- [ ] A Metaknob with several targets starts where they're closest to their defaults when a slot loads or resets.
- [ ] Save an FX slot and a chain, reload: targets, zones and knob order restored. Knob layout right on Perform and in the pair view.
- [ ] ISF auto-bind: load a few filters; Super Knob and Metaknob do something sensible.
- [ ] *Remove Saved Default for (effect)* and *Save as Default* explain what they do.

8. Macros, learn and locks

- [ ] Arm macro Learn, OSC Learn and MIDI Learn at once; Esc cancels all three. MIDI Learn on a parameter, and Learn into a controller profile command, still capture the next control you move (MIDI handling moved earlier in the frame, 2026-10-23).
- [ ]

- [ ] A MIDI/OSC mapping made before a knob binding is suspended while the knob drives the target, flagged in both tables.
- [ ] Range sliders lock when `lfoMin/lfoMax` is bound; Randomize min/max inputs too.
- [ ] Knob- or Metaknob-driven Value: dragging, scrolling or typing in Initial Range moves the knob (through its curve), other targets follow; a Metaknob on a macro knob passes it up. Lobes, Recipe, Max Points and the grid Value cell stay locked.
- [ ] Metaknob-driven rows show the cyan bar, tint, `[K1]` badge and "Linked to its Metaknob" caption; Randomize off.
- [ ] FX-bank bindings are read-only in Properties and slider popups.
- [ ] Select a knob by clicking a parameter, then click the knob: one selection.
- [ ] Bound Min/Max labels and Beat Division labels open the popup.
- [ ] Type a value into a knob with curve, invert and zone set: the result respects them.
- [ ] Macro-bank import onto another deck: paths remap, `Mixer/...` stays.
- [ ] Click a chip on a MASTER knob bound to a deck parameter: selects sensibly.
- [ ] Reorder or delete a modulator: bindings stay on the right one.

9. Modulators and step sequencer

- [ ] Sequencer is on by default (an old settings file turns it on once).
- [ ] Bar editor: paint (5% snap, Shift free), scroll to nudge, double-click to type, right/middle-click resets; playing step outlined; 16 per row.
- [ ] Toolbar: Randomize, Invert, Shift < >, Copy/Paste between sequencers, Fill..., Euclid... (Rotate and preview), Clear. Snap menu. Keyboard editing with the pointer over the bars.

- [ ] Length 1-32 (odd lengths), Phase, Offset, Step Hold (randomize); Glide Curve greys when nothing glides; output trace and live dot; ghost steps past the length; bars dim when bypassed.
- [ ] Auto toggle: randomization re-rolls the pattern, morph slides between patterns.
- [ ] Changing Clock Unit converts the step duration.
- [ ] After the app has run 15+ minutes: sweep a Time-clocked LFO's period (and a sequencer's Time interval) by hand and from a macro. It speeds up or slows down, never jumps. A preset morph between two different LFO periods glides too (2026-10-23).
- [ ] Ctrl+Z undoes sequencer, LFO, Audio and MIDI CC edits (one step per drag).

9b. Audio response (2026-10-25)

- [ ] Preferences > Audio Hardware (reworked 2026-10-28): no Auto Gain checkbox or Headroom slider any more; auto gain is always on. Feed quiet and loud music: the "Auto gain amp/bass/mid/high" readout under Audio Response adapts within a few seconds, and silence does not boost noise. Input Gain is now **Input Trim**, under Channel Routing; turning it down does not calm the picture for long. Turn the input (or Input Trim) right down with music playing: the Sync State goes SILENT and an amber "Input too quiet for beat detection" line appears; it should not appear with nothing playing. If you had changed AGC Headroom before, Audio Response was adjusted once so the picture moves as before.
- [ ] Breakdowns and drops (2026-10-28, auto gain against a long-term level frozen in breakdowns): play a track with a clear breakdown (low end drops out for 15 s or more). Bass-driven motion goes calm within a few seconds and stays calm the whole breakdown (watch the Bass scope: it used to climb back within ~12 s); mids may stay lively. The drop hits as hard as before the breakdown. Steady music should move about as much as before this change. Swap to a much quieter track: it reads quiet for up to a minute, then normal; a much louder one is normal within ~5 s. Pause the music a few seconds and restart at a different level: it levels in at once.

- [ ] Section modulators (2026-10-28): on a parameter's Audio tab, the detection mode has a third button, **Section**, with a Signal combo (Energy, the four band energies, Drop) and no Response Profile. (The three buttons fit at 1280x720: confirmed 2026-10-28.) **Energy**: give a visible parameter a wide range. During steady music it rests mid-range (nothing moves for the first ~20 s), sinks toward Min soon after a breakdown starts and stays there until the drop, and rises when a louder song comes in. **Drop**: on a track with a breakdown of 4 s or more, the parameter jumps to Max at the drop and falls back over 4 bars. Judge whether the hit lands on the beat the bass came back on, or visibly late or early. First test (one song, 107 bpm, before the 2026-10-28 fix) was 2-3 beats late; drops are now called about half a second after the bass returns, so expect at most about a beat late. The Sections line under the auto gain readout shows the state, the level against usual, the 3 s breakdown timer and the drop count. A breakdown that sits around half the usual level (the Skrillex test) is too mild to count, by design for now. The Preferences > Audio Hardware scopes show both under the band scopes. Changing Audio Response must not change either. Copy/paste an Audio cell holding a section modulator keeps it.
- [x] Transient hits (2026-11-04, replaces the old flux signal under the same IDs): play sustained-bass music, then four-on-the-floor, on a few stock sources with kick responses. Also try rock and jazz: snares and hats should read about as strongly as on electronic music (hit sizing, TV v25). Hits should look punchier and less jittery. A held bass note should not pump anything Transient-driven, while a kick on top of it should. **Every stock Transient response changes here, with less motion on average: about 40-50% in the bass and less in the higher bands**: note any look that now feels too calm. At a low JACK buffer (64 or 128) kicks should look the same as at 512.
- [x] Hi-Mid band (2026-11-04): on a parameter's Audio tab, Frequency Band lists Hi-Mid (Crack), in Continuous and Transient. A snare or a bright vocal moves it more than the kick does. Its tooltip gives about 2-5 kHz. The Audio Hardware scopes show Hi-Mid Band and Crack Hits, and the panel still fits at 1280x720 with the extra rows.
- [x] Band energy (2026-11-04): in Section mode, Signal lists Bass, Mid, Hi-Mid and High Energy. Each needs about 20 s of music. Hats coming in lifts High Energy alone, and the bass leaving drops Bass Energy alone. An empty band sits mid-range. Four new scopes

show them in Audio Hardware. Save and reload a preset that uses one.

- [ ] Modulation tour (2026-11-04): the button it points at is now `Transient (Hits)`, so the published video shows the old label until it is re-rendered.

- [ ] Audio slots (2026-10-28): the Audio tab shows Audio 1 and Audio 2 open, one above the other, each with a power button and trash, and no Enable button. With both off, turn on Audio 2: Audio 1 stays off and nothing collapses. Turn Audio 1 on and off: Audio 2 is untouched. Put both on the same band and change Audio 2's range: Audio 1 must not change. Trash Audio 1 while Audio 2 is on: Audio 2 stays in the lower slot. Reload the preset: both slots keep their state.

- [ ] Audio Invert (2026-10-28): on a parameter's Audio tab, an **Invert** toggle sits just above Modulation Range in all three detection modes. Put Punchy bass on Brightness with MUL and a negative Min, then invert: the picture should dim on each kick and ease back, and sit at full brightness in silence. Inverted Section Energy should rise in a breakdown. The ghost trace in the scope flips too. Save, reload and copy/paste the cell: Invert must survive. Check the button fits at 1280x720.

- [ ] Stock section responses (2026-10-28): every stock source now runs one Energy and one Drop modulator (named "breakdown ..." and "drop ..." in the parameter's list; the full set is in RELEASE_NOTES.md). Play a track with a clear breakdown and drop on a few sources of each kind and judge by eye: does the breakdown look read as the music receding (colour drains on most fractals; Isometric Voxels flattens, Thin Film calms, Nebula thins, Tunnel fogs, Mandelbox pulls back) without looking broken, and is the drop hit big enough to notice but not ugly (fly-through surges, punch-ins, Celestial shockwave, Escape Time lurch, Glitch crush)? Specific risks: Reaction-Diffusion's Regime moves in a breakdown, so the pattern may re-form as another species (wanted) or keep re-forming in normal playing (not wanted); Chladni's Frequency N drifts a little during normal playing; Kali Set's Iterations (cost) rise slightly in loud passages; Cyclic CA, Lenia and Reaction-Diffusion reseed once on the drop (Lenia no longer reseeds on hard kicks). Fluid Ink: the ink clears in a breakdown and is stirred on the drop. During steady music, nothing about any source should look different from before.

- [ ] Effect drop hits (2026-10-28): with a stock FX chain on a stock source, play into a drop. Bloom, Anamorphic Streak, Radial Blur (The Drop Weapon chain), Kaleidoscope, Pinch/Bulge and Vortex Swirl hit on the drop together with the source's own hit: judge whether the pile-up reads as one big moment or as mush, and which of the six should go back to bypassed. With an effect's main knob at zero it stays off on the drop. In a breakdown, Bloom spreads wider and Fluid Smear melts further. Switch on a bypassed one (RGB Split "drop split", VHS Glitch "drop tape wreck") and check it is worth having.
- [ ] Audio Response slider (2026-10-27, replaces Reactivity; 0-200%, saved): at 0% nothing follows the music (LFOs and beat-synced motion keep going), 100% as tuned, 200% livelier with loud passages pinned at the top; a modulator you add yourself follows it too; beat detection/BPM unaffected; the band meters show the scaled signals.
- [ ] Fractal Flame recipe (2026-10-27): load the source on a deck with music; Breathe pulses on bass, Warp follows mids, Spin sways over 32 beats, Magnify pushes on the kick, Exposure flashes (check it does not wash out or blink), Brightness lifts. Run a morph (Rand/die) and a Garden preset: the responses should not fight the morph; note that a preset with its own saved parameters replaces the recipe. Mandala recipe (2026-10-27): L1 amplitude jiggle, L2 8-beat sine, L3 16-beat sample-and-hold with 50% hold, L4 6-beat ramp; Hue Offset 1-beat cycle (check it is a smooth cycle, not strobing); Recipe Select every 32 beats, Lobes every 256 (4..~15). Judge the L depths. Batch 4 source recipes (2026-10-27: celestial_engine, chladni_cymatics, escape_time, girih_stars, gyroid_hyperspace, hyper_slice, isometric_voxels, quasicrystal, thin_film): same judging. Chladni's FrequencyM slides a fraction of a mode (check it stays a clean pattern); Hyper Slice SliceOffset sweep. Batch 3 (2026-10-26: reaction_diffusion, lenia, cyclic_ca, nebula_volume): on the sims check that the active responses never kill the pattern (reaction_diffusion Feed breathing, lenia over several minutes), and try the bypassed Reseed (drop) alternates: one reseed per hard kick, none at low Audio Response. Batch 2 (2026-10-26: mandelbulb, mandelbox, kifs, pseudo_kleinian, hyperbolic_tiling, icosa_h3): same judging as batch 1. Batch 1 (apollonian, dynamic_spiral, tunnel_scenes, kali_set, aurora_ribbons, domain_warp_fluid, voronoi_cells, wave_ripples, glitch_blocks, metaballs, halftone_matrix, video_feedback): load each on a deck with music.

Judge by eye: is the active response tasteful, are depths too high or low, do the bypassed alternates (AUD/LFO cells) turn on cleanly and look good? Note changes per source.

- [ ] FX responses, batch 1 (2026-10-27: bloom, color_levels, retro_crt, luma_displace, fluid_smear, wave_displace, mirror_sphere, kaleidoscope, feedback, gradient_map, faceted_glass, rgb_split). The starter chains do NOT carry them (chains store their own slot parameters), so add each effect to an empty slot from the FX Library, with music. With the Metaknob at zero nothing should move (Luma Displace, Fluid Smear, Wave Displace, Feedback, RGB Split load at zero); turn it up and the hits should grow with it (MUL on the Metaknob input: Bloom, Luma Displace, Wave Displace, Mirror Sphere, Faceted Glass, RGB Split). Watch for: Feedback kick push (trails jump outward; too much?), Fluid Smear flow quickening when loud (gentle enough?), Gradient Map cycling only when loud (stops in quiet passages: good or odd?), Color Levels saturation swell and Retro CRT kick flare on the Master chain (too busy for a master grade?), Kaleidoscope kick zoom. Try the bypassed alternates (AUD/LFO cells). Also: Save as Default on one of them, reload it (yours wins), Remove Saved Default (shipped response back); the Vortex Swirl transition shows its own transition response (Rotations on bass), never the effect's.

- [ ] FX responses, batch 2 (2026-10-27: 3d_elevation, anamorphic_streak, directional_blur, halftone, invert, luma_key, neon_edge, pinch_bulge, pixelate, polar_tunnel, radial_blur, thermal_scanner, vhs_glitch, video_strobe, vortex_swirl). Same method and Metaknob-at-zero check as batch 1. Watch for: Pixelate (kick makes 2-pixel blocks even at size 1, the off position: acceptable or bypass it?), Radial Blur and VHS kick hits (too violent?), Pinch/Bulge bass bulge in both directions, Polar Tunnel kick push (and its wrap seam now sits at the bottom instead of the left: check the tunnel looks balanced left to right; same for Kaleidoscope and Feedback Kaleido at 3 or 5 segments, and Chladni Cymatics with Plate Shape at Circular: no seam on the left), Thermal edge heat. Invert, Luma Key and Video Strobe have only bypassed responses: switch each on once and decide whether one should run by default. After both batches are approved: rebuild all stock FX chains so they carry the responses (agreed 2026-10-27).

- [ ] Transition responses (2026-10-27: luminous_flash, film_burn, cyber_datamosh, kinetic_zoom, liquid_displacement, noise_dissolve, vortex_swirl; linear_crossfade has none). With

music playing, rest on A, then on B, on every transition: nothing may move. Then slow manual fades (knob 1 or the Mixer slider) on each: no pop on the first frame of the fade (watch Luminous Flash and Film Burn, and the Inferno Film Burn preset, Burn Spread now 0.45), and judge the running responses mid-fade: Flash punching on the kick, Burn ember flare, Datamosh hat tears and kick colour shear, Zoom kick punch and loudness streak, Liquid bass melt and high dispersion, Dissolve kick fringe and loudness haze, Vortex bass surge and kick fringe. Too busy, too subtle? Try the bypassed alternates (Datamosh Blockiness flips every beat; Noise Scale on mids may boil). Cyber Datamosh Blockiness now reads 0-100 and looks the same as before at the old default. The stock presets (AutoVJ, Festival Elite) carry the same responses: your library still has the old copies, so delete `library/transitions/*.lsdtrans` (or Restore Factory Presets) first. A fresh stock transition shows no `*` and Save stays grey; change a value and it turns amber. Save as Default / Remove Saved Default in the Transitions row and the Mixer TRANS kebab: re-pick the transition in the same session and your values come back (no restart); Remove resets the running one to the shipped response.

9c. Random by default (2026-10-27)

Preferences: randomization on. For each source: pick it fresh from Browse (not a saved preset, which keeps its own values), press the deck die 5-10 times, then turn the deck's Rand knob slowly end to end a few times. Judge: does every roll look good, are there duds (blank, mush, too dark, broken), is the variety too timid or too wild? Note per source what to widen, narrow or drop. Ranges are in `src/main/resources/stock_defaults/sources/<id>.json` (`baseMin`/`baseMax`).

- [ ] Mechanics, on any source (KIFS is a good one): a roll moves the four source knobs on screen (and the Twister rings), and turning a knob afterwards picks up from the rolled value without a jump. Stepped values (KIFS Fractal Type, Color Mode) switch once, halfway through a Rand sweep, never flicker through the types in between. Ctrl+Z after a roll brings the previous look and knob positions back (Fractal Flame excepted: its values stay). The Initial Range slider and its dice now show on a knob-driven parameter (open its Properties); dragging the range there works.

Second pass (2026-10-27, from your first look): Cyclic CA rolls (every roll alive? a roll restarts from noise and organises within a second or two), Gyroid (slower, wider, more varied), Mandala (recipe changes on a roll), Mandelbox/Mandelbulb brightness, Fractal Flame picked from Browse (was black), Reaction Diffusion (fewer flooded solid-colour rolls). Fluid Ink: a roll changes the colour of new ink only, so the change shows over a few seconds as old ink fades; say if that is too slow.

- [ ] Batch 1: apollonian, aurora_ribbons, celestial_engine, chladni_cymatics, cyclic_ca, domain_warp_fluid, dynamic_spiral, escape_time, fluid_ink, girih_stars. Watch: Cyclic CA with many states and a high threshold may freeze (no spirals); Chladni Invert and Plate Shape full range; Escape Time Julia angle full circle (some constants are mostly empty).
- [ ] Batch 2: glitch_blocks, gyroid_hyperspace, halftone_matrix, hyperbolic_tiling, hyper_slice, icosa_h3, isometric_voxels, kali_set, kifs, lenia. Watch: Hyperbolic P/Q (the shader raises Q when the pair is not hyperbolic, so some rolls repeat); Lenia blobs dying out (kick reseeds them); Hyper Slice and Icosa camera angles.
- [ ] Batch 3: mandelbox, mandelbulb, metaballs, nebula_volume, pseudo_kleinian, quasicrystal, reaction_diffusion, thin_film, tunnel_scenes, video_feedback, voronoi_cells, wave_ripples. Watch: Mandelbox stays in the positive-scale family (crossing zero jumps); Reaction Diffusion regimes that blank out; Video Feedback whiteout or blackout from decay/zoom; Tunnel side counts.
- [ ] Effects (2026-10-27): load one effect into a deck's FX slot from the FX tab (or a stock FX chain: they carry the ranges and responses now; delete old library copies first), turn its Metaknob up so it shows, press the deck die 5-10 times. The source and the effect both change; the Metaknob never moves; Ctrl+Z puts the effect's values back too. Batch 1: 3d_elevation, anamorphic_streak, bloom, color_levels, directional_blur, faceted_glass, feedback, fluid_smear, gradient_map, halftone. Batch 2: kaleidoscope, luma_displace, mirror_sphere, neon_edge, pinch_bulge, pixelate, polar_tunnel, radial_blur. Batch 3: retro_crt, rgb_split, thermal_scanner, vhs_glitch, video_strobe, vortex_swirl, wave_displace. Watch: Bloom and Fluid Smear rolls look alike (too timid?); Feedback and Fluid Smear over several seconds after a roll (no smear-out or freeze); 3D Elevation never shrinks to a speck; Video Strobe's Flash Mode includes White Flash (is that OK as a roll?); Wave Displace

tight ripples at high frequency. Turn the deck's Rand knob end to end: effects fade with the source, modes switch once halfway. Rand All also rolls the Master FX slots.

- [ ] Transitions (2026-10-27): for each of the 8 (MIXER page), press the transition die a few times, then fade A to B by hand. Each roll looks different mid-fade (Film Burn tint, Luminous Flash colour, Kinetic Zoom strength, Linear Crossfade curve); fully on A or B the picture never shows the transition. The TRANS knobs 2-4 move with the roll; the die no longer touches inputs without a range. Rand All rolls the transition as well (a jump, not a fade). The stock transition presets roll the same ranges (delete old library copies or Restore Factory Presets first).

10. Mixer, output and app

- [ ] Deck-tile level faders: dragging doesn't snap back with a bound knob (the knob follows); the handle shows the fader's own value, the bar the live level.
- [ ] Output > Output Monitor: Automatic and a named monitor; the output reopens on the chosen screen (try Wayland + projector).
- [ ] New version available: menu-bar download icon instead of a startup popup.
- [ ] During Video Export (offline render), controller knobs and MIDI queue steps still work.
- [ ] Kill the app (`kill -9`) after changing things: preferences and session from the last minute come back.
- [ ] Web Broadcast tab hidden until Show Advanced Preferences (or already configured).
- [ ] A Shadertoy-style shader reading `audioFFT` / `iChannel0` row 0 reacts to audio.

11. Discrete parameters and units

- [ ]

- [ ] Discrete params snap while dragging; ring ticks show on DISCRETE knobs; ISF `STEP` honoured; a controller knob steps cleanly.
- [ ] Angles read in degrees; unit-range values read 0-100.

12. Flame source

- [ ] Garden stock (158 curated) loads, no black frames.
- [ ] Unit/Smooth change: several flames, no popping or wrong scale. `pre_blur` flames look right.
- [ ] Black is transparent: a flame on A over BG shows BG through the dark parts.

13. Generators

Open each: renders, animates, parameters do something. Note anything black, flickering or slow.

Heavy: - [ ] mandelbox (opens on a face, square) - [ ] kifs (static and face-on by default, Color Spread gives several colours, Twist/Morph reshape inside without turning the object) - [ ] kifs_storm (2026-11-03, the original KIFS restored): load it with music; it should tumble by itself (Tumble Speed), fill much of the frame, and feel like the old storm of cubes. Roll it a few times (Fold Angles roll the full circle). Check the RTX A2000 frame rate on a frame-filling roll and in a lattice (Repeat Spacing about 0.3, Repeat 3D on, Fly Speed about 0.15). Judge the stock responses (loudness tumble, drop spin, kick push on Fold X, kick glow, breakdown dims the crease neon) and the NEON knob (Trap Glow floods above about half) - [ ] kifs Icosahedral type (2026-11-03): Fractal Type 4; sweep Vertex 0 to 1 (icosahedron, football, icosidodecahedron, truncated dodecahedron, dodecahedron outlines); Vertex 0.2 + Color Mode 1 + Hue Offset 0.08 = copper frames over blue recessed panels; Flight Speed pops at the wrap like the octahedral type; Rand rolls type 4 and Vertex - [ ] mandelbulb - [ ] pseudo_kleinian - [ ] apollonian - [ ] escape_time - [ ] nebula_volume - [ ] reaction_diffusion (pushing Regime / trims never goes black; reseeds) - [ ] fluid_ink - [ ] lenia (Growth Center high then back: recovers)

Light wave 1: - [ ] quasicrystal - [ ] thin_film - [ ] tunnel_scenes - [ ] video_feedback - [ ] hyperbolic_tiling

Light wave 2: - [ ] cyclic_ca - [ ] metaballs - [ ] wave_ripples - [ ] aurora_ribbons - [ ] isometric_voxels - [ ] halftone_matrix - [ ] kali_set - [ ] girih_stars - [ ] glitch_blocks - [ ] voronoi_cells

- [ ] Speeds never jump (2026-10-23): after the app has run 15+ minutes, sweep each source's speed knob (Speed, Flight/Morph/Wave/Orbit/Drift Speed...) fast, and put an LFO or audio on one. The motion speeds up and slows down, never jumps or stutters. Also Dynamic Spiral Shear and Wave Amp, Harmonograph Detune, and the Wave Displace, Luma Displace, Fluid Smear, Gradient Map cycle and Video Strobe rate effects. A freshly loaded source looks as before.
- [ ] Frame time on the integrated GPU is acceptable (notes in `.planning/light-sources-notes`).
- [ ] Every-ISF binding audit (v1.0 scope): a sample of filters, every parameter binds to a knob.
- [ ] Spectrogram and Scope (2026-11-01), with music playing: Spectrogram in all four Layouts, Mirror, each Palette; notes and kicks readable; Scroll Speed sweeps smoothly with no jump; a quiet input needs Gain, a loud one doesn't burn to solid colour at the defaults. Scope: all four Traces; a held synth note stands still on Wave Line; trails zoom/turn/warp, the kick punches them out; no spokes at the centre of Spectrum Ring. Both: the die rolls varied looks; frame time fine on the integrated GPU.
- [ ] Spectrogram full axis (2026-11-01, desktop + web TV v9 CH 128): on bass-heavy music the Ring lights most of the way round, not just 11-to-1 o'clock; Tilt 0 brings back the bass-only look, Tilt 1 leans to the highs; Log Scale 0.8 gives the bass real room; no hot speckle at the top; at defaults loud music doesn't burn to solid colour and a -20 dBFS track still shows something; frame time still fine on the integrated GPU (8 taps per pixel now).
- [ ] Third-party audio visualizers (2026-11-01): put the Vidvox ISF-Files audio set (FFT Spectrogram, Radial Spectrogram, FFT Color Lines, FFT Filled Waveform, Audio Waveform Shape; `gh api repos/Vidvox/ISF-Files/...` or the scratch copies) in a user ISF folder, play music: each moves with the audio, Radial Spectrogram sweeps

round, no knob called fftImage/audio. Also Waveform Displace as an FX. Stock multipass sources (Reaction Diffusion, Lenia, Fluid Ink, Cyclic CA, Video Feedback) look as before.

14. Twister hardware

- [ ] Clock knob (13): beat-pulse LED, tempo ring, push to tap.
- [ ] Perform pages: banks cycle ab / bgpv / mixer, wrap works, LEDs follow. MIXER bank: knobs 1-4 Transitions, 9-12 Master MST.
- [ ] Native mode (`midi-fighter-twister-xt`) on a FRESH profile (delete the old saved one first). Ring styles, RGB LEDs.
- [ ] Pickup blink: Super Knob response Pickup, a waiting slot's LED strobes amber/dark until picked up (stock firmware also dims the ring).
- [ ] Bank press in the pair view walks A, B, BG, PV, Master. Knob 13 send / quick switch is the Master pair.
- [ ] Bound slot or pair view: knob 16 is the cursor (tap applies, Shift + tap queues), knobs 1-8 live; touching one moves the binding; Shift + tap on a send knob moves it to that deck. Right-middle steps the tab, right-bottom the panes (Shift + right-bottom clears the slot).
- [ ] Library send-to-deck knobs: in Library FULL a send only loads. Shift + tap on a send knob (9-13) switches pair without sending, not intermittent.
- [ ] Library view (queues under the browser), Sources tab: knob 14 moves the A/B queue highlight (first turn lands on the playing item), knob 15 the BG queue's; both columns outlined mint/rose; rings show the place. Hold + turn carries an item, releasing doesn't play it. Tap plays it now; Shift + tap removes (toast, Ctrl+Z). FX tab: the FX queues; Transitions: knob 15 dark. Hide the queues: both dark.
- [ ] Shift + tap knob 16 after turning knob 14 to the playing item: the item plays next; a second one goes after it. Without touching a queue knob: end of the A/B queue. A playlist under the tree cursor goes in whole.

- [ ] Knobs 1-8 in the Library view play Deck PV (label on the tab line); send to Deck A with knob 9: they move to A and light in A's colours; knob 13 send: Master's rows.
- [ ] Auto-preview: Shift + tap knob 12, knob 12 blinks; scroll Sources and stop: PV loads after ~0.4 s, not while scrolling. Watch the output while scrolling past heavy (gauge) sources and Flames on the laptop iGPU: stutter? Tweak PV with knobs 1-8, scroll on: it pauses with a message instead of a prompt. Leave the Library: it's off.
- [ ] Controller FX tap with nothing bound applies to the live deck (first vacant slot, last when full; Shift + tap queues).
- [ ] Link All on the Twister; Chain Link: bank change via `B3 0n 7F`.
- [ ] MIDI input now applies before the frame renders (2026-10-23): knob turns feel at least as tight as before; bank switch, browse cursor (no skipped or lost steps on entering/leaving browse), the unsaved-deck prompt answered from the Twister. Minimise the window and turn knobs: LEDs follow, and on restore nothing replays in a burst.
- [ ] The controller's knob layout is now cached between frames (2026-10-23): right after each of these, the Twister knobs drive the rows now on screen, not the old ones: change page, open and close Edit, switch a row between SRC and FX in Edit, enter and leave a pair view, focus an FX slot, and load a chain with fewer slots filled.

15. Light theme (take notes, do not guess; you decide the fixes)

Known remaining literals: dropdown selected text, ParametersRenderer fills and grey border, grey button triple in PropertiesPanel / AudioModulatorSection / ParametersTabs / ModulatorHeaderRow, MenuBar, MacroBindingEditor mini-slider, TempoSyncPanel, scope and meter text, UIThemeStyler neutrals, die button/fader in MixerPanel vs DeckControlPanel, `CvTheme`, slider literals.

- [ ] Switch to Light. Walk every view (Perform, Edit, Library, pair views, bound lists).

- [ ] New since the last pass: the badge's dimmed source text, the amber ⚠ lines in Browse tooltips, Clock row group tints, Library deck chips, the amber pickup link button, the empty-deck card, `Wet 40%` / dimmed chain names, button bevels.
- [ ] The breathing bound-slot pill behind the Library / Edit header name: label readable, pill visible.
- [ ] Note unreadable text, invisible borders, hover/press overlays.
- [ ] Dark theme unchanged after switching back.

16. Web client (if you test it)

- [ ] Preset pack (125 presets, 35 FX chains; the raymarched fractals should stay fluid on a laptop and a phone) loads and looks like the app; every web source now has a groove, hard and ambient look (2026-10-23).
- [ ] Spectrogram and Scope on the web TV (2026-11-01, local server, not yet published): with the radio playing (and once with the microphone), both move with the music like on the desktop; the spectrum isn't much hotter or dimmer than the desktop's on the same track; no console errors; a phone (Android WebView via ? embed too) shows them. Their scenes get suitable chains (Scope is `sparse`, Spectrogram `fullframe`).
- [ ] Leave the web TV running 20+ minutes: the picture no longer jitters (speeds are now integrated, so even a modulated speed is smooth).
- [ ] Mandala recipe roll (2026-11-01, TV v12): tune through the mandala scenes (web-bass/bloom/groove/hard/build-drop-mandala, stock-mandala) several times: each comes on with a different shape, often 3-lobed, and holds it for the whole scene (arms, thickness, colour still move); web-mandala-lace and -heart look as before.
- [ ] Viewer controls v13 (2026-11-01, local server, unpublished): ROLL (`D`) on a few scenes: values glide in over about a bar and land on the beat, stepped ones (colour modes, petal counts) change once on the bar line; Lenia / Reaction Diffusion don't break on a roll. Tune through ~20 curated scenes: each still looks like itself, none blank

- [ ] or blown out. MENU › AUTO ROLL 4 bars with HOLD on: keeps rolling. `B` and MENU › BACKGROUND change the background (visible on scenes with dark areas); BG CHANGES HOLD keeps it, OFF fades it out and back on fades one in. MENU › EFFECTS OFF: no FX, `F` says EFFECTS OFF, back to AUTO brings chains back. FOLLOW MUSIC OFF: no drop cut. `X` skips and moves on, `X` again undoes; MENU › SKIPPED lists, picking one tunes there, `X` restores; reload keeps skips; digits `0`-`9` tune. ROLL button fits the cabinet at 1280x720 and on a phone; the 21-row MENU scrolls with the arrows.
- [ ] Full-frame looks (Cyclic CA, Kali Set, Voronoi, Ripples, Quasicrystal...) never get trail or bloom chains, and don't wash out.
- [ ] Cyclic CA hard look reseeds on the biggest bass hits and recovers within a few seconds.
- [ ] Drop strobe chain flashes negative once per loud bass hit (no random strobe).
- [ ] With the radio playing, beat pulses land on the kicks within a few seconds of power-on and stay there through track changes.
- [ ] Looks change on the beat, about every 16 bars; the background about every 32.
- [ ] GPU tier: on the NVIDIA (or a Mac) `LSD.gpu` in the console says heavy on and Mandelbulb/Nebula looks appear; on the Intel GPU they never do.
- [ ] Leave the TV on for 15 min on a laptop and a phone: the screen never dims or locks; after power off it sleeps normally.
- [ ] Phone lock screen: shows the show and the look; play/pause powers the TV (on a tape it pauses the tape); next/previous change the look. Laptop media keys do the same.
- [ ] Install the TV from Chrome/Edge (desktop) and Add to Home Screen on a phone: it opens fullscreen with the icon; with the network off it still opens (no signal).
- [ ] `?kiosk` on a spare screen: picture only, turns on by itself (or asks for a click for sound), pointer hides.
- [ ]

- [ ] MENU on a laptop and a phone: readable, every row changes with arrows and taps, Esc closes, settings survive a reload.
- [ ] With Bluetooth headphones/speaker: TAP SYNC lands near their delay (150-250 ms) and the pulses line up with the kicks afterwards.
- [ ] Turn on your OS's reduce-motion setting: MENU shows Reduced motion AUTO (ON), no hard looks or flashes appear, changes are slow.
- [ ] A slow show (hip-hop, dub) mostly brings calm/groove looks; a fast one (techno, drum and bass) mostly hard/kick looks, but not only those.
- [ ] Set Preferences › Web Broadcast › Broadcaster name, go live: the web TV shows the LIVE title card with the name; clear the name mid-broadcast: the next viewer joining sees just LIVE.
- [ ] Branding: nameplate opens the site in a new tab (and doesn't power the TV off); ident at first power-on; ABOUT's QR code scans to liquid-lsd.greenjon.com; paste https://spaz.org/tv/ into a chat app and see the preview.
- [ ] Web TV theme and listener count (2026-11-04, v22): MENU › THEME flips dark/light at once and survives a reload with no dark flash; light is comfortable to look at with the knobs, lit LEDs (LIVE, HOLD, CHAT) and blackboard all easy to read, on a phone too; Add to Home Screen / browser bar colour follows. Under the badge, `N mutants watching TV.` matches the count in the Spaz Radio app and updates within 30 seconds (`1 mutant` when alone; blank at zero).
- [ ] Viewer controls on a real browser and a phone: CH up/down, FX, HOLD, TIME, REACT, swipe, long-press, keyboard; OSD readable; fullscreen keeps the OSD.
- [x] SCHEDULE (2026-10-31, after publishing; TV v4): the button, `G` and MENU › SCHEDULE open Spaz Radio's upcoming shows in your local time zone (header says e.g. TIMES IN PDT), the show playing now marked ON AIR, matching the Spaz Radio app's Schedule tab. Any key or a tap closes it; it scrolls with a finger on a phone without closing. The track line on screen is followed by NEXT: · . Fullscreen: the schedule fills the picture too. !!works in a new tab; a plain reload of an open tab kept the old code (button did nothing). Phone scroll not checked yet.

- [ ] Reload after a publish (2026-10-31, TV v5): with the TV open in a tab, after the next publish that changes code, one or two plain reloads show the new version in the MENU title (the first visit after v5 installs the fixed service worker).
- [ ] Web TV beat tracking (2026-11-05, TV v26, after publishing): on the radio, the beat light should stay lit most of the time on music and beat-synced motion should sit on the music. Try drum and bass and something with tempo changes. Watch for visible speed changes when the tempo moves and for the beat jumping. It takes about 5 seconds to settle on a new tempo. On a talk show the light should mostly stay off and motion should stay calm. A phone should not stutter: the estimate costs nearly twice as much now.
- [ ] Audio clock beat lock (2026-11-05, clock source Audio, Link off): play a steady track with clear kicks and watch something beat-synced, or the beat dots. After about 10 s it should sit on the kicks and stay there through the track, without needing TAP or SNAP. Press SNAP on an off-beat: after a few seconds it should keep that off-beat. Play speech: the clock should stay calm. With Downbeat: Auto, beat 1 may now behave differently.
- [ ] Web TV with the power off (2026-11-04, TV v24, after publishing): with the TV off, MENU, SCHEDULE, TAPES and `?` open and leave it off; picking a tape turns it on and plays, with sound on the first click after a fresh page load. In the menu, the wheel over a label scrolls, the wheel directly on a value changes it, and the stripes make rows easier to follow. The badge always shows the channel, and in the light theme it reads as dark text on a light window. The source badge above it follows STREAM, LIVE SHOW, TAPE and MIC (the mic needs a real browser). The menu's three pages read well, with the help line always visible, on a phone too.
- [ ] Web TV keys (2026-11-03, TV v21, after publishing): `R` rolls, `J` jumps to a random channel, `E` next FX, `F` fullscreen, `S` schedule, `U` mutes and restores the volume; `Space` holds with no tape in and pauses a tape. The `?` page reads well in its two grouped columns at your usual window size and in fullscreen.
- [ ] TAPES (2026-11-03, TV v20, after publishing), on desktop and a phone, **and iPhone Safari** (Ogg playback and seeking there are unproven): LIVE is lit on the radio, TAPES while a tape is in or the list is open; `T` or the button opens the archive; search; RANDOM

- [ ] TAPE; ON THIS DAY; play a show: the badge says TAPE and the picture follows the show; drag the waveform, `,` `.` `<` `>`, `K`; reload and RESUME returns to your place; power off and on keeps the tape; LIVE/`L` goes back to the radio; lock-screen seek works. During a real broadcast or scheduled show: the tape plays on, LIVE pulses red, `LIVE NOW` comes up once, and going back shows the broadcast's picture. The chat board shows the tape note. The button row still fits at 1280x720 and on a phone.
- [ ] CHAT blackboard (2026-10-31, after publishing; TV v6), at 1280x720 and on a phone in portrait: the board is open on a first visit beside the TV (under it on the phone), with the recent conversation and "N here: …" matching the Spaz Radio app; the X closes it and the TV grows back; a reload keeps it closed; CHAT / `C` / MENU › CHAT bring it back. Write a name, then post one line (with the user's OK, it's the real room): it shows on the phone app with a time, and the phone's reply shows on the board within a second or two, name in its chalk colour, yours in yellow. Typing `n`, `m`, `c` or Space on the board doesn't touch the TV. Close the board, have someone post: the CHAT light blinks. Close the tab: your name leaves the phone's online list. Wi-Fi off for a minute while someone posts, back on: "offline · reconnecting…", then the missed line appears once. Fullscreen shows no chat. Caveat 700 legible on the slate (else try Caveat Brush).
- [ ] While broadcasting from the desktop, the web TV shows LIVE and its controls are locked. The desktop uses the rotated relay token (Preferences > Web Broadcast); a wrong token shows [LIVE ERR].
- [ ] Pull the network while the TV plays: snow and NO SIGNAL within a few seconds; plug it back: the radio and the picture come back within ~10 s.
- [ ] On a track with a breakdown and drop, a calm look arrives in the breakdown and a hard look cuts in on the drop (not on every quiet moment).
- [ ] Auto gain on the web TV (2026-10-28): REACT starts at 100% (range 25-200%). The picture should move about as much on a quiet show as on a loud one, and a lot more than before on quiet shows (a 90 s sample of the stream measured bass about 5x livelier than the old 200% default). Judge whether 100% is right for the radio or too busy, especially the `web-*` looks. Breakdowns still bring calm looks

and drops still cut (they use the real level); pulling the network still gives snow. Reduced motion caps REACT at 60%.

- [ ] Web breakdowns (2026-10-28): in a radio breakdown the picture's bass motion goes calm and stays calm, and the calm look the autopilot brings in is not undone by the gain climbing back; the drop still cuts to a hard look. `LSD.cvState.energy` in the console shows the watcher (`section`, `holding`, `short`, `long`).
- [ ] Web section modulators (2026-10-28): the stock presets (every `stock-*.lsd` now uses `audio_energy` and `audio_drop`) breathe out in a radio breakdown and hit on the drop as on the desktop. With SYNC set, the drop hit is delayed with the sound. With reduced motion, the drop hit is softer.
- [ ] Phase 8 CI is not done yet, so nothing to check there.
- [ ] Photo gallery background (2026-11-03, TV v14): a fresh visit (or after RESET) starts with the old radio page's photos behind the scene, turning and growing slowly, a new one on the beat every few beats; BG CHANGES reads HOLD. `B` steps to the shader backgrounds and back to the gallery. First photo within a few seconds; no console errors; a phone and the Android app's WebView (once it ships the new web) keep a steady frame rate. Look out for any photo you'd rather drop (the list is the 200 earliest uploads, `web/gallery.json`, until you curate it).

16b. Audit fixes (2026-10-29)

- [ ] Copy / Move / Swap a deck "Source + FX" onto another deck: the target's FX row, Chain view and Twister knobs show the new effects and drive them; the chain dips like a chain load; a saved chain still says Save (not Save As). After a Move the source deck's chain is "Untitled".
- [ ] Macros tab: Apply to / Save from offer only Decks A/B/BG/PV and Master; the Transitions row's K1 still mirrors the crossfader.
- [ ] Clear each queue (A/B, BG, both FX queues, Transition), drop files onto one, add a playlist from its right-click menu: Ctrl+Z undoes each (the Clear toast says so).
- [ ]

- [ ] Rename a preset and edit its tags: the file keeps everything else (open it in a text editor).
- [ ] Fractal Flame with Pool or Breed: no hitch at morph boundaries; Keep and Import Flame don't hitch, and the import toast gives the real count. Put a macro on the variation choice: the combo greys out. Editor tabs look right in both themes; Skip's tooltip says Skip.
- [ ] Twister: Ctrl-C the app in native mode, the Twister leaves native mode and goes dark; unplug it while playing, the picture doesn't freeze; plug it back in, it comes back.
- [ ] Tooltips: hover the new ones (System Volume, Master BPM and presets, Library tabs, MIDI mapping columns, Broadcast buttons) and a few converted knob/slider tooltips (what / gestures / MIDI layout). Menus say "MIDI Learn (X)" / "OSC Learn (X)"; MIDI Preferences column says Control; the transition on/off checkbox no longer says Bypass; colours of the menu bar, About, Link button and Clock row group tints look unchanged (dark) and sensible (light).

16c. Ableton Link (2026-11-05)

Tested automatically on this Linux machine, between two copies of the Link library and against `aalink` in a separate process (`scripts/link_peer_check.py`). Nothing has been tried in the running app, with a real music app, on a second computer, or on Windows or macOS. Any Link app will do as the peer; Ableton Live has a free trial, and there are free phone apps.

- [ ] With the other app running, click `[ LINK ]` on the Clock row: it reads `LINK 1` in blue within a few seconds.
- [ ] Change the tempo in the other app: the BPM readout follows, and beat-synced motion stays on the other app's click.
- [ ] Is the picture ahead of or behind the other app's sound? There is no latency offset yet, so note by how much.
- [ ] While following, -/+ and TAP change the other app's tempo. SNAP does nothing visible with a peer connected.
- [ ]

Click `[ MAN ]`: it reads `LEAD 1`. The other app takes your BPM, and its bar lines up about 2 seconds later.

- [ ] Still leading, change the tempo in the other app: it goes back within about a second. Is that behavior right, or annoying?
- [ ] Click `[ AUDIO ]` with music playing: while the tracker is unlocked the other app is left alone, and Preferences > Tempo & Sync says it is waiting. Once locked, the other app follows. Does the other app's playback sound acceptable through the small corrections?
- [ ] Untick **Enable Ableton Link** while on `[ LINK ]`: the clock moves to `[ MAN ]` and the button goes dim.
- [ ] Quit with Link on: the other app's peer count drops at once, not after a timeout.
- [ ] A second computer on the same network finds the app. If it shows 0 peers, check the firewall (UDP 20808).
- [ ] Windows and macOS: the app finds the peer, and note any permission prompt.

17. Before release

- [ ] Camera-relative light: Mandelbulb, Mandelbox and KIFS: turn Rotate X/Y/Z (and let Mandelbulb's Flight Speed spin) through a full circle; the lit side stays toward you and no side goes dark. KIFS: try every start face. Icosa H3, Pseudo-Kleinian and Apollonian look as before.
- [x] `ARCHITECTURE.md` refreshed (verified against the code 2026-10-29).
- [ ] Walkthrough videos re-rendered where `scripts/tour_staleness.py` says (much of the UI they show changed).
- [ ] Website deployed (last item).
- [ ] MIDI phase 5 slice 1 (separate agent): Controller Profiles section, copy / delete / reload, validation problems, "Learned mappings" retitle.
- [ ]

Black-is-transparent sources (30 generators + Renderer separate-alpha blend): put Video Feedback and a few others (Kali Set, Lenia, Fluid Ink, Hyper Slice) on a deck over a coloured BG deck; dark areas should show the BG, bright areas cover it; Chladni / Dynamic Spiral / Icosa H3 should look as before (alpha now linear, not squared).

Notes: