上一篇教程我们讲解了分布式的基础,同时ZooKeeper的单机安装和集群搭建(配置observer节点),以及集群中每个节点的角色,接下来讲解的是

一、zoo.cfg配置文件

(一)常规的配置

tickTime=2000 zookeeper中最小的时间单位长度 (ms)

initLimit=10 follower节点启动后与leader节点完成数据同步的时间

syncLimit=5 leader节点和follower节点进行心跳检测的最大延时时间

dataDir=/tmp/zookeeper 表示zookeeper服务器存储快照文件的目录

dataLogDir 表示配置 zookeeper事务日志的存储路径,默认指定在dataDir目录下

clientPort 表示客户端和服务端建立连接的端口号: 2181

下面是一个zoo.cfg的配置文件

```
The number of milliseconds of each tick
tickTime=200
  The number of ticks that the initial
# synchronization phase can take
initLimit=10
  The number of ticks that can pass between
# sending a request and getting an acknowledgement
syncLimit=5
# the directory where the snapshot is stored.
# do not use /tmp for storage, /tmp here is just
# example sakes.
dataDir=/tmp/zookeeper

# the port at which the clients will connect
# the maximum number of client connections.
# increase this if you need to handle more clients
#maxClientCnxns=60
 Be sure to read the maintenance section of the
  administrator guide before turning on autopurge.
# http://zookeeper.apache.org/doc/current/zookeeperAdmin.html#sc_maintenance
# The number of snapshots to retain in dataDir
#autopurge.snapRetainCount=3
# Purge task interval in hours
# Set to "O" to disable auto purge feature
#autopurge.purgeInterval=1
#集群配置
server.1=192.168.190.101:2888:3881
server.2=192.168.190.102:2888:3881
server.3=192.168.190.105:2888:3881
server.4=192.168.190.104:2888:3881:observer
```

(二)高级配置

二、ZooKeeper中的一些概念

1、数据模型


zookeeper的数据模型和文件系统类似,每一个节点称为:znode. 是zookeeper中的最小数据单元。每一个znode上都可以

保存数据和挂载子节点。 从而构成一个层次化的属性结构

2、集群角色:前面已经介绍过(leader、follower、observer)

3、会话

客户端和服务器之间的一次TCP长连接



4、数据节点

持久化节点 : 节点创建后会一直存在zookeeper服务器上,直到主动删除

持久化有序节点 : 每个节点都会为它的一级子节点维护一个顺序

临时节点 : 临时节点的生命周期和客户端的会话保持一致。当客户端会话失效,该节点自

动清理

临时有序节点 : 在临时节点上多勒一个顺序性特性

5、版本

ZooKeeper的每个节点上都会存储数据,对应于每个ZNode, ZooKeeper都会维护一个叫Stat的数据结构, Stat记录了ZNode的三个数据版本,分别是:

cversion = 0 子节点的版本号

aclVersion = 0 表示acl的版本号,修改节点权限

dataVersion = 1 表示的是当前节点数据的版本号

6, watcher

zookeeper提供了分布式数据发布/订阅,zookeeper允许客户端向服务器注册一个watcher监听。当服务器端的节点触发指定事件的时候

会触发watcher。服务端会向客户端发送一个事件通知

watcher的通知是一次性,一旦触发一次通知后,该watcher就失效

7、ACL (Access Cotrol Lists)

zookeeper提供控制节点访问权限的功能,用于有效的保证zookeeper中数据的安全性。避免误操作而导致系统出现重大事故。

CREATE /READ/WRITE/DELETE/ADMIN

CREATE: 创建子节点的权限

READ: 获取节点数据和子节点列表的权限

WRITE:更新节点数据的权限 DELETE:删除子节点的权限 ADMIN:设置节点ACL权限

三、ZooKeeper的命令操作

在{ZOOKEEPER_HOME}目录,连接zkCli客户端,命令格式如下

```
1 sh bin/zkCli.sh -server ip:port
```

现在连接到本机 sh bin/zkCli.sh

```
| Troop# | T
```

键入-help查看有哪些命令

```
[zk: localhost:2181(CONNECTED) 0] -help
ZOOKeeper -server host:port cmd args
    stat path [watch]
    set path data [version]
    ls path [watch]
    delquota [-n|-b] path
    ls2 path [watch]
    setAcl path acl
    setquota -n|-b val path
    history
    redo cmdno
    printwatches on|off
    delete path [version]
    sync path
    listquota path
    rmr path
    get path [watch]
    create [-s] [-e] path data acl
    addauth scheme auth
    quit
    getAcl path
    close
    connect host:port
[zk: localhost:2181(CONNECTED) 1]
```

1、create [-s] [-e] path data acl

- -s 表示节点是否有序
- -e 表示是否为临时节点

默认情况下,是持久化节点

演示:

默认创建node节点

```
create /node1
create /node1/node1-1
create /node1/node1-2
```

```
[zk: localhost:2181(CONNECTED) 6] create /node1 123
Created /node1
[zk: localhost:2181(CONNECTED) 7] create /node1/node1-1 123
Created /node1/node1-1
[zk: localhost:2181(CONNECTED) 8] create /node1/node1-2 123
Created /node1/node1-2
[zk: localhost:2181(CONNECTED) 9]
```

创建有序节点

```
1 create -s /node2
```

```
[zk: localhost:2181(CONNECTED) 4] create -s /node2 123
Created /node20000000003
```

创建临时节点

```
1 create -e /node_tmp1
```

```
[zk: localhost:2181(CONNECTED) 0] create -e /node_tmp1 123
Created /node_tmp1
[zk: localhost:2181(CONNECTED) 1] ls /
[node20000000003, zookeeper, node_tmp1, node1]
[zk: localhost:2181(CONNECTED) 2]
```

会话关闭之后,再重新连接,发现临时节点没有了

```
[zk: localhost:2181(CONNECTED) 5] ls /
[node20000000003, zookeeper, node1]
[zk: localhost:2181(CONNECTED) 6]
```

2, get path [watch]

获得指定 path的信息

```
[zk: localhost:2181(CONNECTED) 6] get /node1
123
cZxid = 0x600000005
ctime = Sun Aug 06 12:13:31 CST 2017
mZxid = 0x600000005
mtime = Sun Aug 06 12:13:31 CST 2017
pZxid = 0x600000007
cversion = 2
dataVersion = 0
aclversion = 0
ephemeralowner = 0x0
dataLength = 3
numChildren = 2
```

3, set path data [version]

修改节点的信息 修改节点 path对应的data 乐观锁的概念 数据库里面有一个 version 字段去控制数据行的版本号

```
#修改node1的值为mic
set /node1 mic

#查看修改后的值
get /node1
```

```
[zk: localhost:2181(CONNECTED) 13] set /node1 mic
cZxid = 0x600000005
ctime = Sun Aug 06 12:13:31 CST 2017
mZxid = 0x600000012
mtime = Sun Aug 06 12:29:16 CST 2017
pZxid = 0x600000007
cversion = 2
dataVersion = 1
aclVersion = 0
ephemeralOwner = 0x0
dataLength = 3
numChildren = 2
[zk: localhost:2181(CONNECTED) 14] get /node1
mic
cZxid = 0x600000005
ctime = Sun Aug 06 12:13:31 CST 2017
mZxid = 0x600000012
mtime = Sun Aug 06 12:29:16 CST 2017
pZxid = 0x600000007
cversion = 2
dataVersion = 1
aclVersion = 0
ephemeralOwner = 0x0
dataLength = 3
numChildren = 2
[zk: localhost:2181(CONNECTED) 15]
```

4、delete path [version]

删除节点,它是从叶子节点开始删除,不能删除非空节点

```
| rumchildren = 0
| [zk: localhost:2181(CONNECTED) 18] delete /node1
| Node not empty: /node1
| [zk: localhost:2181(CONNECTED) 19]
```

```
[zk: localhost:2181(CONNECTED) 18] delete /node1
Node not empty: /node1
[zk: localhost:2181(CONNECTED) 19] ls /node1
[node1-2, node1-1]
[zk: localhost:2181(CONNECTED) 20] delete /node1/node1-1
[zk: localhost:2181(CONNECTED) 21] delete /node1/node1-2
[zk: localhost:2181(CONNECTED) 22] ls /node1
[]
[zk: localhost:2181(CONNECTED) 23] delete /node1
[zk: localhost:2181(CONNECTED) 24] ls /
[node20000000003, zookeeper]
```

四、stat信息

```
cversion = 0 子节点的版本号
aclVersion = 0 表示acl的版本号,修改节点权限
dataVersion = 1 表示的是当前节点数据的版本号

czxid 节点被创建时的事务ID
mzxid 节点最后一次被更新的事务ID
pzxid 当前节点下的子节点最后一次被修改时的事务ID

ctime = Sat Aug 05 20:48:26 CST 2017
mtime = Sat Aug 05 20:48:50 CST 2017
```

下面是一个节点的stat信息

```
cZxid = 0x500000015
ctime = Sat Aug 05 20:48:26 CST 2017
mZxid = 0x500000016
mtime = Sat Aug 05 20:48:50 CST 2017
pZxid = 0x500000015
cversion = 0
dataVersion = 1
aclVersion = 0
ephemeralOwner = 0x0 创建临时节点的时候,会有一个sessionId。 该值存储的就是这个sessionId
dataLength = 3 数据值长度
numChildren = 0 子节点数
```

五、Java操作ZooKeeper

(一) Java API的使用

1、导入jar包

2、代码演示 GitHub地址为:

(二) zkClient

(三) curator