Plugin Quick Start Guide

The plugin is an instrument that holds up to four one-shot sounds. Every note you play picks one of them at random, and each sound has its own pitch, envelope, loop, arpeggiator and effects.


Getting started

Install it

- **Windows:** move the `.vst3` folder into `C:\Program Files\Common Files\VST3`.
- **Mac:** right-click `install.command` → **Open**, and confirm the security warning.

In FL Studio, open **Options → Manage plugins → Find installed plugins**. The plugin appears under **Generators**: add it to the Channel Rack and play it from the piano roll or a keyboard.

The main screen




Area	What it does
Top left	Preset list, previous/next arrows and **Save**

Area	What it does
Top right	**master** volume, and the **sounds** / **fx** tabs
Each row (1–4)	One sound: its number, waveform, **volume**, **pitch**, **mute** and **reverse**
Buttons under a waveform	**start**, **envelope**, **glide**, **loop**, **arp**: each opens a small note with more settings
Arrows in the left margin	Layer links between sounds (see Layers)

A button under a waveform is coloured in when that feature is in use, so you can see what each sound is doing without opening anything.

Loading sounds

Drag an audio file (WAV, AIFF, FLAC, OGG) onto a waveform, from your file browser or FL's browser. You can also click an empty waveform to pick a file. Dropping several files at once fills that slot and the ones below it. The **x** in a waveform's corner removes its sound.



How notes pick a sound

Every note picks one loaded sound at random, and never the same sound twice in a row when there's a choice. The picked sound's number briefly gets a circle around it, and a moving line on its waveform shows what's playing.

C5 in FL (MIDI note 60) plays a sound at its original pitch; higher and lower notes transpose it.


Control	What it does
volume	The sound's level, in dB
pitch	Tunes the sound in semitones; it snaps to whole steps

Control	What it does
mute	Never picked on its own. It still plays as a layer if another sound links to it (see Layers)
reverse	Plays the sound backwards; the waveform flips to match

Using the knobs

Drag a knob up or down to turn it; you can grab it anywhere, including its label. Every knob can be automated in FL.


Action	Result
Hover or drag	The current value appears in a small bubble
Double-click	Resets the knob to its default
Right-click	Opens a box to type an exact value; press Enter to apply, Escape to cancel
Shift + drag (pitch knobs)	Moves freely instead of snapping to whole semitones



Typed values can include the unit (`7 st`, `-12`, `3.5`). Anything out of range is clamped to the nearest allowed value.

Start, random start and stretch

Click **start** under a waveform to choose where the sound begins and how long it lasts.




Knob	What it does
start	Skips the beginning of the sound. The skipped part is shown faded on the waveform
random	Each note starts at a random point between **start** and this far into the rest of the sound. The range shows as hatching
stretch	Makes the sound longer or shorter (25–400%) without changing its pitch. At 100% it's off, and higher notes play faster as on a classic sampler

With **stretch** away from 100%, every note lasts the same time whatever key you play, and pitch, glide and notes only change the pitch.

Envelope

Click **envelope** to shape how a sound fades in, holds and fades out. Each sound has its own envelope.



Knob	What it does
attack	Fade-in time at the start of a note
decay	Time to fall from full level to the sustain level
sustain	Level held while the key stays down
release	Fade-out time after you let go of the key

The defaults play the sound as it is while the key is held. Releasing a key starts the release, so short piano-roll notes can cut sounds off: lengthen the notes or raise **release** to hear more of the tail.

Glide and legato

Click **glide** to make a sound slide in pitch between notes. Both settings apply only to the sound they're turned on for.




Setting	What it does
glide	The sound starts at the pitch of the previous note you played and slides to the new one
time	How long the slide takes
legato	While the key that started this sound is still held, a new key bends it to the new note instead of restarting it

Legato needs overlapping notes: in the piano roll, let each note run slightly past the start of the next. With **glide** also on, the bend slides; with glide off, it jumps. Other sounds are unaffected, and every key still picks a sound as usual.

Loop

Click **loop** to keep a sound going for as long as the key is held, like the loop in FL's own sampler.




Setting	What it does
loop	Turns looping on for this sound
start	Where the loop begins
end	Where the loop ends

The sound plays normally from its start. When it reaches the loop **end**, it jumps back to the loop **start** and repeats until you release the key; then the envelope's release fades it out. The loop region shows on the waveform between two brackets, and the joins are crossfaded so they don't click.

With **random** start, a note that begins after the loop end plays to the end of the sound without looping.

Arpeggiator

Click **arp** and tick **arp on** to make a sound repeat in a rhythm while you hold a key. Each sound has its own arpeggiator, synced to FL's tempo.



Setting	What it does
rate	Step length: 1/4, 1/8, 1/8T, 1/16, 1/16T or 1/32
pattern	Note order: Up, Down, Up/Down, Random or As Played
octaves	Repeats the pattern 1 to 4 octaves up
gate	How long each step is held, as a percentage of the step
swing	Delays every second step for a shuffled feel
velocity	Fully left uses the velocity you played; otherwise every step uses this fixed velocity

The first step plays immediately and the arp stops when you release the key. Each step is a fresh hit, so random start, the envelope and glide apply to every step.


Layers

A layer link makes one sound always bring another along: whenever sound A is picked, the sounds it links to play with it.

To link two sounds

1. Click the number of the sound that should trigger the layer. It gets circled, and a hint appears at the top.
2. Click the number of the sound to add as its layer.

Click the same pair again to remove the link, or click the first number again to cancel.




Each link shows as an arrow in the left margin, from the trigger to its layer.

Rule	Example
Links work one way	With 1→2, picking 1 plays 1 and 2; picking 2 plays only 2
Link both ways to always pair them	With 1→2 and 2→1, they always play together
One sound can layer several	1→2 and 1→3 plays all three when 1 is picked
Links don't chain	With 1→2 and 2→3, picking 1 plays 1 and 2, not 3
A muted sound is "layer only"	Muted with a link pointing to it: never picked alone, but plays as a layer


Layers follow their own settings: their own start, envelope, glide, legato, arp and effects. The waveform tags a muted sound **layer only** when something links to it, or **muted** (faded) when nothing does and it won't play.

Effects (the fx tab)

Click **fx** at the top right to give each sound its own effects. Effects on one sound never touch the others.



Each row is one sound, and its signal runs left to right through four effects. Tick an effect's box to turn it on; its card fills with colour. The **mix** knob sets how much of the effect you hear, and **tweak** opens the rest of its settings. You can adjust an effect while it's off and switch it on later.



Effect	Settings
distortion	**type** (Soft, Hard, Fold, Crush), **drive**, **tone** (a low-pass filter on the distorted sound), **mix**
granular	Replays the sound as a cloud of tiny grains: **size**, **density** (grains per second), **spray** (how far back grains reach), **pitch**, **mix**
delay	**time** (synced to tempo, 1/16 to 1/2), **feedback**, **ping-pong** (echoes bounce left and right), **mix**
reverb	**size**, **damping**, **width**, **mix**

Delay and reverb tails keep ringing after a note ends.

Presets

A preset saves everything on both tabs: all four sounds, every knob and switch, the layer links and the effects.



Control	What it does
Save	Saves the current setup as a preset, named after the current preset by default
Preset list	Loads a preset. Also has **Init** (reset everything), **Open preset file...** and **Show preset folder**
< and **>**	Step through your presets

Presets live in `Documents/<plugin name>/Presets`. FL projects also remember which preset was loaded.

Presets point to your sample files rather than containing the audio. To share a kit, keep the preset and its samples in one folder (for example `MyKit/Big Kick.preset` and `MyKit/samples/kick.wav`) and send the whole folder; it works on both Windows and Mac. If a sample can't be found, that slot loads empty and everything else still loads.