Chapter 3: Processes

Chapter 3: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- Examples of IPC Systems
- Communication in Client-Server Systems

Objectives

- To introduce the notion of a process -- a program in execution, which forms the basis of all computation
- To describe the various features of processes, including scheduling, creation and termination, and communication
- To describe communication in client-server systems

Process Concept

- An operating system executes a variety of programs:
  - Batch system – jobs
  - Time-shared systems – user programs or tasks
- Textbook uses the terms *job* and *process* almost interchangeably
- Process – a program in execution; process execution must progress in sequential fashion
- A process includes:
  - program counter
  - stack
  - data section

Process in Memory



Processes

- A CPU includes (and a process on the CPU uses)
  - Program counter
  - Stack
  - Memory
- A process includes
  - program counter
  - stack
  - data section
- The computer (uniprocessor) has only one PC, stack, etc.
- With multiple processes, each process has a ***virtual*** PC, stack, etc

Process State

- How many processes can be running (in the running state) at any one time?

Process State

- As a process executes, it changes *state*
  - **new**: The process is being created
  - **running**: Instructions are being executed
  - **waiting**: The process is waiting for some event to occur
  - **ready**: The process is waiting to be assigned to a processor
  - **terminated**: The process has finished execution

Diagram of Process State



Process Control Block (PCB)

Information associated with each process

- Process state
- Program counter
- CPU registers
- CPU scheduling information
- Memory-management information
- Accounting information
- I/O status information

Process Control Block (PCB)



Process Control Block

Process management	Memory management	File management
Registers	Pointer to text segment	Root directory
Program counter	Pointer to data segment	Working directory
Program status word	Pointer to stack segment	File descriptors
Stack pointer		User ID
Process state		Group ID
Priority		
Scheduling parameters		
Process ID		
Parent process		
Process group		
Signals		
Time when process started		
CPU time used		
Children's CPU time		
Time of next alarm		

CPU Switch From Process to Process



Interrupts

- Skeleton of OS response to an interrupt

1. Hardware stacks program counter, etc.
2. Hardware loads new program counter from interrupt vector.
3. Assembly language procedure saves registers.
4. Assembly language procedure sets up new stack.
5. C interrupt service runs (typically reads and buffers input).
6. Scheduler decides which process is to run next.
7. C procedure returns to the assembly code.
8. Assembly language procedure starts up new current process.

Interrupts

- Save any registers (including PSW) that have not been saved by hardware
- Set up context (MMU, TLB, page table) for interrupt service routine
- Set up stack for ISR
- Acknowledge interrupt controller
- Copy registers from where they were saved to PCB
- Run interrupt service procedure
- Choose which process to run next
- Set up the MMU context for the next process
- Load new process's registers, including PSW
- Start running new process

Process Scheduling Queues

- **Job queue** – set of all processes in the system
- **Ready queue** – set of all processes residing in main memory, ready and waiting to execute
- **Device queues** – set of processes waiting for an I/O device
- Processes migrate among the various queues

Ready Queue And Various I/O Device Queues



Representation of Process Scheduling



Schedulers

- **Long-term scheduler** (or job scheduler) – selects which processes should be brought into the ready queue
- **Short-term scheduler** (or CPU scheduler) – selects which process should be executed next and allocates CPU

Addition of Medium Term Scheduling



Schedulers (Cont)

- Short-term scheduler is invoked very frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler is invoked very infrequently (seconds, minutes) ⇒ (may be slow)
- The long-term scheduler controls the *degree of multiprogramming*
- Processes can be described as either:
  - **I/O-bound process** – spends more time doing I/O than computations, many short CPU bursts
  - **CPU-bound process** – spends more time doing computations; few very long CPU bursts

Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
- Time dependent on hardware support

Process Creation

- **Parent** process create **children** processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via **a process identifier** (**pid**)
- Resource sharing
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution
  - Parent and children execute concurrently
  - Parent waits until children terminate

Process Creation (Cont)

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- UNIX examples
  - **fork** system call creates new process
  - **exec** system call used after a **fork** to replace the process' memory space with a new program
  - **wait** system call gets the termination status of the child
  - A child process that terminates but whose parent has not yet **wait**ed for it is called a **zombie**
  - A process terminates normally with **exit** (and abnormally with **abort** or because of certain signals)

Process Creation



C Program Forking Separate Process

```
int main()
{
pid_t  pid;
   /* fork another process */
   pid = fork();
   if (pid < 0) { /* error occurred */
     fprintf(stderr, "Fork Failed");
     exit(-1);
   }
   else if (pid == 0) { /* child process */
     execlp("/bin/ls", "ls", NULL);
   }
   else { /* parent process */
     /* parent will wait for the child to
    complete */
     wait (NULL);
     printf ("Child Complete");
     exit(0);
   }
}
```


Fork/exec counter example

- What will this do?

```
int main() (int argc, char*
    argv[])
{
    int pids[20];

    for (int i = 0; i < 20; ++i) {
       pids[i] = fork();
    }

    return 0;
}
```

- **Do not ever, under any circumstances, execute this program in a shared computing environment.**
- **If you do, and I find out about it, you will immediately receive a grade of F for P536.**

A tree of processes on a typical Solaris



Process Termination

- Process executes last statement and asks the operating system to delete it (**exit**)
  - Output data from child to parent (via **wait**)
  - Process' resources are deallocated by operating system
- Parent may terminate execution of children processes (**abort**)
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - If parent is exiting
    - Some operating system do not allow child to continue if its parent terminates
      - All children terminated - **cascading termination**

Interprocess Communication

- Processes within a system may be **independent** or **cooperating**
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience
- Cooperating processes need **interprocess communication** (**IPC**)
- Two models of IPC
  - Shared memory
  - Message passing

Communications Models



Cooperating Processes

- **Independent** process cannot affect or be affected by the execution of another process
- **Cooperating** process can affect or be affected by the execution of another process
- Advantages of process cooperation
  - Information sharing
  - Computation speed-up
  - Modularity
  - Convenience

Producer-Consumer Problem

- Paradigm for cooperating processes, *producer* process produces information that is consumed by a *consumer* process
  - *unbounded-buffer* places no practical limit on the size of the buffer
  - *bounded-buffer* assumes that there is a fixed buffer size

Bounded-Buffer – Shared-Memory Solution

- Shared data

```
#define BUFFER_SIZE 10
typedef struct {
  . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

- Solution is correct, but can only use BUFFER_SIZE-1 elements

Bounded-Buffer – Producer

```
while (true) {
   /* Produce an item */
      while (((in = (in + 1) % BUFFER SIZE
 count)  == out)
      ;   /* do nothing -- no free buffers */
    buffer[in] = item;
    in = (in + 1) % BUFFER SIZE;
  }
```


Bounded Buffer – Consumer

```
while (true) {
       while (in == out)
              ; // do nothing -- nothing
 to consume

     // remove an item from the buffer
     item = buffer[out];
     out = (out + 1) % BUFFER SIZE;
return item;
  }
```

Producer Consumer

- Give me an example

Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system – processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - **send**(*message*) – message size fixed or variable
  - **receive**(*message*)
- If *P* and *Q* wish to communicate, they need to:
  - establish a *communication link* between them
  - exchange messages via send/receive
- Implementation of communication link
  - physical (e.g., shared memory, hardware bus)
  - logical (e.g., logical properties)

Implementation Questions

- How are links established?
- Can a link be associated with more than two processes?
- How many links can there be between every pair of communicating processes?
- What is the capacity of a link?
- Is the size of a message that the link can accommodate fixed or variable?
- Is a link unidirectional or bi-directional?

Direct Communication

- Processes must name each other explicitly:
  - **send** (*P, message*) – send a message to process P
  - **receive**(*Q, message*) – receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - A link is associated with exactly one pair of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional

Indirect Communication

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional

Indirect Communication

- Operations
  - create a new mailbox
  - send and receive messages through mailbox
  - destroy a mailbox
- Primitives are defined as:

  send(*A, message*) – send a message to mailbox A

  receive(*A, message*) – receive a message from mailbox A

Indirect Communication

- Mailbox sharing
  - P_1, P_2, and P_3 share mailbox A
  - P_1, sends; P_2 and P_3 receive
  - Who gets the message?
- Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.

Synchronization

- Message passing may be either blocking or non-blocking
- **Blocking** is considered **synchronous**
  - **Blocking send** has the sender block until the message is received
  - **Blocking receive** has the receiver block until a message is available
- **Non-blocking** is considered **asynchronous**
  - **Non-blocking** send has the sender send the message and continue
  - **Non-blocking** receive has the receiver receive a valid message or null

Buffering

- Queue of messages attached to the link; implemented in one of three ways
  1. Zero capacity – 0 messages
     Sender must wait for receiver (rendezvous)
  2. Bounded capacity – finite length of *n* messages
     Sender must wait if link full
  3. Unbounded capacity – infinite length
     Sender never waits

Examples of IPC Systems - POSIX

- POSIX Shared Memory
  - Process first creates shared memory segment

```
segment id = shmget(IPC PRIVATE, size, S IRUSR | S
    IWUSR);
```

  - Process wanting access to that shared memory must attach to it

```
shared memory = (char *) shmat(id, NULL, 0);
```

  - Now the process could write to the shared memory

```
sprintf(shared memory, "Writing to shared memory");
```

  - When done a process can detach the shared memory from its address space

```
shmdt(shared memory);
```

Examples of IPC Systems - Mach

- Mach communication is message based
  - Even system calls are messages
  - Each task gets two mailboxes at creation- Kernel and Notify
  - Only three system calls needed for message transfer

```
msg_send(), msg_receive(), msg_rpc()
```

  - Mailboxes needed for commuication, created via

```
port_allocate()
```

Examples of IPC Systems – Windows XP

- Message-passing centric via local procedure call (LPC) facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels
  - Communication works as follows:
    - The client opens a handle to the subsystem's connection port object
    - The client sends a connection request
    - The server creates two private communication ports and returns the handle to one of them to the client
    - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies

Local Procedure Calls in Windows XP



Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls
- Remote Method Invocation (Java)

Sockets

- A socket is defined as an *endpoint for communication*
- Concatenation of IP address and port
- The socket **161.25.19.8:1625** refers to port **1625** on host **161.25.19.8**
- Communication consists between a pair of sockets

Socket Communication



Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
- **Stubs** – client-side proxy for the actual procedure on the server
- The client-side stub locates the server and *marshalls* the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and peforms the procedure on the server

Execution of RPC



Remote Method Invocation

- Remote Method Invocation (RMI) is a Java mechanism similar to RPCs
- RMI allows a Java program on one machine to invoke a method on a remote object



Marshalling Parameters



End of Chapter 3