

Combination of Rotation and Stratification

危国锐 (硕士研究生)

2022年3月28日





水平-无地转:
$$V_{\rm h} \cdot \nabla_{\rm h} V_{\rm h} \sim -\frac{1}{\rho} \nabla_{\rm h} p \Rightarrow \frac{U^2}{L} = \frac{\Delta P}{\rho_0 L}$$
.
竖直-层化 & 静力平衡:
$$p = \rho g H \Rightarrow \Delta P = g H \Delta \rho$$

$$N^2 = -\frac{g}{\rho} \frac{\partial \rho}{\partial z} \Rightarrow \Delta \rho = \frac{N^2 \rho_0 \Delta z}{g}$$

$$\Rightarrow \Delta P = N^2 H \rho_0 \Delta z.$$

$$U^{2} = N^{2}H\Delta z.\cdots(1)$$

$$W = \frac{\Delta z}{T} = \frac{\Delta z}{L/U} \Rightarrow \frac{W/H}{U/L} = \frac{\Delta z}{H}.\cdots(3)$$

$$U = \frac{N^{2}H\Delta z}{\Omega L}.\cdots(2)$$

Case 1-仅(竖直)层化、无地转:

(1) & (3)
$$\Rightarrow \frac{W/H}{U/L} = \frac{\Delta z}{H} = \left(\frac{U}{NH}\right)^2 =: Fr^2.$$

水平-地转流: $V_h \sim \frac{k}{\rho f} \times \nabla_h p \Rightarrow \Omega U = \frac{\Delta P}{\rho_0 L}$.

Case 2-仅地转、无层化: [1, pp.357-358]

$$\frac{W/H}{U/L} = \text{Ro} := \frac{U}{\Omega L}.$$

Case 3-(竖直)层化 + 地转:

(2) & (3)
$$\Rightarrow \frac{W/H}{U/L} = \frac{\Delta z}{H} = \frac{\Omega L U}{N^2 H^2} = \frac{Fr^2}{Ro}$$
.





FIGURE 11.5 Situation in which a stratified flow encounters an obstacle, forcing some fluid parcels to move vertically against a buoyancy force.

上图来自: [1, p.356]

[1] Cushman-Roisin, B., & Beckers, J.-M. (2011). Chapter 11 - Stratification. In B. Cushman-Roisin & J.-M. Beckers (Eds.), *International Geophysics (Vol. 101, pp. 347-364). Academic Press.* https://doi.org/10.1016/B978-0-12-088759-0.00011-0





竖直辐合(散) 与 水平辐散(合) 的量级之比

Case 1-层化为主、地转可略 (Fr ≤ 1, Ro ≫ 1)

(1) & (3)
$$\Rightarrow \frac{W/H}{U/L} = \frac{\Delta z}{H} = \left(\frac{U}{NH}\right)^2 =: Fr^2.$$

Case 2-地转为主、层化可略 (Fr ≫ 1, Ro ≤ 1)

$$\frac{W/H}{U/L} = \text{Ro} := \frac{U}{\Omega L}.$$

Case 3-(竖直)层化 + 地转 (Fr ≤ 1, Ro ≤ 1)

(2) & (3)
$$\Rightarrow \frac{W/H}{U/L} = \frac{\Delta z}{H} = \frac{\Omega L U}{N^2 H^2} = \frac{Fr^2}{Ro}$$
.

Burger number:

$$Bu := \left(\frac{Ro}{Fr}\right)^2 = \left(\frac{NH}{\Omega L}\right)^2$$

FIGURE 11.6 Recapitulation of the various scalings of the ratio of vertical convergence (divergence), W/H, to horizontal divergence (convergence), U/L, as a function of the Rossby number, $Ro = U/(\Omega L)$, and Froude number, Fr = U/(NH).

当 Fr, Ro ≤ 1, 净浮力和 科氏力比惯性力相当或 更大, 此时可用 Bu 衡量 层化相对地转的重要性:

Bu ≪ 1: 地转主导;

Bu~1: 同等重要;

Bu ≫ 1: 层化主导.

上图来自: [1, p.359]

[1] Cushman-Roisin, B., & Beckers, J.-M. (2011). Chapter 11 - Stratification. In B. Cushman-Roisin & J.-M. Beckers (Eds.), *International Geophysics (Vol. 101, pp. 347-364). Academic Press.* https://doi.org/10.1016/B978-0-12-088759-0.00011-0

谢谢!

