# Systems and Networking – Unit I

B.Sc. in Applied Computer Science and Artificial Intelligence 2022-2023

#### Gabriele Tolomei

Department of Computer Science Sapienza Università di Roma tolomei@di.uniromal.it



File System API

File System API

File creation, manipulation, protection, etc.

File System API

File creation, manipulation, protection, etc.

OS Implementation

OS internal data structures and algorithms

File System API

File creation, manipulation, protection, etc.

OS Implementation

OS internal data structures and algorithms

Physical Implementation

Second storage structure, disk scheduling algorithms

File System API

File creation, manipulation, protection, etc.

OS Implementation

OS internal data structures and algorithms


Physical Implementation


Second storage structure, disk scheduling algorithms


# Part V: Storage Management


3 categories of mass-storage devices


3 categories of mass-storage devices














13






One or more platters covered with magnetic media




One or more platters covered with magnetic media

Hard disk rigid metal



One or more platters covered with magnetic media

Hard disk rigid metal Floppy disk flexible plastic




One or more platters covered with magnetic media

Hard disk rigid metal

Floppy disk flexible plastic


Each platter has 2 working surfaces

# Magnetic Disks: Tracks and Cylinders




Each surface is divided into a number of concentric rings, called **tracks** 

#### Magnetic Disks: Tracks and Cylinders




Each surface is divided into a number of concentric rings, called **tracks** 

The set of all tracks that are the same distance from the edge of the platter is called a cylinder




Each track is further divided into sectors



Each track is further divided into sectors


Each sector usually contains 512 bytes



Each track is further divided into sectors

Each sector usually contains 512 bytes

Sectors also include a header and a trailer, and checksum information




Each track is further divided into sectors


Each sector usually contains 512 bytes

Sectors also include a header and a trailer, and checksum information

Larger sector sizes reduce the space wasted by headers and trailers, but increase internal fragmentation




Data on hard drive is read by readwrite **heads** 



Data on hard drive is read by readwrite **heads** 


Standard configuration uses one head per surface



Data on hard drive is read by readwrite **heads** 

Standard configuration uses one head per surface

Each head is placed on a separate arm




Data on hard drive is read by readwrite **heads** 


Standard configuration uses one head per surface

Each head is placed on a separate arm

Arms are controlled by a common arm assembly moving simultaneously from one cylinder to another




H = number of heads (working surfaces)



H = number of heads (working surfaces)


T = number of tracks per surface



H = number of heads (working surfaces)

T = number of tracks per surface

S = number of sectors per track




H = number of heads (working surfaces)

T = number of tracks per surface

S = number of sectors per track

B = number of bytes per sector



H = number of heads (working surfaces)


T = number of tracks per surface

S = number of sectors per track


B = number of bytes per sector



OVERALL CAPACITY




Until the end of 1980s, every track had the same number of sectors with the same number of bits



Until the end of 1980s, every track had the same number of sectors with the same number of bits


Therefore, the bit density in the inner sectors was much higher than in the outer sectors



Until the end of 1980s, every track had the same number of sectors with the same number of bits

Therefore, the bit density in the inner sectors was much higher than in the outer sectors

Disk controllers have no "intelligence"




Until the end of 1980s, every track had the same number of sectors with the same number of bits

Therefore, the bit density in the inner sectors was much higher than in the outer sectors

Disk controllers have no "intelligence"

#### Drawbacks:

- The capacity of the disk was determined by the maximum bit density a controller could handle




Until the end of 1980s, every track had the same number of sectors with the same number of bits

Therefore, the bit density in the inner sectors was much higher than in the outer sectors


Disk controllers have no "intelligence"

#### Drawbacks:

- The capacity of the disk was determined by the maximum bit density a controller could handle
- Different frequencies and timing from innermost to outermost tracks




In practice, the number of sectors per track (S) varies with the **radius** of the track on the platter



In practice, the number of sectors per track (S) varies with the **radius** of the track on the platter


The outermost track is larger and can hold more sectors than the inner ones



In practice, the number of sectors per track (S) varies with the **radius** of the track on the platter

The outermost track is larger and can hold more sectors than the inner ones

The bit density is kept almost constant




In practice, the number of sectors per track (S) varies with the **radius** of the track on the platter

The outermost track is larger and can hold more sectors than the inner ones

The bit density is kept almost constant

Smarter disk controllers allow for logical addressing of sectors rather than physical



In practice, the number of sectors per track (S) varies with the **radius** of the track on the platter


The outermost track is larger and can hold more sectors than the inner ones

The bit density is kept almost constant

Smarter disk controllers allow for logical addressing of sectors rather than physical

Zone Bit Recording (ZBR)

# Magnetic Disks: (Logical) Referencing



A physical block of data is specified by the (head, cylinder, sector) number

Disk blocks are numbered starting at the outermost cylinder, identified by 0

Note that cylinder coincides with track

• The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)

- The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)
  - Outer tracks spin faster than inner tracks (more sectors traversed in the same amount of time due to larger radius → more sectors per zone in ZBR)


- The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)
  - Outer tracks spin faster than inner tracks (more sectors traversed in the same amount of time due to larger radius → more sectors per zone in ZBR)
- Data transfer from the disk to memory is made of 3 steps:

- The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)
  - Outer tracks spin faster than inner tracks (more sectors traversed in the same amount of time due to larger radius → more sectors per zone in ZBR)
- Data transfer from the disk to memory is made of 3 steps:
  - positioning time (a.k.a., seek time or random access time)
  - rotational delay
  - transfer time

- The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)
  - Outer tracks spin faster than inner tracks (more sectors traversed in the same amount of time due to larger radius)
- Data transfer from the disk to memory is made of 3 steps:
  - positioning time (a.k.a., seek time or random access time)
  - rotational delay
  - transfer time

mechanical

- The disk rotates at constant angular speed (e.g., 7200 rpm = 120 rps)
  - Outer tracks spin **faster** than inner tracks (more sectors traversed in the same amount of time due to larger radius)
- Data transfer from the disk to memory is made of 3 steps:
  - positioning time (a.k.a., seek time or random access time)
  - rotational delay
  - transfer time



# Magnetic Disks: Positioning (Seek) Time

- The time required to move the heads to a specific track/cylinder
- Includes the time needed for the heads to settle after the move
- Depends on how fast the hardware moves the assembly arm
- Typically, the slowest step in the entire process

# Magnetic Disks: Positioning (Seek) Time

- The time required to move the heads to a specific track/cylinder
- Includes the time needed for the heads to settle after the move
- Depends on how fast the hardware moves the assembly arm
- Typically, the slowest step in the entire process

Bottleneck of overall disk data transfer

• The time required for the desired sector to rotate and come under the read-write head

- The time required for the desired sector to rotate and come under the read-write head
- Can range from 0 up to one full revolution

  - full revolution  $\rightarrow$  the sector is the one before but in the opposite direction

- The time required for the desired sector to rotate and come under the read-write head
- Can range from 0 up to one full revolution

  - full revolution  $\rightarrow$  the sector is the one before but in the opposite direction
- On average, 0.5 revolutions (r)
  - E.g., for a 7200 rpm (120 rps) disk this equals to 0.5 r/120 rps ~4 msec

- The time required for the desired sector to rotate and come under the read-write head
- Can range from 0 up to one full revolution

  - full revolution  $\rightarrow$  the sector is the one before but in the opposite direction
- On average, 0.5 revolutions (r)
  - E.g., for a 7200 rpm (120 rps) disk this equals to 0.5 r/120 rps ~4 msec

The second highest bottleneck

#### Magnetic Disks: Transfer Time

• The time required to move data (i.e., bytes) electronically from disk to memory

#### Magnetic Disks: Transfer Time

- The time required to move data (i.e., bytes) electronically from disk to memory
- This is sometimes expressed as **transfer rate** (bandwidth) in bytes per second

## Magnetic Disks: Transfer Time

- The time required to move data (i.e., bytes) electronically from disk to memory
- This is sometimes expressed as **transfer rate** (bandwidth) in bytes per second

Data Transfer Time = Seek Time + Rotational Delay + Transfer Time

Sometimes the term transfer rate is used to refer to the overall data transfer time

• Addressed as large one-dimensional arrays of logical blocks

- Addressed as large one-dimensional arrays of logical blocks
- Each logical block is the smallest unit of transfer (e.g., 512 bytes)

- Addressed as large one-dimensional arrays of logical blocks
- Each logical block is the smallest unit of transfer (e.g., 5 1 2 bytes)
- The array of blocks is mapped onto disk sectors sequentially

- Addressed as large one-dimensional arrays of logical blocks
- Each logical block is the smallest unit of transfer (e.g., 5 1 2 bytes)
- The array of blocks is mapped onto disk sectors sequentially
- Sector 0 is the first sector of the first track of the outermost cylinder
  - The mapping proceeds in order through that track
  - Then through the rest of tracks in the same cylinder
  - Then through other cylinders (from the outermost to innermost)

• Disk heads "fly" over the surface on a very thin cushion of air

- Disk heads "fly" over the surface on a very thin cushion of air
- If they accidentally contact the disk then a head crash occurs

- Disk heads "fly" over the surface on a very thin cushion of air
- If they accidentally contact the disk then a head crash occurs
- Head crash may permanently damage the disk or even destroy it

- Disk heads "fly" over the surface on a very thin cushion of air
- If they accidentally contact the disk then a head crash occurs
- Head crash may permanently damage the disk or even destroy it
- To avoid such a risk, disk heads are "parked" when the computer is turned off

- Disk heads "fly" over the surface on a very thin cushion of air
- If they accidentally contact the disk then a head crash occurs
- Head crash may permanently damage the disk or even destroy it
- To avoid such a risk, disk heads are "parked" when the computer is turned off
- Parking heads means to move them off the disk or to an area where no data is stored

#### Magnetic Disks: Interfaces

- Hard drives may be removable as floppy disks, and some are even hotswappable
  - they can be removed while the computer is running
- Disk drives are connected to the computer via the I/O bus
- Some of the common interface formats include:
  - Enhanced Integrated Drive Electronics (EIDE);
  - Advanced Technology Attachment (ATA) and Serial ATA (SATA);
  - Universal Serial Bus (USB);
  - Fiber Channel (FC);
  - Small Computer Systems Interface (SCSI)

• The host controller is at the computer's end of the I/O bus

- The host controller is at the computer's end of the I/O bus
- The disk controller is built into the disk itself

- The host controller is at the computer's end of the I/O bus
- The disk controller is built into the disk itself
- The CPU issues commands to the host controller (typically via memory-mapped I/O ports)

- The host controller is at the computer's end of the I/O bus
- The disk controller is built into the disk itself
- The CPU issues commands to the host controller (typically via memory-mapped I/O ports)
- Data is transferred between the magnetic surface and onboard cache by the disk controller

- The host controller is at the computer's end of the I/O bus
- The disk controller is built into the disk itself
- The CPU issues commands to the host controller (typically via memory-mapped I/O ports)
- Data is transferred between the magnetic surface and onboard cache by the disk controller
- Finally, data is transferred from that cache to the host controller and the motherboard memory at electronic speeds

12/21/22

74

- Mechanical components of magnetic disks cause bottleneck
  - Seek Time
  - Rotational Delay

- Mechanical components of magnetic disks cause bottleneck
  - Seek Time
  - Rotational Delay
- To minimize data transfer time from disk we need to minimize those

- Mechanical components of magnetic disks cause bottleneck
  - Seek Time
  - Rotational Delay
- To minimize data transfer time from disk we need to minimize those
- How?
  - Smaller disks -> lower seek time, since arms have to travel smaller distance
  - Fast-spinning disks → lower rotational delay

- Mechanical components of magnetic disks cause bottleneck
  - Seek Time
  - Rotational Delay
- To minimize data transfer time from disk we need to minimize those
- How?
  - Smaller disks -> lower seek time, since arms have to travel smaller distance
  - Fast-spinning disks → lower rotational delay

Hardware Optimization

- How can the OS help minimize data transfer time?
- Schedule disk operations so as to minimize head movement
- Lay out data on disk so that related data are located on close tracks
- Place commonly-used data on a specific portion of the disk
- Pick carefully the block size contained on each sector:
  - Too small -> more seeks are needed to transfer the same amount of data
  - Too large → more internal fragmentation and space wasted

## Summary

- Disks are slow devices compared to CPUs (and main memory)
- Manage those device efficiently is crucial
- Minimize seek and rotational delay on magnetic disks
- HW optimizations are limited  $\rightarrow$  OS needs to take the lead here!