## Systems and Networking I

Applied Computer Science and Artificial Intelligence 2024–2025



Dipartimento di Informatica Sapienza Università di Roma

tolomei@di.uniroma1.it



#### Problems Seen So Far

- Contiguous allocation
  - Hard to grow or shrink process memory
- Fragmentation
  - Frequent compaction needed
- Process entirely loaded
  - Swapping helps but it may be too inefficient

• A memory management scheme that addresses the problems above

- A memory management scheme that addresses the problems above
- The logical address space of a process is still **contiguous** but it is divided into **fixed-size blocks**, called **pages**

- A memory management scheme that addresses the problems above
- The logical address space of a process is still contiguous but it is divided into fixed-size blocks, called pages
- Contiguous allocation is no longer required as logical pages can be mapped to non-contiguous physical frames


- A memory management scheme that addresses the problems above
- The logical address space of a process is still contiguous but it is divided into fixed-size blocks, called pages
- Contiguous allocation is no longer required as logical pages can be mapped to non-contiguous physical frames
- External fragmentation is eliminated because pages have fixed size
  - Internal fragmentation may still occur though

- A memory management scheme that addresses the problems above
- The logical address space of a process is still contiguous but it is divided into fixed-size blocks, called pages
- Contiguous allocation is no longer required as logical pages can be mapped to non-contiguous physical frames
- External fragmentation is eliminated because pages have fixed size
  - Internal fragmentation may still occur though

#### 90/10 Rule

Processes spend 90% of their time accessing only 10% of their allocated memory space

## Paging: The Big Picture



Logical/Virtual Address Space of process A

Physical Memory Paging: The Big Picture frame O OS OS frame 1 page 0  $A_0$ frame 2  $A_4$ page 1  $A_1$ frame 3 page 2  $A_2$ frame 4 page 3  $A_3$  $A_1$ frame 5 page 4  $A_4$ frame 6 page 5  $A_5$ frame 7  $A_2$ Logical/Virtual Address Space frame 8  $A_{O}$ of process A frame 9  $A_3$ frame 10  $A_5$ 12/03/2024

# Basic OS Responsibilities for Paging

- The OS has 2 main responsibilities:
  - mapping between logical pages and physical frames
  - translating logical addresses to physical addresses


# Basic OS Responsibilities for Paging


- The OS has 2 main responsibilities:
  - mapping between logical pages and physical frames
  - translating logical addresses to physical addresses
- All of this must be done efficiently!
  - Remember, memory addresses are referenced all the time

# Basic OS Responsibilities for Paging

- The OS has 2 main responsibilities:
  - mapping between logical pages and physical frames
  - translating logical addresses to physical addresses
- All of this must be done efficiently!
  - Remember, memory addresses are referenced all the time
- OS needs dedicated support for doing it → Page
   Table

## Page Table: Mapping Pages to Frames





## Page Table: Mapping Pages to Frames

Lookup table to retrieve what frame a page is stored in

| Ao             |
|----------------|
| $A_1$          |
| $A_2$          |
| A <sub>3</sub> |
| A <sub>4</sub> |
| A <sub>5</sub> |
|                |

| Page | Frame |
|------|-------|
| 0    | 8     |
| 1    | 5     |
| 2    | 7     |
| 3    | 9     |
| 4    | 2     |
| 5    | 10    |

| OS             | 0      |
|----------------|--------|
| OS             | 1      |
| A <sub>4</sub> | 2      |
|                | 3<br>4 |
|                | 4      |
| $A_1$          | 5      |
|                | 6      |
| A <sub>2</sub> | 7      |
| A <sub>O</sub> | 8      |
| $A_3$          | 9      |
| A <sub>5</sub> | 10     |
|                |        |

## Page Table: Mapping Pages to Frames

Lookup table to retrieve what frame a page is stored in

| Ο | A <sub>O</sub> |
|---|----------------|
| 1 | $A_1$          |
| 2 | A <sub>2</sub> |
| 3 | $A_3$          |
| 4 | A <sub>4</sub> |
| 5 | A <sub>5</sub> |

| Page | Frame |
|------|-------|
| 0    | 8     |
| 1    | 5     |
| 2    | 7     |
| 3    | 9     |
| 4    | 2     |
| 5    | 10    |

| OS             | 0  |
|----------------|----|
| OS             | 1  |
| $A_4$          | 2  |
|                | 3  |
|                | 4  |
| $A_1$          | 5  |
|                | 6  |
| A <sub>2</sub> | 7  |
| A <sub>O</sub> | 8  |
| $A_3$          | 9  |
| A <sub>5</sub> | 10 |
|                |    |

We have assumed all pages of a process are mapped to physical frames, but this is not always the case


 Processes use virtual (logical) addresses to refer to memory (not page number!)

- Processes use virtual (logical) addresses to refer to memory (not page number!)
- Virtual (logical) address space is still contiguous starting from O

- Processes use virtual (logical) addresses to refer to memory (not page number!)
- Virtual (logical) address space is still contiguous starting from O
- Page table must ultimately translate virtual address to physical address


#### virtual address consists of 2 parts:

- p: page number where the address resides
- offset: relative from the beginning of the page



#### virtual address consists of 2 parts:


- p: page number where the address resides
- offset: relative from the beginning of the page



Page Table 20

#### virtual address consists of 2 parts:


- p: page number where the address resides
- offset: relative from the beginning of the page




Page Table 21

#### virtual address consists of 2 parts:


- p: page number where the address resides
- offset: relative from the beginning of the page



22



## Page Table: Example of Address Translation



### Paging as Dynamic Relocation

- Paging is an advanced form of dynamic relocation
- Each virtual address is bound by the page table to a physical address
- Page table can be seen just as a set of base (relocation)
   registers, one for each frame
- Mapping is invisible to the user process: the OS maintains the page table and translation happens in hardware (via the MMU)
- Protection is provided similarly to dynamic relocation (limit register)

How does MMU use page table to translate a virtual address **x** into a physical address **y**?

How does MMU use page table to translate a virtual address **x** into a physical address **y**?

1. Get the page number (**p**) and the **offset** where the virtual address **x** resides

How does MMU use page table to translate a virtual address **x** into a physical address **y**?

- 1. Get the page number (**p**) and the **offset** where the virtual address **x** resides
- 2. Use **p** to index into the page table to retrieve the frame number **f**

How does MMU use page table to translate a virtual address **x** into a physical address **y**?

- 1. Get the page number (**p**) and the **offset** where the virtual address **x** resides
- 2. Use **p** to index into the page table to retrieve the frame number **f**
- 3. Combine **f** with **offset** to obtain the physical address **y**

Suppose we have **50B** of physical memory available for user processes

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

p = x div S

page number

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

$$p = x div S$$

page number

$$p = 27 \text{ div } 10 = 2$$

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

$$p = x div S$$

page number

$$p = 27 \text{ div } 10 = 2$$

offset

#### Paging: Get p and offset from x

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

$$p = x div S$$

page number

$$p = 27 \text{ div } 10 = 2$$

offset

offset = 
$$27 \mod 10 = 7$$

#### Paging: Get p and offset from x

Suppose we have **50B** of physical memory available for user processes

Assume we use paging with page (frame) size S = 10B

Each process can generate virtual addresses in the range [0, 49]

Suppose a process generates virtual address x = 27

$$p = x div S$$

page number

offset

$$p = 27 \text{ div } 10 = 2$$

12/03/202

offset = 
$$27 \mod 10 = 7$$

Address translation requires a div and a mod operation

 Page/frame numbers and page/frame sizes are determined by the architecture

- Page/frame numbers and page/frame sizes are determined by the architecture
- Page/frame sizes are typically a **power of 2**, ranging between 512B and 8192B (i.e., 8KiB)

- Page/frame numbers and page/frame sizes are determined by the architecture
- Page/frame sizes are typically a **power of 2**, ranging between 512B and 8192B (i.e., 8KiB)
- Powers of 2 make the translation from virtual to physical address easy (i.e., no need for **div** and **mod**)

- Page/frame numbers and page/frame sizes are determined by the architecture
- Page/frame sizes are typically a **power of 2**, ranging between 512B and 8192B (i.e., 8KiB)
- Powers of 2 make the translation from virtual to physical address easy (i.e., no need for **div** and **mod**)



• Virtual address is made of m bits


- Virtual address is made of m bits
  - Then, virtual address space (i.e., the set of bytes addressable by each user process) is  $2^m$  long, and ranges between  $[0, 2^m-1]$

- Virtual address is made of m bits
  - Then, virtual address space (i.e., the set of bytes addressable by each user process) is  $2^m$  long, and ranges between  $[0, 2^m-1]$
- Assume page (frame) size is 2<sup>n</sup>, n < m</li>


- Virtual address is made of m bits
  - Then, virtual address space (i.e., the set of bytes addressable by each user process) is  $2^m$  long, and ranges between  $[0, 2^m-1]$
- Assume page (frame) size is 2<sup>n</sup>, n < m</li>
- The higher m-n bits of the virtual address indicates the page number


- Virtual address is made of m bits
  - Then, virtual address space (i.e., the set of bytes addressable by each user process) is  $2^m$  long, and ranges between  $[0, 2^m-1]$
- Assume page (frame) size is 2<sup>n</sup>, n < m</li>
- The higher m-n bits of the virtual address indicates the page number
- The low order n bits represent the offset


12/03/2024 47




#### page number









- Typical values of virtual address size is m = 32 or 64 bits
  - The virtual address space is  $2^{32} = 4GiB$  or  $2^{64} = 16EiB$

- Typical values of virtual address size is m = 32 or 64 bits
  - The virtual address space is  $2^{32} = 4GiB$  or  $2^{64} = 16EiB$
- Typical values of page/frame sizes is n = 12 bits
  - Each page/frame is  $2^{12} = 4KiB$

- Typical values of virtual address size is m = 32 or 64 bits
  - The virtual address space is  $2^{32} = 4GiB$  or  $2^{64} = 16EiB$
- Typical values of page/frame sizes is n = 12 bits
  - Each page/frame is  $2^{12} = 4KiB$
- Assuming m = 32 bits, there are  $2^{m-n} = 2^{20} = ^1M$  pages/frames
  - The page table has  $2^{20}$  entries (i.e., one for each page/frame)

Suppose we have a virtual memory and a physical memory, both of size M = 1024B (1KiB)

#### Q1

How many bits are needed for a virtual/physical address (assuming single-byte addressing)

Suppose we have a virtual memory and a physical memory, both of size M = 1024B (1KiB)

#### Q1

How many bits are needed for a virtual/physical address (assuming single-byte addressing)

#### R1

10 bits to address M = 1024 bytes (both for virtual and physical address)

12/03/2024 57

Now, assume we use paging with page/frame size S = 16B

#### Q2

How big is the page table? (i.e., how many pages/entries does it have to index?)

Now, assume we use paging with page/frame size S = 16B

#### Q2

How big is the page table? (i.e., how many pages/entries does it have to index?)

#### R2

T = M / S = 1024 memory bytes / 16 bytes per page = 64 pages

Q3

What is p and offset (i.e., how many bits for p and offset?)

#### Q3

What is p and offset (i.e., how many bits for p and offset?)

#### **R3**

Our logical address is made of m = 10 bits

n = 4 bits are used to represent the offset, as each page/frame is S

= 16 bytes

m-n = 6 bits are used to represent page number p, as there are T =

64 pages

12/03/2024 61

Q4

Translate the virtual address x = 42, assuming the following page table

| page | frame |
|------|-------|
| 0    | 12    |
| 1    | 5     |
| 2    | 37    |
| 3    | Ο     |
|      |       |
| 63   | 29    |

Q4

Translate the virtual address x = 42, assuming the following page table

| page | frame |
|------|-------|
| 0    | 12    |
| 1    | 5     |
| 2    | 37    |
| 3    | 0     |
| •••  | ••    |
| 63   | 29    |

R4

p = x div S = 42 div 16 = 2

Q4

Translate the virtual address x = 42, assuming the following page table

| page | frame |  |
|------|-------|--|
| 0    | 12    |  |
| 1    | 5     |  |
| 2    | 37    |  |
| 3    | 0     |  |
|      |       |  |
| 63   | 29    |  |

R4

p = x div S = 42 div 16 = 2

Q4

Translate the virtual address x = 42, assuming the following page table

| page | frame |
|------|-------|
| 0    | 12    |
| 1    | 5     |
| 2    | 37    |
| 3    | 0     |
|      |       |
| 63   | 29    |

R4

$$p = x \text{ div } S = 42 \text{ div } 16 = 2$$
offset = x mod  $S = 42 \text{ mod } 16 = 10$ 
10th byte from the beginning of frame 37

Suppose we still have a virtual memory and a physical memory, both of size M = 1024B

Suppose we still have a virtual memory and a physical memory, both of size M = 1024B

Modern computers however operate natively on multiple of bytes (i.e., words) rather than single-byte. Typical values of word length is: 16, 32 or 64 bits.

If we assume 32-bit architecture (i.e., word = 32 bits = 4 bytes), virtual addresses refer to words instead of bytes

Suppose we still have a virtual memory and a physical memory, both of size M = 1024B

Modern computers however operate natively on multiple of bytes (i.e., words) rather than single-byte. Typical values of word length is: 16, 32 or 64 bits.

If we assume 32-bit architecture (i.e., word = 32 bits = 4 bytes), virtual addresses refer to words instead of bytes

#### Q1

How many bits are therefore needed to address the number of words available on M?

Suppose we still have a virtual memory and a physical memory, both of size M = 1024B

Modern computers however operate natively on multiple of bytes (i.e., words) rather than single-byte. Typical values of word length is: 16, 32 or 64 bits.

If we assume 32-bit architecture (i.e., word = 32 bits = 4 bytes), virtual addresses refer to words instead of bytes

#### Q1

How many bits are therefore needed to address the number of words available on M?

#### R1

8 bits to address M = 1024/4 = 256 4-byte words

12/03/2024 69

Now, assume we still use paging with page/frame size S = 16B

#### Q2

How big is the page table? (i.e., how many pages/entries does it have to index?)

Now, assume we still use paging with page/frame size S = 16B

#### Q2

How big is the page table? (i.e., how many pages/entries does it have to index?)

#### R2

T = M / S = 1024 memory bytes / 16 bytes per page = 64 pages

12/03/2024 71

Q3

What is p and offset (i.e., how many bits for p and offset?)

#### Q3

What is p and offset (i.e., how many bits for p and offset?)

#### **R3**

```
Our logical address is now made of m=8 bits n=2 bits are used to represent the offset, as each page/frame is: S=16 bytes = 4*4-byte words m-n=6 bits are used to represent page number p, as there are still T=64 pages
```

Q4

Translate the virtual address x = 7, assuming the following page table

| page | frame |
|------|-------|
| 0    | 12    |
| 1    | 5     |
| 2    | 37    |
| 3    | Ο     |
|      |       |
| 63   | 29    |

Q4

Translate the virtual address x = 7, assuming the following page table

| page | frame |  |  |
|------|-------|--|--|
| 0    | 12    |  |  |
| 1    | 5     |  |  |
| 2    | 37    |  |  |
| 3    | 0     |  |  |
|      |       |  |  |
| 63   | 29    |  |  |

Remember: now virtual address refers to a 4-byte word!

12/03/2024 75

Q4

Translate the virtual address x = 7, assuming the following page table

|   |  | page | frame |   |  |  |
|---|--|------|-------|---|--|--|
|   |  | 0    | 12    | _ |  |  |
|   |  | 1    | 5     |   |  |  |
|   | 1  | 2    | 37    |   |  |  |
| S = 16 bytes = 4 * 4-byte                     |  | 3    | 0     |   |  |  |
| words   |  |      |       |   |  |  |
| Must be expressed in terms of number of words |  | 63   | 29    |   |  |  |
|   | R4   |      |       |   |  |  |
| P   | $\mathbf{p} = \mathbf{x} \operatorname{div} \mathbf{S} = 7 \operatorname{div} 4 = 1$ |      |       |   |  |  |

Q4

Translate the virtual address x = 7, assuming the following page table

| page | frame |  |
|------|-------|--|
| 0    | 12    |  |
| 1    | 5     |  |
| 2    | 37    |  |
| 3    | Ο     |  |
| ***  |       |  |
| 63   | 29    |  |

R4

$$p = x \text{ div } S = 7 \text{ div } 4 = 1$$
offset =  $x \text{ mod } S = 7 \text{ mod } 4 = 3$ 
3rd word from the beginning of frame 5

• A user process generates (virtual) memory addresses almost constantly through the CPU

- A user process generates (virtual) memory addresses almost constantly through the CPU
- Every time a user process references a virtual memory address this must be translated to a physical one

- A user process generates (virtual) memory addresses almost constantly through the CPU
- Every time a user process references a virtual memory address this must be translated to a physical one
- To do so, the MMU must access the page table

• Where should the page table be stored, then?

- Where should the page table be stored, then?
  - Registers → PRO: very fast CON: very expensive and limited

- Where should the page table be stored, then?
  - Registers → PRO: very fast CON: very expensive and limited
  - Main Memory → PRO: highest capacity CON: quite slow (every memory translation requires one extra memory access!)

- Where should the page table be stored, then?
  - Registers → PRO: very fast CON: very expensive and limited
  - Main Memory → PRO: highest capacity CON: quite slow (every memory translation requires one extra memory access!)
- Trade-off solution: Translation Look-aside Buffer (TLB), namely a cache!

 All memory accesses are equivalent: the memory hardware doesn't know what a particular part of memory is being used for

- All memory accesses are equivalent: the memory hardware doesn't know what a particular part of memory is being used for
- CPU can only access its registers and main memory (any access to other devices, e.g., hard drive, requires data to be moved into main memory first)

- All memory accesses are equivalent: the memory hardware doesn't know what a particular part of memory is being used for
- CPU can only access its registers and main memory (any access to other devices, e.g., hard drive, requires data to be moved into main memory first)
- Access to registers is very fast, generally one clock cycle

- All memory accesses are equivalent: the memory hardware doesn't know what a particular part of memory is being used for
- CPU can only access its registers and main memory (any access to other devices, e.g., hard drive, requires data to be moved into main memory first)
- Access to registers is very fast, generally one clock cycle
- Access to main memory is comparatively slow, and may take several clock cycles to complete

• Bridge the gap between fast registers and slower main memory

- Bridge the gap between fast registers and slower main memory
- Cache Memory: on-chip (thereby, fast!) intermediary memory built into most modern CPUs

- Bridge the gap between fast registers and slower main memory
- Cache Memory: on-chip (thereby, fast!) intermediary memory built into most modern CPUs
- Several chunks of memory transferred from main memory to the cache

- Bridge the gap between fast registers and slower main memory
- Cache Memory: on-chip (thereby, fast!) intermediary memory built into most modern CPUs
- Several chunks of memory transferred from main memory to the cache
- Access individual memory locations one at a time from the cache rather than from memory directly


• Essentially, a very fast L1-cache


- Essentially, a very fast L1-cache
- Fully-associative memory that stores page numbers (keys) and frame numbers (values) where the former are stored


- Essentially, a very fast L1-cache
- Fully-associative memory that stores page numbers (keys) and frame numbers (values) where the former are stored
- Memory accesses obey to the "locality" principle (memory references are often "close" to each other)


- Essentially, a very fast L1-cache
- Fully-associative memory that stores page numbers (keys) and frame numbers (values) where the former are stored
- Memory accesses obey to the "locality" principle (memory references are often "close" to each other)
- Locality still holds for address translation


- Essentially, a very fast L1-cache
- Fully-associative memory that stores page numbers (keys) and frame numbers (values) where the former are stored
- Memory accesses obey to the "locality" principle (memory references are often "close" to each other)
- Locality still holds for address translation
- Typical TLB sizes range from 8 to 2048 entries




















 TLB is a piece of hardware that is shared across all the processes

- TLB is a piece of hardware that is shared across all the processes
- The same page number can be mapped to different frame number depending on the process running

- TLB is a piece of hardware that is shared across all the processes
- The same page number can be mapped to different frame number depending on the process running
- We must ensure the TLB content is up-to-date w.r.t.
   the currently running process

### Translation Look-aside Buffer (TLB)

How to deal with multiple process and a single TLB?

### Translation Look-aside Buffer (TLB)

How to deal with multiple process and a single TLB?

#### 2 setups:

 basic: at each context switch the content of the TLB is fully flushed and cleaned (cold-start → the first accesses will generate all TLB misses)

### Translation Look-aside Buffer (TLB)

How to deal with multiple process and a single TLB?

#### 2 setups:

- basic: at each context switch the content of the TLB is fully flushed and cleaned (cold-start → the first accesses will generate all TLB misses)
- advanced: TLB entries dumped and restored within the PCB or adding a so-called process context ID (PCID) to each entry (the CPU will use a TLB entry iff the PCID of that entry corresponds to the ID of the running process)

```
t_{MA} = physical memory access time t_{TLB} = lookup time on the TLB cache (NOTE: t_{TLB} \ll t_{MA}) p = probability of TLB cache hit (i.e., hit\ ratio) T_{MA} = total time required to actually get to physical memory each time a virtual address is referenced
```

```
t_{MA} = physical memory access time t_{TLB} = lookup time on the TLB cache (NOTE: t_{TLB} \ll t_{MA}) p = probability of TLB cache hit (i.e., hit\ ratio) T_{MA} = total time required to actually get to physical memory each time a virtual address is referenced
```

without TLB (i.e., Page Table full in memory)

```
t_{MA} = physical memory access time t_{TLB} = lookup time on the TLB cache (NOTE: t_{TLB} \ll t_{MA}) p = probability of TLB cache hit (i.e., hit\ ratio) T_{MA} = total time required to actually get to physical memory each time a virtual address is referenced
```

without TLB

(i.e., Page Table full in memory)

$$T_{MA} = 2 * t_{MA}$$

 $t_{MA}$  = physical memory access time  $t_{TLB}$  = lookup time on the TLB cache (NOTE:  $t_{TLB} \ll t_{MA}$ ) p = probability of TLB cache hit (i.e., hit ratio)

 $T_{MA}$  = total time required to actually get to physical memory each time a virtual address is referenced

without TLB (i.e., Page Table full in memory)

 $T_{MA} = 2 * t_{MA}$ 

with TLB

 $t_{MA}$  = physical memory access time  $t_{TLB}$  = lookup time on the TLB cache (NOTE:  $t_{TLB} \ll t_{MA}$ ) p = probability of TLB cache hit (i.e.,  $hit\ ratio$ )  $T_{MA}$  = total time required to actually get to physical memory each time a virtual address is referenced

without TLB (i.e., Page Table full in memory)

 $T_{MA} = 2 * t_{MA}$ 

#### with TLB

$$T_{MA} = p*(\underbrace{t_{MA} + t_{TLB}}) + (1-p)*\underbrace{(2*t_{MA} + t_{TLB})}_{\text{TLB miss}}$$

 $t_{MA}$  = physical memory access time  $t_{TLB}$  = lookup time on the TLB cache (NOTE:  $t_{TLB} \ll t_{MA}$ ) p = probability of TLB cache hit (i.e.,  $hit\ ratio$ )

 $T_{MA}$  = total time required to actually get to physical memory each time a virtual address is referenced

without TLB (i.e., Page Table full in memory)

$$T_{MA} = 2 * t_{MA}$$

#### with TLB

$$T_{MA} = p*(\underbrace{t_{MA} + t_{TLB}}) + (1-p)*\underbrace{(2*t_{MA} + t_{TLB})}_{\text{TLB miss}}$$

The larger the TLB the higher the probability p of hit ratio, thereby decreasing the average memory access cost

 The page table can also help to protect processes from accessing memory they shouldn't

- The page table can also help to protect processes from accessing memory they shouldn't
- A bit or bits can be added to the page table to classify a page as read-write, read-only, read-write-execute, or combination of those


- The page table can also help to protect processes from accessing memory they shouldn't
- A bit or bits can be added to the page table to classify a page as read-write, read-only, read-write-execute, or combination of those
- Each memory reference can be checked to ensure it is accessing the memory in the appropriate mode

- The page table can also help to protect processes from accessing memory they shouldn't
- A bit or bits can be added to the page table to classify a page as read-write, read-only, read-write-execute, or combination of those
- Each memory reference can be checked to ensure it is accessing the memory in the appropriate mode
- Valid/invalid bits can be added to "mask off" entries in the page table that are not in use by the current process


• Valid/Invalid bits cannot block all illegal memory accesses, due to the internal fragmentation

- Valid/Invalid bits cannot block all illegal memory accesses, due to the internal fragmentation
- Many processes do not use all of the page table entries available, particularly in modern systems with very large potential page tables

- Valid/Invalid bits cannot block all illegal memory accesses, due to the internal fragmentation
- Many processes do not use all of the page table entries available, particularly in modern systems with very large potential page tables
- Some systems use a page-table length register (PTLR) to specify the length of the page table



valid/invalid bits can be
used to flush TLB entries
upon context switch if
 basic setup is used



valid/invalid bits can be
used to flush TLB entries
upon context switch if
 basic setup is used

any entry whose invalid bit is set will be discarded (and updated)

1. Process requests for k pages

- 1. Process requests for k pages
- 2. If *k* frames are free then allocate those to the process, otherwise free frames no longer needed (swapping-out)

- 1. Process requests for k pages
- 2. If *k* frames are free then allocate those to the process, otherwise free frames no longer needed (swapping-out)
- 3. OS puts each page into a frame and sets the corresponding mapping into the page table (in main memory)

- 1. Process requests for k pages
- 2. If *k* frames are free then allocate those to the process, otherwise free frames no longer needed (swapping-out)
- 3. OS puts each page into a frame and sets the corresponding mapping into the page table (in main memory)
- 4. OS marks all previous TLB entries as invalid (i.e., flushes the cache) or restores TLB entries from saved PCB

- 1. Process requests for k pages
- 2. If *k* frames are free then allocate those to the process, otherwise free frames no longer needed (swapping-out)
- 3. OS puts each page into a frame and sets the corresponding mapping into the page table (in main memory)
- 4. OS marks all previous TLB entries as invalid (i.e., flushes the cache) or restores TLB entries from saved PCB
- 5. As process runs, OS loads TLB missed entries possibly replacing existing entries if TLB is full

### Saving/Restoring Memory Upon Context Switch

- The PCB must now contain:
  - The value of the Page Table Base Register (PTBR)
  - Possibly a copy of the TLB entries

### Saving/Restoring Memory Upon Context Switch

- The PCB must now contain:
  - The value of the Page Table Base Register (PTBR)
  - Possibly a copy of the TLB entries
- On a context switch:
  - Copy the PTBR value to the PCB
  - Copy the TLB to the PCB (optional)
  - Flush the TLB (if TLB is not saved to/restored from the PCB)
  - Restore the PTBR (i.e., with the value of the new running process)
  - Restore the TLB (if it was previously saved)

 Paging systems can make it very easy to share blocks of memory

- Paging systems can make it very easy to share blocks of memory
- Memory doesn't have to be contiguous anymore!


- Paging systems can make it very easy to share blocks of memory
- Memory doesn't have to be contiguous anymore!
- Just duplicate page entries of different processes to the same page frames (both for code and data)

• Only if code is reentrant!

- Only if code is reentrant!
- It does not write to or change the code (i.e., it is non self-modifying)


- Only if code is reentrant!
- It does not write to or change the code (i.e., it is non self-modifying)
- The code can be shared by multiple processes, as long as each has their own copy of the data and registers, including the instruction register

# Sharing Pages: Example



3 user processes are using the editor program ed

# Sharing Pages: Example



3 user processes are using the editor program ed

Only a single copy of the code of ed is actually loaded in main memory

# Paging: Summary

- A big improvement over relocation
- Eliminates the problem of external fragmentation and therefore the need for compaction
- Allows code sharing among processes, reducing memory footprint
- Enables processes to run when they are partially loaded

## Paging: Summary

- However, paging comes with its costs...
- Virtual/Physical address translation may be time consuming
- Hardware support like TLB cache is needed to make it efficient enough
- OS has to be inevitably more complex