# Chapter 3 Transport Layer

#### A note on the use of these PowerPoint slides:


We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we'd like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

For a revision history, see the slide note for this page.

Thanks and enjoy! JFK/KWR

All material copyright 1996-2020 J.F Kurose and K.W. Ross, All Rights Reserved



# Computer Networking: A Top-Down Approach

8<sup>th</sup> edition Jim Kurose, Keith Ross Pearson, 2020

### Transport layer: overview

### Our goal:

- understand principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control

- learn about Internet transport layer protocols:
  - UDP: connectionless transport
  - TCP: connection-oriented reliable transport
  - TCP congestion control


# Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### Transport services and protocols

- provide logical communication between application processes running on different hosts
- transport protocols actions in end systems:
  - sender: breaks application messages into segments, passes to network layer
  - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
  - TCP, UDP



### Transport vs. network layer services and protocols



### household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes


### Transport vs. network layer services and protocols

- network layer: logical communication between hosts
- transport layer: logical communication between processes
  - relies on, enhances, network layer services

### household analogy:


- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes

### **Transport Layer Actions**




### Sender:

- is passed an applicationlayer message
- determines segment header fields values
- creates segment
- passes segment to IP




### **Transport Layer Actions**



#### Receiver:

- receives segment from IP
- checks header values
- extracts application-layer message
- demultiplexes message up to application via socket




# Two principal Internet transport protocols

- TCP: Transmission Control Protocol
  - reliable, in-order delivery
  - congestion control

n fornece garantia de atraso nem largura de banda

- flow control
- connection setup
- UDP: User Datagram Protocol
  - unreliable, unordered delivery
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees





### Chapter 3: roadmap


- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality




### **HTTP** server














### **HTTP** server













# Multiplexing/demultiplexing



# How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries one transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

# Connectionless demultiplexing

### Recall:

when creating socket, must specify *host-local* port #:

- when creating datagram to send into UDP socket, must specify
  - destination IP address
  - destination port #

when receiving host receives *UDP* segment:

- checks destination port # in segment
- directs UDP segment to socket with that port #




IP/UDP datagrams with same dest.

port #, but different source IP
addresses and/or source port
numbers will be directed to same
socket at receiving host

# Connectionless demultiplexing: an example

Quandp app precisa encaminhar dados para outro host, vai criar um socket




### Connection-oriented demultiplexing

- TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - dest IP address
  - dest port number
- demux: receiver uses all four values (4-tuple) to direct segment to appropriate socket

- server may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
  - each socket associated with a different connecting client

# Connection-oriented demultiplexing: example



Three segments, all destined to IP address: B, dest port: 80 are demultiplexed to *different* sockets

# Summary

- Multiplexing, demultiplexing: based on segment, datagram header field values
- UDP: demultiplexing using destination port number (only)
- TCP: demultiplexing using 4-tuple: source and destination IP addresses, and port numbers
- Multiplexing/demultiplexing happen at all layers

# Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



# **UDP: User Datagram Protocol**

- "no frills," "bare bones"
   Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out-of-order to app
- connectionless:
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

### Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
  - UDP can blast away as fast as desired!
  - can function in the face of congestion

# **UDP: User Datagram Protocol**

- UDP use:
  - streaming multimedia apps (loss tolerant, rate sensitive)
  - DNS
  - SNMP
  - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
  - add needed reliability at application layer
  - add congestion control at application layer

### UDP: User Datagram Protocol [RFC 768]

INTERNET STANDARD

**RFC 768** 

J. Postel ISI 28 August 1980


#### User Datagram Protocol

#### Introduction


This User Datagram Protocol (UDP) is defined to make available a datagram mode of packet-switched computer communication in the environment of an interconnected set of computer networks. This protocol assumes that the Internet Protocol (IP) [1] is used as the underlying protocol.

This protocol provides a procedure for application programs to send messages to other programs with a minimum of protocol mechanism. The protocol is transaction oriented, and delivery and duplicate protection are not guaranteed. Applications requiring ordered reliable delivery of streams of data should use the Transmission Control Protocol (TCP) [2].

#### Format



# **UDP: Transport Layer Actions**



# **UDP: Transport Layer Actions**


### SNMP client

application
transport
(UDP)
network (IP)
link
physical

### **UDP** sender actions:


- is passed an applicationlayer message
- determines UDP segment header fields values
- creates UDP segment
- passes segment to IP

### SNMP server



# **UDP: Transport Layer Actions**


### SNMP client




### **UDP** receiver actions:

- receives segment from IP
- checks UDP checksum header value
- extracts application-layer message
- demultiplexes message up to application via socket

### **SNMP** server




# **UDP** segment header



### **UDP** checksum

*Goal:* detect errors (*i.e.*, flipped bits) in transmitted segment



### **UDP** checksum

*Goal:* detect errors (i.e., flipped bits) in transmitted segment

### sender:


- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - Not equal error detected
  - Equal no error detected. But maybe errors nonetheless? More later ....

# Internet checksum: an example

example: add two 16-bit integers




Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

# Internet checksum: weak protection!

example: add two 16-bit integers



# Summary: UDP

- "no frills" protocol:
  - segments may be lost, delivered out of order
  - best effort service: "send and hope for the best"
- UDP has its plusses:
  - no setup/handshaking needed (no RTT incurred)
  - can function when network service is compromised
  - helps with reliability (checksum)
- build additional functionality on top of UDP in application layer (e.g., HTTP/3)


# Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality






reliable service abstraction



reliable service implementation


Complexity of reliable data transfer protocol will depend (strongly) on characteristics of unreliable channel (lose, corrupt, reorder data?)




reliable service implementation

Sender, receiver do *not* know the "state" of each other, e.g., was a message received?

unless communicated via a message




## Reliable data transfer protocol (rdt): interfaces



## Reliable data transfer: getting started

#### We will:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow in both directions!
- use finite state machines (FSM) to specify sender, receiver




### rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - no bit errors
  - no loss of packets
- separate FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver reads data from underlying channel







2 maquinas de estado bastante simples. Uma no emissor e outra no emissor

### rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum (e.g., Internet checksum) to detect bit errors
- *the* question: how to recover from errors?

How do humans recover from "errors" during conversation?

Analogia


### rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- *the* question: how to recover from errors?
  - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - sender *retransmits* pkt on receipt of NAK


stop and wait

sender sends one packet, then waits for receiver response

## rdt2.0: FSM specifications



## rdt2.0: FSM specification




Note: "state" of receiver (did the receiver get my message correctly?) isn't known to sender unless somehow communicated from receiver to sender


that's why we need a protocol!



## rdt2.0: operation with no errors



## rdt2.0: corrupted packet scenario



### rdt2.0 has a fatal flaw!

# what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


#### handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


#### stop and wait

sender sends one packet, then waits for receiver response

## rdt2.1: sender, handling garbled ACK/NAKs



## rdt2.1: receiver, handling garbled ACK/NAKs



### rdt2.1: discussion

#### sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "expected" pkt should have seq # of 0 or 1

#### receiver:


- must check if received packet is duplicate
  - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

## rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

As we will see, TCP uses this approach to be NAK-free

## rdt2.2: sender, receiver fragments



#### rdt3.0: channels with errors and loss

New channel assumption: underlying channel can also lose packets (data, ACKs)

checksum, sequence #s, ACKs, retransmissions will be of help ...
 but not quite enough

Q: How do *humans* handle lost sender-to-receiver words in conversation?


#### rdt3.0: channels with errors and loss

Approach: sender waits "reasonable" amount of time for ACK


- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but seq #s already handles this!
  - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after "reasonable" amount of time

timeout


### rdt3.0 sender




### rdt3.0 sender





### rdt3.0 in action





### rdt3.0 in action






(d) premature timeout/ delayed ACK

## Performance of rdt3.0 (stop-and-wait)

- *U* <sub>sender</sub>: *utilization* fraction of time sender busy sending
- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
  - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

## rdt3.0: stop-and-wait operation



## rdt3.0: stop-and-wait operation

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R}$$

$$= \frac{.008}{30.008}$$


$$= 0.00027$$

- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

## rdt3.0: pipelined protocols operation


pipelining: sender allows multiple, "in-flight", yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

## Pipelining: increased utilization



### Go-Back-N: sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
  - k-bit seq # in pkt header




- cumulative ACK: ACK(n): ACKs all packets up to, including seq # n
  - on receiving ACK(n): move window forward to begin at n+1
- timer for oldest in-flight packet
- timeout(n): retransmit packet n and all higher seq # packets in window

### Go-Back-N: receiver

- ACK-only: always send ACK for correctly-received packet so far, with highest in-order seq #
  - may generate duplicate ACKs
  - need only remember rcv base
  - on receipt of out-of-order packet:
    - can discard (don't buffer) or buffer: an implementation decision
    - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:




received and ACKed

Out-of-order: received but not ACKed

Not received


### Go-Back-N in action



## Selective repeat

- receiver individually acknowledges all correctly received packets
  - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
  - sender maintains timer for each unACKed pkt
- sender window
  - N consecutive seq #s
  - limits seq #s of sent, unACKed packets

## Selective repeat: sender, receiver windows



## Selective repeat: sender and receiver

#### sender

#### data from above:

if next available seq # in window, send packet

#### timeout(*n*):

resend packet n, restart timer

#### ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

#### receiver

#### packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yetreceived packet


#### packet n in [rcvbase-N,rcvbase-1]

ACK(n)

#### otherwise:

ignore


# Selective Repeat in action




# Selective repeat: a dilemma!

#### example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3






# Selective repeat: a dilemma!

#### example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: what relationship is needed between sequence # size and window size to avoid problem in scenario (b)?



## Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



## **TCP: overview** RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - no "message boundaries"
- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size

- cumulative ACKs
- pipelining:
  - TCP congestion and flow control set window size
- connection-oriented:
  - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

# TCP segment structure

32 bits dest port # source port # segment seq #: counting ACK: seq # of next expected bytes of data into bytestream sequence number byte; A bit: this is an ACK (not segments!) acknowledgement number head not len used C E length (of TCP header) receive window flow control: # bytes Internet checksum receiver willing to accept checksum Urg data pointer options (variable length) C, E: congestion notification TCP options application data sent by RST, SYN, FIN: connection data application into management (variable length) TCP socket

# TCP sequence numbers, ACKs

#### Sequence numbers:


 byte stream "number" of first byte in segment's data

#### Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-oforder segments

 <u>A:</u> TCP spec doesn't say, - up to implementor



# TCP sequence numbers, ACKs



simple telnet scenario

# TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss


### Q: how to estimate RTT?

- SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT

# TCP round trip time, timeout


EstimatedRTT =  $(1-\alpha)$ \*EstimatedRTT +  $\alpha$ \*SampleRTT

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value:  $\alpha$  = 0.125



# TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
  - large variation in EstimatedRTT: want a larger safety margin



■ DevRTT: EWMA of SampleRTT deviation from EstimatedRTT:

DevRTT = 
$$(1-\beta)$$
\*DevRTT +  $\beta$ \*|SampleRTT-EstimatedRTT|

(typically,  $\beta = 0.25$ )

<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

# TCP Sender (simplified)

# event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval:TimeOutInterval


#### event: timeout

- retransmit segment that caused timeout
- restart timer


#### event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments


# TCP Receiver: ACK generation [RFC 5681]



## TCP: retransmission scenarios



## TCP: retransmission scenarios




## TCP fast retransmit

#### TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

 likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!




## Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control




Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack


Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?






**Q**: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers



receiver protocol stack



Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?


#### -flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

application process Application removing data from TCP socket buffers TCP socket receiver buffers **TCP** code code from sender

receiver protocol stack


- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow



TCP receiver-side buffering

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

# TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
application

connection state: ESTAB
connection Variables:
seq # client-to-server
server-to-client
rcvBuffer size
at server,client


network
```


```
Socket clientSocket =
  newSocket("hostname", "port number");
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

# Agreeing to establish a connection

#### 2-way handshake:






**Q**: will 2-way handshake always work in network?


- variable delays
- retransmitted messages (e.g. req\_conn(x)) due to message loss
- message reordering
- can't "see" other side

# 2-way handshake scenarios






# 2-way handshake scenarios



# 2-way handshake scenarios



accepted!

# TCP 3-way handshake

#### Client state


serverSocket.listen(1) clientSocket = socket(AF INET, SOCK STREAM) LISTEN clientSocket.connect((serverName, serverPort)) choose init seq num, x send TCP SYN msq **SYNSFNT** SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live **ESTAB** 

#### Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) connectionSocket, addr = serverSocket.accept() LISTEN SYN RCVD

Transport Layer: 3-101

# A human 3-way handshake protocol



# Closing a TCP connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

## Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



# Principles of congestion control

### Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!



too many senders, sending too fast

flow control: one sender too fast for one receiver

# Causes/costs of congestion: scenario 1


#### Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed


original data:  $\lambda_{in}$  throughput:  $\lambda_{out}$  infinite shared output link buffers

Host B

Q: What happens as arrival rate  $\lambda_{in}$  approaches R/2?




maximum per-connection throughput: R/2



large delays as arrival rate  $\lambda_{in}$  approaches capacity

# Causes/costs of congestion: scenario 2


- one router, *finite* buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes retransmissions :  $\lambda'_{in} \ge \lambda_{in}$




# Causes/costs of congestion: scenario 2

#### Idealization: perfect knowledge


sender sends only when router buffers available






#### Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



#### Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

#### Realistic scenario: un-needed duplicates


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





#### Realistic scenario: un-needed duplicates

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered




#### "costs" of congestion:


- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput

- four senders
- multi-hop paths
- timeout/retransmit

 $\underline{Q}$ : what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow$  0







#### another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


# Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












### Approaches towards congestion control

#### End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



### Approaches towards congestion control

# Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



#### Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

#### Additive Increase Multiplicative <u>D</u>ecrease increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth

time

#### TCP AIMD: more


#### Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

#### Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

### TCP congestion control: details



#### TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

#### TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = 1 MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




# TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.


#### Implementation:

- variable ssthresh
- on loss event, ssthresh is set to
   1/2 of cwnd just before loss event




<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

# Summary: TCP congestion control




#### TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
  - W<sub>max</sub>: sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn't changed much
  - after cutting rate/window in half on loss, initially ramp to to  $W_{max}$  faster, but then approach  $W_{max}$  more slowly




#### TCP CUBIC

- K: point in time when TCP window size will reach W<sub>max</sub>
  - K itself is tuneable
- increase W as a function of the cube of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




# TCP and the congested "bottleneck link"

 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link




# TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



### Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



#### Delay-based approach:

- RTT<sub>min</sub> minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT<sub>min</sub>

```
if measured throughput "very close" to uncongested throughput increase cwnd linearly /* since path not congested */ else if measured throughput "far below" uncongested throughout decrease cwnd linearly /* since path is congested */
```


### Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google's (internal) backbone network

### Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
  - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



#### TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



### Q: is TCP Fair?

#### Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



#### Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

### Fairness: must all network apps be "fair"?

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

# Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2

### Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### Evolving transport-layer functionality


- TCP, UDP: principal transport protocols for 40 years
- different "flavors" of TCP developed, for specific scenarios:

Scenario	Challenges
Long, fat pipes (large data	Many packets "in flight"; loss shuts down
transfers)	pipeline
Wireless networks	Loss due to noisy wireless links, mobility;
	TCP treat this as congestion loss
Long-delay links	Extremely long RTTs
Data center networks	Latency sensitive
Background traffic flows	Low priority, "background" TCP flows

- moving transport—layer functions to application layer, on top of UDP
  - HTTP/3: QUIC

#### **QUIC: Quick UDP Internet Connections**

- application-layer protocol, on top of UDP
  - increase performance of HTTP
  - deployed on many Google servers, apps (Chrome, mobile YouTube app)




#### QUIC: Quick UDP Internet Connections

adopts approaches we've studied in this chapter for connection establishment, error control, congestion control


- error and congestion control: "Readers familiar with TCP's loss detection and congestion control will find algorithms here that parallel well-known TCP ones." [from QUIC specification]
- connection establishment: reliability, congestion control, authentication, encryption, state established in one RTT
- multiple application-level "streams" multiplexed over single QUIC connection
  - separate reliable data transfer, security
  - common congestion control

### QUIC: Connection establishment



TCP (reliability, congestion control state) + TLS (authentication, crypto state)


2 serial handshakes



QUIC: reliability, congestion control, authentication, crypto state

1 handshake

### QUIC: streams: parallelism, no HOL blocking



(a) HTTP 1.1

### Chapter 3: summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

#### Up next:


- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network-layer chapters:
  - data plane
  - control plane

# Additional Chapter 3 slides

#### Go-Back-N: sender extended FSM

```
rdt_send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt_send(sndpkt[nextseqnum])
                          if (base == nextsegnum)
                           start_timer
                          nextseqnum++
                       else
                        refuse_data(data)
  base=1
  nextseqnum=1
                                          timeout
                                          start timer
                            Wait
                                          udt_send(sndpkt[base])
                                          udt_send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                          udt_send(sndpkt[nextseqnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start_timer
```


#### Go-Back-N: receiver extended FSM




#### ACK-only: always send ACK for correctly-received packet with highest in-order seq #

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order packet:
  - discard (don't buffer): no receiver buffering!
  - re-ACK pkt with highest in-order seq #


# TCP sender (simplified)



# TCP 3-way handshake FSM



### Closing a TCP connection



### TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume there is always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# in-flight bytes) is ¾ W
  - avg. thruput is 3/4W per RTT

avg TCP thruput = 
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec

# TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput = 
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L =  $2\cdot10^{-10} a$  very small loss rate!
- versions of TCP for long, high-speed scenarios