



Onboarding Databases to DSF Hub Reference Guide

3 June 2026

Contents

AWS Asset Specifications 3

AWS Asset Specifications

Overview

This page provides general guidelines for configuring this asset, including the following:

- The expected parameter fields in this asset's document
- Information about connecting to this asset (expected fields in the "connection" document)
- Information about Sensitive Data Management (SDM) connections (if supported)
- Auto-discovery action for this asset (if supported)

For detailed instructions about onboarding this database type to DSF Hub for Auditing, reporting, compliance and security purposes, see [Onboarding Databases to DSF Hub - Overview](#).

For general information about configuring assets and connections, see [Using Assets in DSF Hub](#).

Permissions

Permissions are required to use this asset with specific DSF Hub features, as described in the table below.

DSF Hub feature	Minimum permissions required
Audit Management	N/A
Data Privacy	N/A
Discovery	Cluster / Neptune Cluster: ▪ rds:DescribeDBClusters Kinesis: ▪ kinesis:DescribeStream ▪ kinesis:ListStreams Log Group: ▪ logs:DescribeLogGroups

	RDS / Neptune: ▪ rds:DescribeDBInstances Redshift: ▪ redshift:DescribeClusters ▪ redshift-serverless:ListWorkgroups ▪ redshift-serverless:GetWorkgroup ▪ redshift-serverless:ListNamespaces Opensearch: ▪ es:ListDomainNames ▪ es:DescribeDomain S3: ▪ s3:ListAllMyBuckets ▪ rds:DescribeDBInstances (when running Discovery from Connect Gateway)
SonarGateway	Kinesis: ▪ kinesis:GetShardIterator, ▪ kinesis:GetRecords, ▪ kinesis:DescribeStream, ▪ kms:Decrypt Log Group: ▪ logs:DescribeLogGroups ▪ logs:DescribeLogStreams ▪ logs:FilterLogEvents ▪ logs:GetLogEvents RDS:

	▪ rds:DescribeDBInstances, ▪ rds:DescribeOptionGroups S3: ▪ s3:ListBucket, ▪ s3:GetObject, ▪ s3:ListAllMyBuckets, ▪ cloudtrail:DescribeTrails
--	--

Asset Parameters

Field	Type	Mandatory / optional	Value / <description>
asset_id	string	mandatory	<AWS ARN>
asset_display_name	string	mandatory	<User-friendly name of the asset, defined by user>
Server Type	string	mandatory	AWS
Server IP	string	mandatory	<AWS ARN>
Server Host Name	string	mandatory	<Endpoint URL, e.g. domain.amazon.com>
asset_source	string	mandatory	<The source platform / vendor / system of the asset data>
admin_email	string	mandatory	<The email address to notify about this asset>

Server Port	integer	mandatory	Default: 443
Service Name	string	mandatory	See Service Name Guidelines
timestamp	ISODate	auto-generated	<Timestamp of the asset document version creation>
jsonar_uid	string	auto-generated	<Unique identifier (UID) attached to the jSonar machine controlling the asset>
jsonar_uid_display_name	string	auto-generated	<Human-friendly ID attached to the jSonar machine controlling the asset>
version	float	optional	<Denotes the major version of the asset, e.g. postgres 9 vs. postgres 10>
location	string	optional	<Region>
used_for	string	optional	<Designates how this asset is used / the environment that the asset is supporting. Allowed values: Production Test Development Demonstration QA Staging Training

			Disaster Recovery>
owned_by	string	optional	<Email of person responsible for the asset; can be different from the person in the managed_by field. Defaults to admin_email>
managed_by	string	optional	<Email of person who maintains the asset; can be different from the owner specified in the owned_by field. Defaults to admin_email>
criticality	integer	optional	<The asset's importance to the business. These values are measured on a scale from "Most critical" (1) to "Least critical" (4). Allowed values: 1, 2, 3, 4>
asset_model	string	optional	<You can dynamically group actual discovered or imported assets into logical, operational, and financial models / domain via this parameter. Examples: CRM application, HR data>
urm_enabled	boolean	optional	<User rights management is enabled if this parameter is set to "True">
database_name	string	optional	<Specifies the name of the database you are connected to (or default DB)>
db_engine	string	optional	<Specifies the version of the engine being used by the database (e.g. oracle-

			ee, oracle-se, oracle-se1, oracle-se2)>
application	string	optional	<The Asset ID of the application asset that "owns" the asset>
service_endpoint_maxretries	integer	optional	<Maximum number of retry attempts. Default: 10>
service_endpoint_scalefactor	integer	optional	<Length of time between retry attempts (in minutes). Default value: 25>
service_endpoint_maxretries	integer	optional	<Maximum number of retry attempts. Default: 10>
service_endpoint_scalefactor	integer	optional	<Length of time between retry attempts (in minutes). Default value: 25>
enable_audit_management	boolean	optional	<If true, jSonar is responsible for setting and updating the policies. Default: false>
enable_audit_monitoring	boolean	optional	<If true, jSonar sends emails/alerts when the audit policies change. Default: false>
entitlement_enabled	boolean	optional	<If true, Entitlement Management system is enabled. Default: False>
service_endpoints	json	optional	Specify particular endpoints for a given

			service in the for of <service name> : "endpoint" e.g. {"logs": "https://logs.us-east-1.amazonaws.com". If uploading as part of a spreadsheet the header should be service_endpoints.logs and the value in the row should be the url.
credentials_endpoint	string	optional	A specific sts endpoint to use. e.g. if you want to use the global endpoint: https://sts.amazonaws.co m
aws_proxy_config	json	optional	{"http": <proxy>, "https": <proxy>}
proxy	string	optional	Proxy to use for AWS calls if aws_proxy_config is populated the proxy field will get populated from the http value there
available_regions	list	optional	A list of regions to use in discovery actions that iterate through regions. added in 4.3.d and 4.4.b +

Audit Information (audit_info) Sub-document

This asset type does not support Audit Information.

Connection

Note:

The *AWS Credentials file* is located at `${JSONAR_LOCALDIR}/credentials/.aws/credentials`, which is stored in the environment variable: `$AWS_SHARED_CREDENTIALS_FILE`

Authentication Mechanisms

- **key:** Uses `access_key_id` and `access_key_secret` to authenticate with the given IAM user access keys.
Template spreadsheet: `AWS_ACCOUNT_ASSET_KEY_PAIR_template.xlsx`
- **iam_role:** The DSF machine (either Hub or Agentless Gateway) will assume the given role.
Template spreadsheet: `AWS_IAM_ROLE_template.xlsx`

Note:

The **iam_role** authentication mechanism is supported only when the Hub host or Agentless Gateway host runs as an AWS EC2 instance.

- **profile:** Uses a given profile, defined in the *AWS Credentials file*.
Template spreadsheet: `AWS_PROFILE_template.xlsx`
- **default:** DSF uses the role attached to the DSF instance metadata. If there is no role attached, DSF will look for a profile name called "default" in the *AWS Credentials file*, and use that. See <https://boto3.amazonaws.com/v1/documentation/api/1.10.46/guide/configuration.html>
Template spreadsheet: `AWS_EC2_DEFAULT_ROLE_template.xlsx`

Connection Parameters

Authentication mechanism	Field	Mandatory / optional	Value / <description>
profile	Server Type	mandatory	AWS
	auth_mechanism	mandatory	profile
	Service Name	mandatory	<empty string>
	asset_id	mandatory	<string>
	asset_display_name	mandatory	<string>
	username	mandatory	<Profile name from the credentials file; credential file is located at

			JSONAR_LOCALDIR/ credentials/.aws/ credentials>
	region	mandatory	<string>
	reason	optional	<string: Used to differentiate connections that belong to the same asset>
key	Server Type	mandatory	<string>
	auth_mechanism	mandatory	key
	Service Name	mandatory	<empty string>
	asset_id	mandatory	<string>
	asset_display_name	mandatory	<string>
	access_id	mandatory	<string>
	secret_key	mandatory	<string>
	region	mandatory	<string>
	reason	optional	<string: Used to differentiate connections that belong to the same asset>
iam_role	Server Type	mandatory	<string>
	auth_mechanism	mandatory	iam_role

	Service Name	mandatory	<empty string>
	asset_id	mandatory	<string>
	asset_display_name	mandatory	<string>
	username	deprecated	<string; legacy option for backwards compatibility. The name of a profile from the credentials file; credential file is located at JSONAR_LOCALDIR/credentials/.aws/credentials If this field is given the gateway will use the profile specified in the username field rather than assuming the specified arn using the default role.>
	region	mandatory	<string>
	arn	mandatory	<string: the arn of the role to be assumed>
	external_id	optional	<string> available from 4.5.b+
	reason	optional	<string: Used to differentiate connections that belong to the same asset>
default	Server Type	mandatory	<string>
	auth_mechanism	mandatory	default
	Service Name	mandatory	<empty string>

	asset_id	mandatory	<string>
	asset_display_name	mandatory	<string>
	region	mandatory	<string>
	reason	optional	<string: Used to differentiate connections that belong to the same asset>
Key, iam_role, profile, default	available_regions	optional	<list; A list of regions to use in discovery actions that iterate through regions. added in 4.3.d and 4.4.b +>
Key, iam_role, profile, default	Server Port	mandatory	Default: 443

SDM Connections

This asset type does not currently support SDM connections.

Test Connection

This asset type supports the Test Connection action.

Auto-Discovery

This asset supports auto-discovery via the Discover RDS DBs action.

Document generated by Confluence on May 29, 2026 02:42

Atlassian