Asset Library for Unreal Engine

Documentation · version 2.7.4 · Unreal Engine 5.1 - 5.8 · Windows (Win64) · Editor-only

Asset Library keeps your reusable assets in one shared place on your machine and moves them between projects in a single click. When you save an asset, everything it references is copied with it, so importing it in another project brings the complete dependency tree.

1. Install

1. Close the Unreal Editor.
2. Download the zip that matches your engine version and extract it so you end up with `<YourProject>/Plugins/AssetLibrary/`. Create the `Plugins` folder if it does not exist.
3. Open the project. The plugin loads with no compile step when the folder contains `Binaries/Win64`.

You should see a **Library** button in the Content Browser toolbar, a **Window > Asset Library** entry and an **Add to Asset Library** option in the asset right-click menu.

> **Source-only builds.** A package that has only `Source/` (no `Binaries/`) must be compiled once inside a C++ project. Binary builds are specific to one engine version, so use the zip that matches your project.

2. Saving and importing assets

- **Save:** right-click an asset in the Content Browser and choose **Add to Asset Library**, or drag assets (or whole folders) into the Library panel. Everything they reference is copied too.
- **Import:** in any other project click **Library**, select an asset and press **Import to Project**.
- **Dependency picker:** choose which dependencies come along, grouped by class (Material, Texture2D, Skeleton and so on).
- **Engine-version awareness:** each asset is stamped with the engine version that saved it; you are warned before importing from a newer engine.

3. Organising the library (new in 2.7)

Folders first

The panel opens at **Library**. It shows sub-folders as cards first and then the assets that live directly in that folder, so a large library stays organised. You can still keep assets in the root. Double-click a folder to open it; use the breadcrumbs or the tree to go back. The last folder you used is remembered.

Moving things

Action	How
Move a folder	Drag a folder card, or a folder in the tree, onto another folder. Everything inside moves with it.
Move a folder to the top level	Drop it on **Library** in the tree.
Move assets	Select one or many (Ctrl / Shift) and drop them on a folder card or on a folder in the tree.
Menu alternative	Right-click a folder > **Move to**, or an asset > **Move to folder**.
Add from the Content Browser into a folder	Drop assets or folders from the Content Browser directly onto a library folder.
Rename / delete	`F2` renames the selected folder; `Del` deletes the selected folder (or removes the selected assets when the grid has focus).

Search

The search box looks through the current folder and everything below it. To also see assets from sub-folders while browsing, use **Sort > Show > Assets from sub-folders**.

4. Views and sorting

- **Grid** and **List** views (the list works like Windows Explorer, with columns).
- **Sort** by name, date added, date modified and more, ascending or descending.
- Asset names are always shown in full and wrap onto more lines instead of being cut with "...".

5. Thumbnails

For every asset the plugin tries, in order: the same renderer the Content Browser uses; its own renderers for types that need them (for example HDR cube maps and skyboxes); and the thumbnail stored inside the asset file. If none is available a clean placeholder with the asset type is shown, and the inspector explains why there is no image.

Right-click an asset > **Reload thumbnail** rebuilds its preview on demand.

6. Appearance

Open the gear menu > **Appearance** to pick a theme (light and dark options), an accent colour, and the thumbnail background: **Soft**, **By asset type** or **Original**. Choices are saved per user.

7. Where is the library stored?

By default in `<UserDir>/UEAssetLibrary` (for example `C:\Users\You\Documents\UEAssetLibrary`). Change it under **Project Settings > Asset Library**. Point it at a synced or network folder to share it between machines or a team.

8. Known limitations

- If an asset references content from a plugin that is not enabled in the destination project, the import will contain broken references. Enable the same plugins in both projects.
- Assets saved by a newer engine cannot be loaded by an older one (you get a warning before importing).
- The library is not a multi-user version control system: with a shared library the last writer wins.
- Engine content (anything under `/Engine/...`) is never copied.
- Editor-only plugin: no runtime cost, not included in packaged builds.

9. Troubleshooting and bug reports

Please include: engine version (Help > About), plugin version (`AssetLibrary.uplugin`), the exact steps to reproduce, and the relevant lines of `Saved/Logs/*.log` filtered by `LogAssetLibrary`.

10. Changelog

2.7.4

- Folders-first browsing; the library opens at **Library** with folder cards, and remembers the last folder.
- Move folders and assets by drag and drop, **Move to** menus, rename and delete shortcuts.
- List view, sorting, full asset names, themes and accent colours, thumbnail background options.
- More reliable thumbnails (HDR cube maps, embedded thumbnails, placeholders, **Reload thumbnail**).
- Fixed a crash when adding assets that depend on Deformer Graph (Optimus) content.
- Builds for UE 5.1 to 5.8.