# **Project 3**

Due May 18, 2020 at 11:59 PM

You will be working alone for this project. This specification is subject to change at anytime for additional clarification. For this project, you will be implementing a virtual machine threading API in either C or C++. **Your virtual machine will be tested on the CSIF machines.** You must submit the provided source code (including apps), your source files, readme and Makefile in a tgz file to Canvas prior to the deadline. Submit your project on Canvas.

You will be continuing the development of your virtual machine. You will be adding to the virtual machine a mutex API which provides a synchronization mechanism. Except were specified in this description the API will remain as stated in the Project 2 description.

The communication between the virtual machine and machine has changed. The MachineFileRead and MachineFileWrite functions require that shared memory locations be used to transfer data to/from the machine. In addition the maximum amount of data transferred must be limited to 512 bytes. VMFileRead and VMFileWrite **must** still be able to transfer up any number of bytes specified.

A working example of the vm and apps can be found in /home/cjnitta/ecs150. The vm syntax is vm [options] appname [appargs]. The possible options for vm are -t, and -s; -t specifies the tick time in millisecond, and -s specifies the size of the shared memory used between the virtual machine and machine. By default the tick time is set to 10ms, for debugging purposes you can increase these values to slow the running of the vm. The size of the shared memory is 16KiB. When specifying the application name the ./ should be prepended otherwise vm may fail to load the shared object file.

The function specifications for both the virtual machine and machine are provided in the subsequent pages, those that did not change from project 2 are not listed.

You should avoid using existing source code as a primer that is currently available on the Internet. You **must** specify in your readme file any sources of code that you have viewed to help you complete this project. If you do not have any sources, you must specify that as well. All class projects will be submitted to MOSS to determine if students have excessively collaborated with others. Excessive collaboration, or failure to list external code sources will result in the matter being transferred to Student Judicial Affairs.

# **Helpful Hints**

- You may want to start by adding the Mutex functions to your project 2 implementation. This will allow you to postpone making the changes to the VMFileWrite that is necessary for the output of all the applications.
- Each Mutex will probably need their own wait queues similar to the ready queues used in project 2.

• When updating the machine interface, you may want to use a wait queue similar to that of your mutex. It may be possible that the amount of shared memory available has been used up by all of the other threads.

- In order to simplify the Machine file interaction, you could allocate sections of the shared memory into 512B chunks. This is the largest allowed for a single transfer and will simplify bookkeeping for allocated vs free space.
- Two new apps badprogram.so and badprogram2.so attempt to test the VM API by passing in invalid parameters. These are good tests to make sure you can pass.

#### Name

VMStart – Start the virtual machine.

## Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMStart(int tickms, TVMMemorySize sharedsize, int argc, char *argv[]);
```

# Description

VMStart() starts the virtual machine by loading the module specified by argv[0]. The argc and argv are passed directly into the VMMain() function that exists in the loaded module. The time in milliseconds of the virtual machine tick is specified by the tickms parameter. The size of the shared memory space between the virtual machine and the machine is specified by the sharedsize.

#### Return Value

Upon successful loading and running of the VMMain() function, VMStart() will return VM\_STATUS\_SUCCESS after VMMain() returns. If the module fails to load, or the module does not contain a VMMain() function, VM\_STATUS\_FAILURE is returned.

#### Name

VMThreadTerminate—Terminates a thread in the virtual machine.

### Synopsys

#include "VirtualMachine.h"

TVMStatus VMThreadTerminate(TVMThreadID thread);

### **Description**

VMThreadTerminate() terminates the thread specified by *thread* parameter in the virtual machine. After termination the thread enters the state VM\_THREAD\_STATE\_DEAD, and must release any mutexes that it currently holds. The termination of a thread can trigger another thread to be scheduled.

#### Return Value

Upon successful termination of the thread in the virtual machine, VMThreadTerminate() returns VM\_STATUS\_SUCCESS. If the thread specified by the thread identifier *thread* does not exist, VM\_STATUS\_ERROR\_INVALID\_ID is returned. If the thread does exist, but is in the dead state VM\_THREAD\_STATE\_DEAD, VM\_STATUS\_ERROR\_INVALID\_STATE is returned.

### Name

VMMutexCreate—Creates a mutex in the virtual machine.

## Synopsys

#include "VirtualMachine.h"

TVMStatus VMMutexCreate(TVMMutexIDRef mutexref);

## **Description**

VMMutexCreate() creates a mutex in the virtual machine. Once created the mutex is in the unlocked state. The mutex identifier is put into the location specified by the *mutexref* parameter.

### Return Value

Upon successful creation of the thread VMMutexCreate() returns VM\_STATUS\_SUCCESS. VMMutexCreate() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER if either *mutexref* is NULL.

### Name

VMMutexDelete – Deletes a mutex from the virtual machine.

### Synopsys

#include "VirtualMachine.h"

TVMStatus VMMutexDelete(TVMMutexID mutex);

## Description

VMMutexDelete() deletes the unlocked mutex specified by *mutex* parameter from the virtual machine.

### Return Value

Upon successful deletion of the thread from the virtual machine, VMMutexDelete() returns VM\_STATUS\_SUCCESS. If the mutex specified by the thread identifier *mutex* does not exist, VM\_STATUS\_ERROR\_INVALID\_ID is returned. If the mutex does exist, but is currently held by a thread, VM\_STATUS\_ERROR\_INVALID\_STATE is returned.

#### Name

VMMutexQuery– Queries the owner of a mutex in the virtual machine.

### Synopsys

#include "VirtualMachine.h"

TVMStatus VMMutexQuery(TVMMutexID mutex, TVMThreadIDRef ownerref);

### Description

VMMutexQuery() retrieves the owner of the mutex specified by *mutex* and places the thread identifier of owner in the location specified by *ownerref*. If the mutex is currently unlocked, VM\_THREAD\_ID\_INVALID returned as the owner.

#### Return Value

Upon successful querying of the mutex owner from the virtual machine, VMMutexQuery() returns VM\_STATUS\_SUCCESS. If the mutex specified by the mutex identifier *mutex* does not exist, VM\_STATUS\_ERROR\_INVALID\_ID is returned. If the parameter *ownerref* is NULL, VM\_STATUS\_ERROR\_INVALID\_PARAMETER is returned.

#### Name

VMMutexAcquire – Locks the mutex.

### Synopsys

```
#include "VirtualMachine.h"
#define VM_TIMEOUT_INFINITE ((TVMTick)0)
#define VM_TIMEOUT_IMMEDIATE ((TVMTick)-1)

TVMStatus VMMutexAcquire(TVMMutexID mutex, TVMTick timeout);
```

## Description

VMMutexAcquire() attempts to lock the mutex specified by *mutex* waiting up to *timeout* ticks. If *timeout* is specified as VM\_TIMEOUT\_IMMEDIATE the current returns immediately if the mutex is already locked. If *timeout* is specified as VM\_TIMEOUT\_INFINITE the thread will block until the *mutex* is acquired.

### Return Value

Upon successful acquisition of the currently running thread, VMMutexAcquire() returns VM\_STATUS\_SUCCESS. If the *timeout* expires prior to the acquisition of the mutex, VM\_STATUS\_FAILURE is returned. If the mutex specified by the mutex identifier *mutex* does not exist, VM\_STATUS\_ERROR\_INVALID\_ID is returned.

#### Name

VMMutexRelease – Releases a mutex held by the currently running thread.

### Synopsys

#include "VirtualMachine.h"

TVMStatus VMMutexRelease(TVMMutexID mutex);

## **Description**

VMMutexRelease() releases the mutex specified by the *mutex* parameter that is currently held by the running thread. Release of the mutex may cause another higher priority thread to be scheduled if it acquires the newly released mutex.

#### Return Value

Upon successful release of the mutex, VMMutexRelease() returns VM\_STATUS\_SUCCESS. If the mutex specified by the mutex identifier *mutex* does not exist,

VM\_STATUS\_ERROR\_INVALID\_ID is returned. If the mutex specified by the mutex identifier *mutex* does exist, but is not currently held by the running thread,

VM\_STATUS\_ERROR\_INVALID\_STATE is returned.

### Name

MachineInitialize – Initializes the machine abstraction layer.

### Synopsys

#include "Machine.h"

void \*MachineInitialize(size t sharesize);

## Description

MachineInitialize() initializes the machine abstraction layer. The *sharesize* parameter specifies the size of the shared memory location to be used by the machine. The size of the shared memory will be set to an integral number of pages (4096 bytes) that covers the size of *sharesize*.

#### Return Value

Upon successful initialization MachineInitialize returns the base address of the shared memory. NULL is returned if the machine has already been initialized. If the memory queues or shared memory fail to be allocated the program exits.

#### Name

MachineFileRead – Reads from a file in the machine abstraction.

### Synopsys

```
#include "Machine.h"
typedef void (*TMachineFileCallback) (void *calldata, int result);

void MachineFileRead(int fd, void *data, int length, TMachineFileCallback
callback, void *calldata);
```

## Description

MachineFileRead() attempts to read the number of bytes specified in by *length* into the location specified by *data* from the file specified by *fd*. If the *data* value is not a location in the shared memory, MachineFileRead will fail; in addition if length is greater than 512 bytes MachineFileRead will also fail. The *fd* should have been obtained by a previous call to MachineFileOpen(). The actual number of bytes transferred will be returned in the *result* parameter when the *callback* function is called. Upon failure the *result* will be less than zero. The *calldata* parameter will also be passed into the *callback* function upon completion of the read file request. MachineFileRead () should return immediately, but will call the *callback* function asynchronously when completed.

### Return Value

N/A

#### Name

MachineFileWrite – Writes to a file in the machine abstraction.

### Synopsys

```
#include "Machine.h"
typedef void (*TMachineFileCallback) (void *calldata, int result);

void MachineFileWrite(int fd, void *data, int length, TMachineFileCallback callback, void *calldata);
```

## **Description**

MachineFileWrite() attempts to write the number of bytes specified in by *length* into the location specified by *data* to the file specified by *fd*. If the *data* value is not a location in the shared memory, MachineFileWrite will fail; in addition if length is greater than 512 bytes MachineFileWrite will also fail. The *fd* should have been obtained by a previous call to MachineFileOpen(). The actual number of bytes transferred will be returned in the *result* parameter when the *callback* function is called. Upon failure the *result* will be less than zero. The *calldata* parameter will also be passed into the *callback* function upon completion of the write file request. MachineFileWrite() should return immediately, but will call the *callback* function asynchronously when completed.

### Return Value

N/A