BASIC OOP IN C++

Overview

- · Object Models, Classes, Inheritance, and Polymorphism
- Interface-based Design: Abstract Classes

References

- Gary J. Bronson: C++ for Engineers and Scientists. 3rd Edition. Thomson (2010)
- Stanley B. Lippman, Josée Lajoie, and Barbara E. Moo: C++ Primer. 5th Edition. Addison-Wesley (2013)

C++ OBJECT MODELS

- C++ supports:
 - A value-based object model (stack-based objects)
 - · A reference-based object model (heap-based objects)

VALUE-BASED OBJECT MODEL

- In the value-based object model:
 - Objects are stored on the stack.
 - Object are accessed through object variables.
 - C++ scoping mechanism controls the lifetime of objects.
 - An object's memory is implicitly released when the object's lifetime reaches its end.

VALUE-BASED OBJECTS

· Value-based objects look and feel like records (or structs):

Card AceOfDiamond (Diamond, 14);

Card Test Card (Diamond, 14);

std::cout << "The test card is " << TestCard.getName() << std::endl;

<< std::endl;

member selection

REFERENCE-BASED OBJECT MODEL

- In the reference-based object model:
 - Objects are stored on the heap.
 - · Objects are accessed through pointer variables.
 - Heap objects persist even if the scope in which they have been created is closed.
 - · An object's memory must be explicitly released.

REFERENCE-BASED OBJECTS

 Reference-based objects require pointer variables and an explicit new and delete:

```
Card* AceOfDiamond = new Card( Diamond, 14);
```

Card* TestCard = new Card(Diamond, 14);

std::cout << "The test card is " << TestCard->getName() << std::endl;

delete AceOfDiamond;

delete TestCard;

release memory

member dereference

INHERITANCE

- Inheritance lets us define classes that model relationships among classes, sharing what is common, and specializing only that which is inherently different.
- Inheritance is
 - A mechanism for specialization;
 - A mechanism for reuse;
 - Fundamental to supporting polymorphism.

CLASSACCOUNT

```
class Account
private:
  uint64_t fNumber;
  double fBalance;
public:
  Account( uint64_t aNumber, double aBalance = 0.0 ) noexcept;
  virtual ~Account() {}
  uint64_t number() const noexcept { return fNumber; }
  double balance() const noexcept { return fBalance; }
  bool deposit( double aAmount ) noexcept;
  virtual bool withdraw( double aAmount ) noexcept;
};
```

- An account has a number (264- I values) and a balance.
- To create an account we need a number. Funds can be credited to an account once it has been created.
- Class Account defines virtual members. Hence, it must define a virtual destructor and class Account can be overridden using inheritance.

VIRTUAL MEMBER FUNCTIONS

- To assign a member function inherited from a base class new behavior in a derived class, one overrides it.
- To allow a member function in a base class to be overridden, one must declare the member function virtual.
- Note, non-virtual member functions are resolved with respect to the declared type of the object.
- Explicitly defining a (virtual) destructor affects which special member functions the compiler synthesizes (i.e., no default constructor is automatically created).

METHOD OVERRIDING

- Method overriding is an object-oriented programming mechanism that allows a subclass to provide a more specific implementation of a method, which is also present in one of its superclasses.
- The implementation in the subclass overrides (replaces) the implementation in the superclass by providing a method that has the same name, same parameter signature, and same return type as the method in the parent class. We say these methods belong to the same method family.
- Which (overridden) method is selected at runtime is determined by the receiver object used to invoke the member. In general, the most recent definition is chosen, if possible.

METHOD FAMILY

- A member function of a class always belongs to a specific set, called method family.
- If the elements of this set are virtual (default), then their invocation is governed by dynamic binding, a technique that makes polymorphism real.

VIRTUAL WITHDRAW METHOD

```
class BankAccount : public Account
private:
  double finterestRate;
public:
  BankAccount( uint64_t aNumber, double aBalance = 0.0, double aInterestRate = 0.0 ) noexcept;
  virtual ~BankAccount() override {}
  double& interest() noexcept { return finterestRate; }
  bool withdraw( double aAmount ) noexcept override;
                                                                               overridden method
  bool creditInterest( double aInterval = 31.0 / 365.0 ) noexcept;
  bool applyServiceFee( double aFee = 5.0 ) noexcept;
  // inherited from Account
  // uint64_t number() const noexcept;
  // double balance() const noexcept;
  // bool deposit( double aAmount ) noexcept;
  // bool withdraw( double aAmount ) noexcept;
```

ACCESS LEVELS FOR INHERITANCE

• public:

- · Public members in the base class remain public.
- Protected members in the base class remain protected.
- Yields a "is a" relationship, that is, a subtype.

protected:

- Public and protected members in the base class are protected in the derived class.
- Yields a "implemented in terms of" relationship, that is, a new type.

private:

- · Public and protected members in the base class become private in the derived class.
- Yields a stricter "implemented in terms of" relationship, that is, a new type.

PUBLIC INHERITANCE

- Public inheritance enables inclusion polymorphism: A subclass is a subtype.
- The subtype relationship is a key ingredient in contemporary object-oriented software development.
- An object of a subclass can be used safely anywhere an object of a superclass is expected. Example, we can use a BankAccount object in lieu of an Account object.

INHERITANCE: OBJECT CONSTRUCTION

```
BankAccount::BankAccount( uint64_t aNumber, double aBalance, double aInterestRate ) noexcept :

Account(aNumber, aBalance),

fInterestRate(aInterestRate)

{}
```

- The subclass constructor must first initialize the base class object using a suitable base class constructor.
- We use a member initializer list to initialize both, the base class object and the subclass member variables.
- The base class constructor cannot be called from within the body of a subclass constructor.

OVERRIDING WITHDRAW

```
bool BankAccount::withdraw( double aAmount ) noexcept
{
   if ( (balance() - aAmount) > 0.0 )
   {
      return Account::withdraw( aAmount );
   }
   return false;
}
```

- BackAccount's withdraw() performs a balance check and allows withdraws only if sufficient funds are available.
- To call a base class method in C++, we must refer to the corresponding base class scope (e.g. Account::).

VIRTUAL METHOD CALLS

```
int main()
  BankAccount | Account ( 12345 );
  std::cout << "Balance: " << IAccount.balance() << std::endl;
  // test dynamic method invocation
  Account& | BankAccount = | Account;
  if ( IBankAccount.withdraw( 50.0 ) )
     std::cout << "Instant credit. Wow!" << std::endl;
  else
     std::cout << "Sorry, not enough funds available.:(" << std::endl;
  return 0;
```

calls BankAccount::withdraw()

Balance: 0
Sorry, not enough funds available.:(

INTERFACE-BASED DESIGN

- Interface-based design is an architectural pattern for modular program development in object-oriented programming languages.
- From a conceptual standpoint, an interface is a contractual specification (i.e., protocol) between two parties. Ideally, if both parties adhere to the specification of the same interface, then correct interaction is guaranteed.
- In C++, we can use abstract classes as a means to create interfaces.
- Note, languages like C# or Java natively support interfaces as built-in abstraction. Interfaces and abstract classes coexist in these languages.
- An abstract class can define behavior, whereas an interface cannot (except for class-level features).

ABSTRACT CLASSES

- A class is abstract if it contains one or more pure virtual member functions.
- An abstract class cannot be instantiated.
- Derived classes must provide an implementation for the pure virtual member functions.
- An abstract class requires a virtual destructor. If one declares a pure virtual destructor, a definition for it must be given in a subclass eventually.

PURE VIRTUAL MEMBER FUNCTIONS

```
class AbstractClass
private:
public:
  AbstractClass();
  virtual ~AbstractClass();
  virtual type methodA() qualifier = 0;
  virtual type methodN() qualifier = 0;
```

- Pure virtual member functions declare what a class provides, but defer the implementation of that behavior to subclasses.
- In C++, we use = 0 to denote that a member function is abstract, that is, it does not have an implementation.

IMPLEMENTING PURE VIRTUAL MEMBER FUNCTIONS

```
class ConcreteClass: public AbstractClass
private:
public:
  ConcreteClass
  virtual ~ConcreteClass();
  virtual type methodA() qualifier override;
  virtual type methodN() qualifier override;
```

- In a subclass we override the pure virtual members.
- If all pure virtual members have been overridden, then we can create objects of this class.