### 动手实践-编写一个简单的块设备驱动


笨叔叔

#### 什么是块设备?

- ▶ 块设备的特点:
  - ✔ 字符设备是以字节流为传输单位的
  - ✓ 块设备是以块(block)为传输单位的
  - ✔ 字符设备按照字节流顺序来访问的
  - ✓ 块设备可以随机访问




- ✓ 磁头(head): 磁头固定在可移动的机械臂上,用于读写数据
- ✓ 磁道(track): 每个盘面都有 n 个同心圆组成, 每个同心圆称之为一个磁道
- ✓ 柱面(cylinder): n 个盘面的相同磁道(位置相同)共同组成一个柱面
- ✔ 扇区(sector):从磁盘中心向外画直线,可以将磁道划分为若干个弧段。每个
  - 一个弧段被称之为一个扇区
- ▶ 其他常见块设备:光盘,SSD等



#### 块设备驱动架构

- > 块设备驱动架构
  - ✓ 文件系统层:包含了常用的文件系统如ext4
  - ✓ 通用块层:
  - ✓ IO 调度器:
  - ✓ 具体块设备驱动:



#### block\_device数据结构

- ▶ block\_device数据结构用来抽象和描述一个块设备。
- ▶ block\_device把虚拟文件系统VFS和块设备子 系统关联起来

#### gendisk数据结构

- ▶ 磁盘类设备的一个抽象
- ▶ 可以表示一个已经分区的磁盘,也可以表示一个未分区的磁盘

```
struct gendisk {
    int major;
    int first_minor;
    int minors;
    char disk_name[DISK_NAME_LEN];
    struct disk_part_tbl __rcu *part_tbl;
    const struct block_device_operations *fops;
    struct request_queue *queue;
}:
```


#### block\_device\_operations操作方法集

▶ 块设备的操作方法集,类似字符设备的file\_opereations操作方法集

```
struct block device operations {
     int (*open) (struct block device *, fmode t);
     void (*release) (struct gendisk *, fmode t);
     int (*rw page) (struct block device *, sector t, struct page *, int rw);
     int (*ioctl) (struct block device *, fmode t, unsigned, unsigned long);
     int (*compat ioctl) (struct block device *, fmode t, unsigned, unsigned long);
      long (*direct access) (struct block device *, sector t,
                              void **, unsigned long *pfn, long size);
     unsigned int (*check events) (struct gendisk *disk,
                              unsigned int clearing);
     int (*media changed) (struct gendisk *);
     void (*unlock native capacity) (struct gendisk *);
     int (*revalidate disk) (struct gendisk *);
     int (*getgeo) (struct block device *, struct hd geometry *);
     /* this callback is with swap lock and sometimes page table lock held */
     void (*swap slot free notify) (struct block device *, unsigned long);
     struct module *owner:
};
```


#### 请求队列request\_queue

- ➤ request\_queue数据 结构来抽象和描述请 求队列
- ▶ 当文件系统这样的高层代码有新的请求队列中求队列请求队列不为空,只要请求队列不为空,那么队列中对应中的块设备驱动程序就以有求队列中获取下equest,然后送到对应的块设备驱动中。




#### bio数据结构

> 块设备数据传输的数据结构



#### 块设备子系统常用数据结构的关系图



- > 注册函数
  - ✓ int register\_blkdev(unsigned int major, const char \*name)

- > 注销函数
  - > void unregister\_blkdev(unsigned int major, const char \*name)

- ▶ 初始化请求队列:
  - ✓ struct request\_queue \*blk\_init\_queue(request\_fn\_proc \*rfn, spinlock t \*lock)

- > 注销请求队列
  - ✓ void blk\_cleanup\_queue(struct request\_queue \*q)

- ➤ 分配gendisk对象:
  - ✓ struct gendisk \*alloc disk(int minors)
- ➤ 注册gendisk对象
  - ✓ void add\_disk(struct gendisk \*disk)
- > 注销gendisk对象
  - ✓ void del gendisk(struct gendisk \*disk)

- ➤ 初始化一个BIO:
  - ✓ void bio\_init(struct bio \*bio)

- ➤ 提交BIO:
  - ✓ void submit\_bio(int rw, struct bio \*bio)

# 实 验

#### 实验: 写一个简单的ramdisk设备驱动

- ▶ 使用系统的物理内存来实现一个块设备, ramdisk
- > 实验要求
  - 1. 写一个简单的ramdisk设备驱动。可以使用ext4的格式化工具来格式化这个ramdisk。
  - 2. 在这个设备驱动中,实现HDIO\_GETGEO的ioctl命令,可以读出ramdisk的 hd\_geometry参数,比如有多少磁头,多少个柱面,多少个扇区等信息。写一个 简单的用户空间的测试程序来读取hd\_geometry参数。


## 进阶思考


#### 进阶思考题

▶ 假设系统使用eMMC作为存储介质,文件系统采用ext4。使用C语言的open函数打开一个文件,然后使用write函数来对写入内容,比如字符串"helloworld"

请阅读Linux内核代码,跟踪从用户空间write函数到eMMC存储设备了解写入内容经历了内核中哪些内核模块,期间使用了哪些主要的数据结构,并请画出其代码workflow。

# Backup





#### Card Identification (卡检测过程)



When eMMCinit

```
mmc_detect_change()
mmc rescan()
mmc_rescan_try_freq(): try to scan card by
100kHz/200K/300K/400K
    mmc attach mmc()
           Send CMD1 get OCR
           Set lowest voltage depend on OCR
           mmc_init_card()
                > Set ORC bit30, sector mode
                Send CMD2 fetch CID
                > Set card RCA and open drain mode
                > Send CMD9 fetch CSD, decode it.
                > Send CMD8 fetch EXT CSD, decode it
                Active high speed.
                      ✓ Use CMD 6 to Set HS TIMING= 1, enable high speed mode
                      ✓ mmc set timing() => mmc set ios() => host->ops->set ios()
                Set max clock: ext_csd.hs_max_dtr => mmc_set_clock()
                > Activate wide bus and DDR mode
                      ✓ select PowerClass for the current bus width. Select pwrclass val by vdd
                        (OCR), set pwrclass_val to EXT_CSD[187]

✓ Set bus width to EXT_CSD[183], and mmc_set_bus_width()

                      ✓ Enable DDR mode: DDR PowerClass, DDR bus width, mmc_set_timing(),
                        mmc set bus width()
           > mmc_add_card()
                ✓ device_add()
```