
ww3-gpu Time Step Sequence



NOAA WW3 (03adda91)

- W3WAVE loops DO JSEA=1, NSEAL at w3wavemd.F90:2246 and calls W3SRCE at :2311
- W3SRCE calls W3SIN4 :1239, W3SNL1 :1260, W3SDS4 :1303 in w3srcemd.F90
- Output: W3OUTG (VA, ...) at w3wavemd.F90:2490

Fork, phase 1 (769c44f0)

- Each flag is resolved once by ww_kokkos_flag; WW_KOKKOS_<PART>=1 on, unset follows WW_KOKKOS_ALL, default off
- Phase 1 copies one sea point in, runs the kernel, copies it out
- Flag off runs the same Fortran call as NOAA, in the same executable

Resident (--kokkos resident)

- Preset SRCE,XYP3,KTP3,OUTG,IOPE,UPDV (scripts/ww3-gpu.sh:167)
- VA stays on the device; host readers call W3KOKKOS_VA_HOST_READ first
- XYP3, KTP3, OUTG, IOPE, UPDV are opt-in and not regtested