

Type of work	dw	Comments	Units†
Expansion	$-p_{\rm ex} dV$	$p_{\rm ex}$ is the external pressure d $V$ is the change in volume	Pa m³
Surface expansion	$\gamma \mathrm{d}\sigma$	$\gamma$ is the surface tension ${ m d}\sigma$ is the change in area	$N m^{-1} m^2$
Extension	fdl	f is the tension $dl$ is the change in length	N m
Electrical	$\phi$ d $Q$	$\phi$ is the electric potential dQ is the change in charge	V C
	$Q d\phi$	$\mathrm{d}\phi$ is the potential difference $Q$ is the charge transferred	V C



Reversible change : can be reversed by an infinitesimal modification of variable
example : thermal equilibrium of two systems with same temperature

Reversible change : can be reversed by an infinitesimal modification of a variable
example : thermal equilibrium of two systems with same temperature
transfer of energy as heat between the two is reversible because



example: thermal equilibrium of two systems with same temperature transfer of energy as heat between the two is reversible because if temperature of either system is lowered infinitesimally then energy flows into the system with the lower temperature

example: thermal equilibrium of two systems with same temperature

transfer of energy as heat between the two is reversible because if temperature of either system is lowered infinitesimally

then energy flows into the system with the lower temperature

If temperature of either system at thermal equilibrium is raised infinitesimally

example: thermal equilibrium of two systems with same temperature

transfer of energy as heat between the two is reversible because if temperature of either system is lowered infinitesimally then energy flows into the system with the lower temperature

then energy flows into the system with the lower temperature

If temperature of either system at thermal equilibrium is raised infinitesimally

then energy flows out of the hotter system

example : thermal equilibrium of two systems with same temperature

transfer of energy as heat between the two is reversible because if temperature of either system is lowered infinitesimally then energy flows into the system with the lower temperature

If temperature of either system at thermal equilibrium is raised infinitesimally then energy flows out of the hotter system

There is a very close relationship between reversibility and equilibrium:

example : thermal equilibrium of two systems with same temperature

transfer of energy as heat between the two is reversible because if temperature of either system is lowered infinitesimally then energy flows into the system with the lower temperature

If temperature of either system at thermal equilibrium is raised infinitesimally then energy flows out of the hotter system

There is a very close relationship between reversibility and equilibrium:

There is a very close relationship between reversibility and equilibrium: systems at equilibrium are poised to undergo reversible change

Suppose a gas is confined by a piston and external pressure,  $p_{ex}$  is set equal

to the pressure, p, of the confined gas

to the pressure, p, of the confined gas Such a system is in mechanical equilibrium with its surroundings because an infinitesimal change in the external pressure in either direction causes changes in volume in opposite directions

Suppose a gas is confined by a piston and external pressure,  $p_{\rm ex}$  is set equal

Suppose a gas is confined by a piston and external pressure,  $p_{ex}$  is set equal to the pressure, p, of the confined gas Such a system is in mechanical equilibrium with its surroundings

because an infinitesimal change in the external pressure in either direction

causes changes in volume in opposite directions

If external pressure is reduced infinitesimally, the gas expands slightly

Suppose a gas is confined by a piston and external pressure,  $p_{\rm ex}$  is set equal to the pressure,  $p_{\rm ex}$  of the confined gas

Such a system is in mechanical equilibrium with its surroundings

because an infinitesimal change in the external pressure in either direction causes changes in volume in opposite directions

causes changes in volume in opposite directions

If external pressure is reduced infinitesimally, the gas expands slightly

If the external pressure is increased infinitesimally, the gas contracts slightly

Suppose a gas is confined by a piston and external pressure,  $p_{\rm ex}$  is set equal to the pressure,  $p_{\rm ex}$  of the confined gas

Such a system is in mechanical equilibrium with its surroundings

because an infinitesimal change in the external pressure in either direction causes changes in volume in opposite directions

If external pressure is reduced infinitesimally, the gas expands slightly

If the external pressure is increased infinitesimally, the gas contracts slightly

In either case the change is reversible in the thermodynamic sense

Suppose a gas is confined by a piston and external pressure,  $p_{ex}$  is set equal to the pressure, p, of the confined gas Such a system is in mechanical equilibrium with its surroundings

because an infinitesimal change in the external pressure in either direction

causes changes in volume in opposite directions If external pressure is reduced infinitesimally, the gas expands slightly If the external pressure is increased infinitesimally, the gas contracts slightly In either case the change is reversible in the thermodynamic sense If, on the other hand, the external pressure differs measurably from the internal pressure, then changing  $p_{\rm ex}$  infinitesimally will not decrease it below the pressure of the gas, so will not change the direction of the process.

Suppose a gas is confined by a piston and external pressure,  $p_{\rm ex}$  is set equal to the pressure, p, of the confined gas

Such a system is in mechanical equilibrium with its surroundings


Such a system is in mechanical equilibrium with its surroundings because an infinitesimal change in the external pressure in either direction causes changes in volume in opposite directions

If external pressure is reduced infinitesimally, the gas expands slightly

If the external pressure is increased infinitesimally, the gas contracts slightly
In either case the change is reversible in the thermodynamic sense
If, on the other hand, the external pressure differs measurably from the


If, on the other hand, the external pressure differs measurably from the internal pressure, then changing  $p_{\rm ex}$  infinitesimally will not decrease it below the pressure of the gas, so will not change the direction of the process. Such a system is **not** in mechanical equilibrium

## Calculating work:



For a perfect gas, reversible work of expansion =

### Calculating work:



For a perfect gas, reversible work of expansion =


expansion =
$$V_{f}$$

$$-\int_{V_{i}}^{V_{f}} p_{\text{ext}} dV = -\int_{V_{i}}^{V_{f}} p dV$$

$$= -nRT \ln \frac{V_{f}}{V_{i}}$$


for spontaneous expansion :  $work = -p_{ext} (V_f - V_i)$ 

Internal energy (U) as a function of temperature : U(V, T)





internal energy of a system increases as temperature is raised

Internal energy (U) as a function of temperature : U(V, T)




internal energy of a system increases as temperature is raised slope of tangent at any temperature =heat capacity, *C* in the Fig., *C* at A < *C* at B






$$C_V = \left(\frac{dq}{dT}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$



Volume, V

$$C_V = \left(\frac{dq}{dT}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$


$$\implies dU = C_V dT$$



$$C_V = \left(\frac{dq}{dT}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$

$$\implies dU = C_V dT$$


If heat capacity is independent of temperature over range of temperatures of interest




$$C_V = \left(\frac{dq}{dT}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$
  
 $\implies dU = C_V dT$   
If heat capacity is independent

If heat capacity is independent of temperature over range of temperatures of interest then  $\Delta U = C_V \Delta T$ 


for 
$$f \equiv f(x, y)$$
 
$$df = \left(\frac{\partial f}{\partial x}\right)_y dx + \left(\frac{\partial f}{\partial y}\right)_x dy$$



for 
$$f \equiv f(x, y)$$
 
$$df = \left(\frac{\partial f}{\partial x}\right)_y dx + \left(\frac{\partial f}{\partial y}\right)_x dy$$



for 
$$f \equiv f(x, y)$$
 
$$df = \left(\frac{\partial f}{\partial x}\right)_y dx + \left(\frac{\partial f}{\partial y}\right)_x dy$$



•	large heat capacity ⇒ small increase in temper	y of energy transferi	red as heat, a

- ▶ large heat capacity ⇒ for given quantity of energy transferred as heat, a small increase in temperature
  - phase transition : heat capacity of a sample is infinite

large heat capacity \Rightarrow for given quantity of energy transferred as heat, a small increase in temperature

phase transition : heat capacity of a sample is infinite mean energy of a molecule due to its translational motion  $=\frac{3}{2}k_BT$ 

 $\therefore$  contribution to molar energy =  $\frac{3}{2}RT$ 

▶ large heat capacity ⇒ for given quantity of energy transferred as heat, a small increase in temperature

phase transition: heat capacity of a sample is infinite mean energy of a molecule due to its translational motion  $= \frac{3}{2}k_BT$ 

 $\therefore$  contribution to molar energy  $=\frac{3}{2}RT$   $\implies$  considering only translational contribution to internal energy

$$U_m(T) = U_m(0) + \frac{3}{2}RT$$

lacktriangle large heat capacity  $\implies$  for given quantity of energy transferred as heat, a small increase in temperature

phase transition : heat capacity of a sample is infinite mean energy of a molecule due to its translational motion  $=\frac{3}{2}k_BT$ 

 $\therefore$  contribution to molar energy =  $\frac{3}{2}RT$ ⇒ considering only translational contribution to internal energy

 $U_m(T) = U_m(0) + \frac{3}{2}RT$ 

For polyatomics, rotational and vibrational contributions must be added:


ightharpoonup large heat capacity  $\implies$  for given quantity of energy transferred as heat, a small increase in temperature


phase transition: heat capacity of a sample is infinite mean energy of a molecule due to its translational motion  $=\frac{3}{2}k_BT$ 

 $\therefore$  contribution to molar energy =  $\frac{3}{2}RT$ ⇒ considering only translational contribution to internal energy

$$U_m(T) = U_m(0) + \frac{3}{2}RT$$
  
For polyatomics, rotational and vibrational contributions must be added:

e.g., for  $CO_2$ ,  $U_m(T) = U_m(0) + \frac{3}{2}RT + RT + \cdots$ 





Thermodynamic definition of a perfect gas :
no intermolecular interactions in a perfect gas
: distance between molecules has no effect on energy

Thermodynamic definition of a perfect gas :

no intermolecular interactions in a perfect gas

: distance between molecules has no effect on energy

⇒ internal energy of a perfect gas is independent of the volume it occupies

 $\begin{aligned} \text{Heat}: \\ dU &= dq + dw_{\text{exp}} + dw_{\text{e}} \end{aligned}$ 

Heat :  $dU = dq + dw_{\rm exp} + dw_{\rm e}$   $\uparrow \qquad \uparrow \qquad \uparrow \qquad \uparrow$ upper lower expansion extra case

Heat:  $dU = dq + dw_{\rm exp} + dw_{\rm e}$  $\uparrow$   $\uparrow$   $\uparrow$   $\uparrow$ upper lower expansion extra

generally, we consider only  $w_{exp}$ ,  $dU = dq_V$ 

Heat :  $dU = dq + dw_{\rm exp} + dw_{\rm e}$   $\uparrow \qquad \uparrow \qquad \uparrow \qquad \uparrow$ upper lower expansion extra case

generally, we consider only  $w_{exp}$ ,  $dU = dq_V$ 

Heat and work are equivalent ways of changing a system's internal energy

Heat :  $dU = dq + dw_{\rm exp} + dw_{\rm e}$   $\uparrow \qquad \uparrow \qquad \uparrow \qquad \uparrow$ upper lower expansion extra case

generally, we consider only  $w_{\text{exp}}$ ,  $dU = dq_V$ 

Heat and work are equivalent ways of changing a system's internal energy A system is like a bank: it accepts deposits in either currency, but stores its reserves as internal energy

Heat:  $dU = dq + dw_{exp} + dw_{e}$   $\uparrow \qquad \uparrow \qquad \uparrow \qquad \uparrow$ upper lower expansion extra

generally, we consider only  $w_{exp}$ ,  $dU = dq_V$ 

Heat and work are equivalent ways of changing a system's internal energy A system is like a bank: it accepts deposits in either currency, but stores its reserves as internal energy

First Law: internal energy of an isolated system is constant

$$\Delta U = q + w$$

Heat:  $dU = dq + dw_{exp} + dw_{e}$   $\uparrow \qquad \uparrow \qquad \uparrow \qquad \uparrow$ upger lower expansion extra

generally, we consider only  $w_{\text{exp}}$ ,  $dU = dq_V$ 

Heat and work are equivalent ways of changing a system's internal energy A system is like a bank: it accepts deposits in either currency, but stores its reserves as internal energy


First Law: internal energy of an isolated system is constant

$$\Delta U = q + w$$

dU = dq + dw


### Calorimetry

- Constant volume bomb calorimeter : measurement of  $q_{\it V}$ 



## Calorimetry


- Constant volume bomb calorimeter : measurement of  $q_{\it V}$ 



'bomb': central vessel, strong enough to withstand high pressures

### Calorimetry

- Constant volume bomb calorimeter : measurement of  $q_V$ 



'bomb': central vessel, strong enough to withstand high pressures To ensure adiabaticity, calorimeter is immersed in a water bath with temperature continuously readjusted to that of calorimeter at each stage of combustion

change in calorimeter temperature, $\Delta \mathcal{T} \propto$ energy released or al	osorbed in reaction

change in calorimeter temperature,  $\Delta T \propto$  energy released or absorbed in reaction

measure  $\Delta T \implies q_V$  and hence  $\Delta U$ 

change in calorimeter temperature,  $\Delta T \propto$  energy released or absorbed in reaction

measure 
$$\Delta T \implies q_V$$
 and hence  $\Delta U$ 

Calibration: use a process of known energy output and determine calorimeter constant


 $q = C\Delta T$ 

# Enthalpy

 $\Delta \text{energy} \neq \text{energy transferred as heat}$  when system is free to change its volume

Under these circumstances some of the


energy supplied as heat to system is returned to surroundings as expansion work, so dU < dq




# **Enthalpy**

 $\Delta$ energy  $\neq$  energy transferred as heat when system is free to change its volume

Under these circumstances some of the energy supplied as heat to system is returned to surroundings as expansion work, so dU < dq




def. 
$$H = U + pV$$
, a state function  $dH = d(U + pV) = dU + pdV + Vdp = dq + Vdp \implies dq_p = dH$  def.  $c_p = \left(\frac{dq}{dT}\right)_p = \left(\frac{\partial H}{\partial T}\right)_p \implies dH = C_p dT$ 



$$\int_{i}^{H_{f}-H_{i}} dH = \int_{i}^{q_{p}} dq_{p}$$


Part of a constant-pressure adiabatic flame calorimeter it is immersed in a stirred waterbath



$$\int_{i}^{H_{f}-H_{i}} dH = \int_{i}^{q_{p}} dq_{p}$$

Part of a constant-pressure adiabatic flame calorimeter

it is immersed in a stirred waterbath



Combustion occurs as a known amount of reactant is passed through to fuel the flame, and the rise of temperature is monitored.

when 1.0 mol CaCO $_3$  as calcite converts to aragonite,  $\Delta U = 0.21$  kJ

Calculate  $\Delta H - \Delta U$  when p=1 bar given densities of solids : 2.71 g cm<sup>-3</sup> and

2.93g cm<sup>-3</sup> respectively

2.93g cm \* respectively

when 1.0 mol CaCO<sub>3</sub> as calcite converts to aragonite,  $\Delta U = 0.21$  kJ

Calculate  $\Delta H - \Delta U$  when p = 1 bar given densities of solids: 2.71 g cm<sup>-3</sup> and

2.93g cm<sup>-3</sup> respectively
$$\Delta[H(\text{aragonite}) - H(\text{calcite})] = [U + pV](a) - [U + pV](c)$$

$$= \Delta U + \rho \left[ V(\mathbf{a}) - V(\mathbf{c}) \right] = \Delta U + \rho \Delta V$$

when 1.0 mol CaCO $_3$  as calcite converts to aragonite,  $\Delta \textit{U} = 0.21 \text{ kJ}$ 

Calculate 
$$\Delta H - \Delta U$$
 when  $p=1$  bar given densities of solids : 2.71 g cm $^{-3}$  and 2.93g cm $^{-3}$  respectively

$$\Delta[H(\text{aragonite}) - H(\text{calcite})] = [U + pV](a) - [U + pV](c)$$

$$= \Delta U + p[V(a) - V(c)] = \Delta U + p\Delta V$$

$$V_m \text{ for CaCO}_3 (100 \text{ g}) = \frac{34(a)}{37(c)} \text{ cm}^3$$

when 1.0 mol CaCO<sub>3</sub> as calcite converts to aragonite,  $\Delta U = 0.21$  kJ

Calculate 
$$\Delta H - \Delta U$$
 when  $p=1$  bar given densities of solids : 2.71 g cm<sup>-3</sup> and 2.93g cm<sup>-3</sup> respectively

$$\Delta[H(\text{aragonite}) - H(\text{calcite})] = [U + pV](a) - [U + pV](c)$$

$$= \Delta U + p[V(a) - V(c)] = \Delta U + p\Delta V$$

$$= \Delta U + p [V(a) - V(c)] = \Delta U + p \Delta V$$

$$V_m \text{ for CaCO}_3 (100 \text{ g}) = \frac{34(a)}{37(c)} \text{ cm}^3$$

$$ightharpoonup \therefore p\Delta V = 10^5 \text{ Pa} \times (34 - 37) \times 10^{-6} \text{ m}^3 = -0.3 \text{ J}$$

$$\rho \Delta V = 10^{3} \text{ Pa} \times (34 - 37) \times 10^{-6} \text{ m}^{3} = -0.3$$

when 1.0 mol CaCO<sub>3</sub> as calcite converts to aragonite,  $\Delta U = 0.21$  kJ

Calculate 
$$\Delta H - \Delta U$$
 when  $p=1$  bar given densities of solids : 2.71 g cm<sup>-3</sup> and 2.93g cm<sup>-3</sup> respectively

$$\Delta[H(\text{aragonite}) - H(\text{calcite})] = [U + pV](a) - [U + pV](c)$$

$$= \Delta U + p[V(a) - V(c)] = \Delta U + p\Delta V$$

$$= \Delta U + p [V(\mathbf{a}) - V(\mathbf{c})] = \Delta U + p \Delta V$$

$$\blacktriangleright V_m \text{ for } CaCO_3 \text{ (100 g)} = \frac{34(\mathbf{a})}{37(\mathbf{c})} \text{ cm}^3$$

$$ightharpoonup \therefore p\Delta V = 10^5 \text{ Pa} \times (34 - 37) \times 10^{-6} \text{ m}^3 = -0.3 \text{ J}$$

$$\therefore p\Delta V = 10^{\circ} \text{ Pax} (34 - 37) \times 10^{\circ} \text{ m}^{\circ} = -0.3 \text{ J}$$

$$\Rightarrow \Delta H - \Delta U = -0.3 \text{J} (\approx 0.15\% \text{ of } \Delta U)$$

when 1.0 mol CaCO<sub>3</sub> as calcite converts to aragonite,  $\Delta U = 0.21$  kJ Calculate  $\Delta H - \Delta U$  when p=1 bar given densities of solids : 2.71 g cm<sup>-3</sup> and 2.93g cm<sup>-3</sup> respectively

≥ 
$$\Delta[H(\text{aragonite}) - H(\text{calcite})] = [U + pV](a) - [U + pV](c)$$
  
=  $\Delta U + p[V(a) - V(c)] = \Delta U + p\Delta V$ 

 $V_m \text{ for CaCO}_3 (100 \text{ g}) = \frac{34(\text{a})}{37(\text{c})} \text{ cm}^3$ 

► : 
$$p\Delta V = 10^5 \text{ Pa} \times (34 - 37) \times 10^{-6} \text{ m}^3 = -0.3 \text{ J}$$

usually justifiable to ignore  $\Delta H - \Delta U$  for condensed phases, except at very high pressures, when  $\rho V$  is no longer negligible

Ex. Calculate  $\Delta H - \Delta U$  when 1.0 mol Sn(s, grey) of density 5.75 g cm<sup>-3</sup> changes to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K,  $\Delta H = 2.1$  kJ

Ex. Calculate  $\Delta H - \Delta U$  when 1.0 mol Sn(s, grey) of density 5.75 g cm<sup>-3</sup> changes to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K,  $\Delta H = 2.1$  k l

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ
$$\Delta [H(w) - H(g)] = [U + pV](w) - [U + pV](g)$$

Ex. Calculate  $\Delta H - \Delta U$  when 1.0 mol Sn(s, grey) of density 5.75 g cm<sup>-3</sup> changes

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ  $\Delta [H(w) - H(g)] = [U + pV](w) - [U + pV](g)$ 

 $=\Delta U + p[V(\mathbf{w}) - V(\mathbf{g})] = \Delta U + p\Delta V$ 

 $V_m$  for Sn (118.71 g)=  ${20.65(g) \over 16.24(w)}$  cm<sup>3</sup>

Ex. Calculate  $\Delta H - \Delta U$  when 1.0 mol Sn(s, grey) of density 5.75 g cm<sup>-3</sup> changes

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ  $\Delta [H(w) - H(g)] = [U + pV](w) - [U + pV](g)$ 

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ
$$\Delta [H(w) - H(g)] = [U + pV](w) - [U + pV](g)$$

 $=\Delta U + p[V(\mathbf{w}) - V(\mathbf{g})] = \Delta U + p\Delta V$ 

 $V_m$  for Sn (118.71 g)=  ${20.65 \text{ (g)} \atop 16.24 \text{ (w)}}$  cm<sup>3</sup>

 $ightharpoonup 
ho \Delta V = 10 \times 10^5 \text{ Pa} \times (16.24 - 20.65) \times 10^{-6} \text{ m}^3 = -4.4 \text{ J}$ 

Ex. Calculate  $\Delta H - \Delta U$  when 1.0 mol Sn(s, grey) of density 5.75 g cm<sup>-3</sup> changes to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K,  $\Delta H = 2.1$  kJ

to Sn(s, white) of density 7.31 g cm<sup>-3</sup> at 10.0 bar. At 298 K, 
$$\Delta H = 2.1$$
 kJ  $\Delta [H(w) - H(g)] = [U + pV](w) - [U + pV](g)$ 

$$\triangle[H(\mathbf{w}) - H(\mathbf{g})] = [U + pV](\mathbf{w}) - [U + pV](\mathbf{g})$$

$$= \Delta U + p[V(\mathbf{w}) - V(\mathbf{g})] = \Delta U + p\Delta V$$

$$\Delta[H(\mathbf{w}) - H(\mathbf{g})] = [U + \rho V](\mathbf{w}) - [U + \rho V](\mathbf{g})$$

$$= \Delta U + \rho [V(\mathbf{w}) - V(\mathbf{g})] = \Delta U + \rho \Delta V$$

 $V_m$  for Sn (118.71 g)=  ${20.65(g) \atop 16.24(w)}$  cm<sup>3</sup>

 $ightharpoonup 
ho \Delta V = 10 \times 10^5 \text{ Pa} \times (16.24 - 20.65) \times 10^{-6} \text{ m}^3 = -4.4 \text{ J}$ 

 $\rightarrow$   $\Delta H - \Delta U = -0.44 \text{ J} \ (\approx 0.2\% \text{ of } \Delta U)$ 

enthalpy of a perfect gas:

 $H = U + pV = U + nRT \implies \Delta H = \Delta U + \Delta nRT$ 

Water is heated to boiling under p = 1.0 atm. When an electric current of 0.50 A

from a 12 V supply is passed for 300 s through a resistance in thermal contact

with it,

0.798 g of water is vaporized. Calculate  $\Delta U_m$  and  $\Delta H_m$  at the boiling point

(373.15 K)

Water is heated to boiling under p = 1.0 atm. When an electric current of 0.50 A from a 12 V supply is passed for 300 s through a resistance in thermal contact with it.

0.798 g of water is vaporized. Calculate  $\Delta U_m$  and  $\Delta H_m$  at the boiling point (373.15 K)

$$\Delta H = q_p = 0.50 \text{ A} \times 12 \text{ V} \times 300 \text{s}$$

$$\Lambda H_{m} = q_{n} = \frac{0.50 \times 12 \times 300}{0.50 \times 10^{-200}} = 41 \text{ k/m}$$

$$\Delta H_m = q_p = rac{0.50 \times 12 \times 300}{rac{0.798}{18}} = 41 \ {
m kJ \ mol^{-1}}$$

Water is heated to boiling under p = 1.0 atm. When an electric current of 0.50 A

from a 12 V supply is passed for 300 s through a resistance in thermal contact with it. 0.798 g of water is vaporized. Calculate  $\Delta U_m$  and  $\Delta H_m$  at the boiling point (373.15 K)

 $\Delta U_m = \Delta H_m - RT = 38 \text{ kJ mol}^{-1} \left[ : p(V_g - V_I) \approx pV_g = RT \right]$ 

$$\Delta H = q_p = 0.50 \text{ A} \times 12 \text{ V} \times 300 \text{s}$$
 
$$\Delta H_m = q_p = \frac{0.50 \times 12 \times 300}{0.798} = 41 \text{ kJ mol}^{-1}$$

$$\Delta H_m = q_p = \frac{0.50 \times 12 \times 300}{\frac{0.798}{18}} = 41 \text{ kJ mol}^{-1}$$

solved problem:

Water is heated to boiling under p=1.0 atm. When an electric current of 0.50 A from a 12 V supply is passed for 300 s through a resistance in thermal contact with it,

from a 12 V supply is passed for 300 s through a resistance in thermal contact with it, 0.798 g of water is vaporized. Calculate  $\Delta U_m$  and  $\Delta H_m$  at the boiling point (373.15 K)


$$\Delta H = q_p = 0.50 \text{ A} \times 12 \text{ V} \times 300 \text{s}$$

$$\Delta H_m = q_p = \frac{0.50 \times 12 \times 300}{0.798} = 41 \text{ kJ mol}^{-1}$$

$$\Delta U_m = \Delta H_m - RT = 38 \text{ kJ mol}^{-1} \left[ \because p \left( V_g - V_l \right) \approx p V_g = RT \right]$$


Notice  $\Delta U_m < \Delta H_m$  because energy has been used to drive back surrounding atmosphere to make room for vapour

#### Enthalpy (H) as a function of temperature :



internal energy and enthalpy of system increase as temperature is raised

#### Enthalpy (H) as a function of temperature :



internal energy and enthalpy of system increase as temperature is raised at constant pressure, slope of tangent at any temperature =heat capacity,  $C_p$ 

For gases, at a given temperature the slope is steeper than that of internal energy versus temperature

$$C_{p, m} > C_{V, m}$$

# Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change

Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change 'differential' refers to the fact that the behaviour of the sample is compared to that

of a reference material which does not undergo a physical or chemical change

during the analysis

Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change 'differential' refers to the fact that the behaviour of the sample is compared to that


of a reference material which does not undergo a physical or chemical change

'scanning': temperatures are increased, or scanned, during the analysis

during the analysis


Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change 'differential' refers to the fact that the behaviour of the sample is compared to that of a reference material which does not undergo a physical or chemical change during the analysis

'scanning': temperatures are increased, or scanned, during the analysis DSC consists of two small, separate but identical compartments heated electrically at constant rate



Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change 'differential' refers to the fact that the behaviour of the sample is compared to that of a reference material which does not undergo a physical or chemical change during the analysis


'scanning': temperatures are increased, or scanned, during the analysis DSC consists of two small, separate but identical compartments heated electrically at constant rate



output: difference in power needed to maintain heat sinks at equal temperatures as temperature rises.


Differential scanning calorimeter (DSC) measures energy transferred as heat to or from a sample at constant pressure during a physical or chemical change 'differential' refers to the fact that the behaviour of the sample is compared to that of a reference material which does not undergo a physical or chemical change during the analysis

'scanning': temperatures are increased, or scanned, during the analysis DSC consists of two small, separate but identical compartments heated electrically at constant rate



output : difference in power needed to maintain heat sinks at equal temperatures as temperature rises.  $T(t) = T_0 + \alpha t$ , where  $T_0 =$  initial temperature  $\alpha =$  temperature scan rate (in  $Ks^{-1}$ )

A computer controls electrical power to maintain same temperature in sample and reference compartments



sample temperature changes significantly relative to that of reference material if transfer of energy as heat occurs in the sample during the scan
To maintain same temperature in both compartments, excess energy is transferred as heat to or from sample during the process

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

If no physical or chemical change occurs in sample at temperature T heat transferred to sample,  $q_p = C_p \Delta T$  if transfer of energy as heat occurs in the sample during the scan

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

If no physical or chemical change occurs in sample at temperature T heat transferred to sample,  $q_p = C_p \Delta T$  if transfer of energy as heat occurs in the sample during the scan

The chemical or physical process requires the transfer of  $q_p+q_{p,\,{\rm ex}}$  where  $q_{p,\,{\rm ex}}=$  excess energy transferred as heat, to attain same change in temperature of the sample

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

If no physical or chemical change occurs in sample at temperature T heat transferred to sample,  $q_p = C_p \Delta T$  if transfer of energy as heat occurs in the sample during the scan

The chemical or physical process requires the transfer of  $q_p+q_{p,\,{\rm ex}}$  where  $q_{p,\,{\rm ex}}=$  excess energy transferred as heat, to attain same change in temperature of the sample

 $q_{p,\,{
m ex}}=$  apparent change in heat capacity at constant pressure,  $\mathcal{C}_p$  during temperature scan

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

If no physical or chemical change occurs in sample at temperature T heat transferred to sample,  $q_p = C_p \Delta T$  if transfer of energy as heat occurs in the sample during the scan

The chemical or physical process requires the transfer of  $q_p+q_{p,\,{\rm ex}}$  where  $q_{p,\,{\rm ex}}=$  excess energy transferred as heat, to attain same change in temperature of the sample

 $q_{p,\,{
m ex}}=$  apparent change in heat capacity at constant pressure,  $\mathcal{C}_p$  during temperature scan

heat capacity  $= \mathcal{C}_p + \mathcal{C}_{p,\,\mathrm{ex}}$  and  $q_p + q_{p,\,\mathrm{ex}} = (\mathcal{C}_p + \mathcal{C}_{p,\,\mathrm{ex}})\,\Delta T$ 

an endothermic process lowers sample temperature relative to that of reference and, as a result, the sample must be heated more strongly than reference in order to maintain equal temperatures if transfer of energy as heat occurs in the sample during the scan

If no physical or chemical change occurs in sample at temperature T heat transferred to sample,  $q_p = C_p \Delta T$  if transfer of energy as heat occurs in the sample during the scan

The chemical or physical process requires the transfer of  $q_p+q_{p,\,ex}$  where  $q_{p,\,ex}=$  excess energy transferred as heat, to attain same change in temperature of the sample

 $q_{p,\,{
m ex}}=$  apparent change in heat capacity at constant pressure,  $C_p$  during temperature scan

heat capacity 
$$=$$
  $C_p$   $+$   $C_{p,\,\mathrm{ex}}$  and  $q_p$   $+$   $q_{p,\,\mathrm{ex}}$   $=$   $(C_p$   $+$   $C_{p,\,\mathrm{ex}})\Delta T$ 

 $\therefore C_{p, ex} = \frac{q_{p, ex}}{\Delta T} = \frac{q_{p, ex}}{\alpha t} = \frac{P_{ex}}{\alpha}; \quad P_{ex} = \text{excess electrical power necessary to}$  equalize the temperature of sample and reference compartments

DSC trace - a thermogram : plot of  $P_{ex}$  or C against T

Broad peaks in thermogram indicate processes requiring transfer of energy as heat

DSC trace - a thermogram : plot of  $P_{ex}$  or C against T

Broad peaks in thermogram indicate processes requiring transfer of energy as heat

$$\Delta H = \int_{T_1}^{T_2} C_{p, ex} dT$$


DSC trace - a thermogram : plot of  $P_{ex}$  or C against T


Broad peaks in thermogram indicate processes requiring transfer of energy as heat


$$\Delta H = \int_{T_1}^{T_2} C_{p, \text{ ex}} dT$$

thermogram for protein ubiquitin at pH = 2.45


native structure up to  $\approx 45^{\circ}\text{C}$  and then endothermic conformational change









when a perfect gas expands adiabatically




when a perfect gas expands adiabatically work is done but no heat enters the system



when a perfect gas expands adiabatically work is done but no heat enters the system internal energy falls - kinetic energy of molecules falls, average speed decreases




when a perfect gas expands adiabatically work is done but no heat enters the system internal energy falls - kinetic energy of molecules falls, average speed decreases ∴ temperature falls



when a perfect gas expands adiabatically work is done but no heat enters the system internal energy falls - kinetic energy of molecules falls, average speed decreases

∴ temperature falls

 $\Delta U$  for temperature change from  $T_i$  to  $T_f$  and the volume change from  $V_i$  to  $V_f$  can be seen as the sum of two steps




when a perfect gas expands adiabatically work is done but no heat enters the system internal energy falls - kinetic energy of molecules falls, average speed decreases

∴ temperature falls

 $\Delta U$  for temperature change from  $T_i$  to  $T_f$  and the volume change from  $V_i$  to  $V_f$  can be seen as the sum of two steps

1st step: only volume changes and

temperature is constant



when a perfect gas expands adiabatically work is done but no heat enters the system internal energy falls - kinetic energy of molecules falls, average speed decreases

∴ temperature falls

 $\Delta U$  for temperature change from  $T_i$  to  $T_f$  and the volume change from  $V_i$  to  $V_f$  can be seen as the sum of two steps

1st step : only volume changes and temperature is constant

U for perfect gas is independent of volume of molecules, the overall  $\Delta U$  arises solely from second step, the change in temperature at

$$\Delta U = C_v (T_f - T_i) = w_{ad}$$

constant volume

$$w_{ad} = C_v \Delta T$$

 $w_{ad} = C_v \Delta T$ reversible adiabatic expansion :  $C_v dT = -pdV$ 

$$w_{ad}=C_v\Delta T$$
  
reversible adiabatic expansion :  $C_vdT=-pdV$   
For perfect gas,  $C_v\frac{dT}{T}=-\frac{nRdV}{V}$ 


$$w_{ad} = C_v \Delta T$$
  
reversible adiabatic expansion :  $C_v dT = -pdV$   
For perfect gas,  $C_v \frac{dT}{T} = -\frac{nRdV}{V}$   
 $C_v \int\limits_{T_1}^{T_2} \frac{dT}{T} = -\int\limits_{V_1}^{V_2} \frac{nRdV}{V}$ 

$$w_{ad} = C_V \Delta T$$
 reversible adiabatic expansion :  $C_V dT = -pdV$  For perfect gas,  $C_V \frac{dT}{T} = -\frac{nRdV}{V}$   $C_V \int_{T_1}^{T_2} \frac{dT}{T} = -\int_{V_1}^{V_2} \frac{nRdV}{V}$   $C_V \ln \frac{T_2}{T_1} = -nR \ln \frac{V_2}{V_1}$ 

$$\begin{array}{l} w_{ad} = C_v \Delta T \\ \text{reversible adiabatic expansion} : \\ C_v dT = -p dV \\ \text{For perfect gas, } C_v \frac{dT}{T} = -\frac{nR dV}{V} \\ C_v \int\limits_{T_1}^{T_2} \frac{dT}{T} = -\int\limits_{V_1}^{V_2} \frac{nR dV}{V} \\ C_v \ln \frac{T_2}{T_1} = -nR \ln \frac{V_2}{V_1} \end{array}$$

or,  $\ln\left(\frac{T_2}{T_1}\right)^{\frac{C_V}{nR}} = \ln\left(\frac{V_1}{V_2}\right)$  or,  $\left(\frac{T_2}{T_1}\right)^{\frac{C_V}{nR}} = \frac{V_1}{V_2}$ 


 $w_{ad} = C_{V} \Delta T$ reversible adiabatic expansion:  $C_{v}dT = -pdV$ For perfect gas,  $C_V \frac{dT}{T} = -\frac{nRdV}{V}$  $C_{v} \int_{T}^{T_{2}} \frac{dT}{T} = -\int_{V}^{V_{2}} \frac{nRdV}{V}$  $C_v \ln \frac{T_2}{T_1} = -nR \ln \frac{V_2}{V_1}$ or,  $\ln\left(\frac{T_2}{T_1}\right)^{\frac{C_V}{nR}} = \ln\left(\frac{V_1}{V_2}\right)$  or,  $\left(\frac{T_2}{T_1}\right)^{\frac{C_V}{nR}} = \frac{V_1}{V_2}$   $\frac{T_2}{T_1} = \left(\frac{V_1}{V_2}\right)^{\frac{nR}{C_V}} = \left(\frac{V_1}{V_2}\right)^{\gamma-1}$  or,  $TV^{\gamma-1} = \text{const.}$ 




label :  $\frac{C_V}{R}$ 

show:  $pV^{\gamma} = \text{const}$ 

p-V-T plots: isotherms and adiabats pressure declines more steeply for an adiabat than for an isotherm



p-V-T plots: isotherms and adiabats pressure declines more steeply for an adiabat than for an isotherm



in isothermal expansion, energy flows into the system as heat and maintains the temperature; as a result, pressure does not fall as much as in adiabatic expansion

adiabatic, reversible expansion of 0.020 mol Ar initially at  $25^{\circ}$ C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup>

ex :

adiabatic, reversible expansion of 0.020 mol Ar

initially at 25°C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup>

 $C_V$  of argon = 12.48 JK<sup>-1</sup> mol<sup>-1</sup>,  $\gamma = \frac{12.48 + 8.314}{12.48} = \frac{20.794}{12.48} = 1.666$ 

adiabatic, reversible expansion of 0.020 mol Ar initially at 25°C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup>

 $C_V$  of argon = 12.48 JK<sup>-1</sup> mol<sup>-1</sup>,  $\gamma = \frac{12.48 + 8.314}{12.48} = \frac{20.794}{12.48} = 1.666$ 

Using  $T_f V_f^{\gamma-1} = T_i V_i^{\gamma-1}$ 

initially at 25°C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup>

nitially at 
$$25^{\circ}$$
C, from  $0.50 \text{ dm}^3$  to  $1.00 \text{ dm}^3$ 

we have  $T_f = 298 \times \left(\frac{0.50}{1}\right)^{0.666} = 188 \text{ K}$ 

Using  $T_f V_f^{\gamma-1} = T_i V_i^{\gamma-1}$ 

initially at 25°C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup> 
$$C_V$$
 of argon = 12.48 JK<sup>-1</sup> mol<sup>-1</sup>,  $\gamma = \frac{12.48 + 8.314}{12.48} = \frac{20.794}{12.48} = 1.666$ 

adiabatic, reversible expansion of 0.020 mol Ar

we have  $T_f = 298 \times \left(\frac{0.50}{1}\right)^{0.666} = 188 \text{ K}$ 

Using  $T_f V_f^{\gamma-1} = T_i V_i^{\gamma-1}$ 

initially at 25°C, from 0.50 dm<sup>3</sup> to 1.00 dm<sup>3</sup> 
$$C_V$$
 of argon = 12.48 JK<sup>-1</sup> mol<sup>-1</sup>,  $\gamma = \frac{12.48 + 8.314}{12.48} = \frac{20.794}{12.48} = 1.666$ 

 $\Delta T = 188 - 298 = -110$ K and  $w_{ad} = nC_V \Delta T = -0.020 \times 12.48 \times 110 = -27$  J

adiabatic, reversible expansion of 0.020 mol Ar

ex : adiabatic, reversible expansion of 0.020 mol Ar

 $C_V$  of argon = 12.48 JK<sup>-1</sup> mol<sup>-1</sup>,  $\gamma = \frac{12.48 + 8.314}{12.48} = \frac{20.794}{12.48} = 1.666$ 

Using  $T_f V_f^{\gamma-1} = T_i V_i^{\gamma-1}$ 

we have 
$$T_f = 298 imes \left( rac{0.50}{1} 
ight)^{0.666} = 188$$
 K

Note:  $\Delta T$  is independent of the amount of gas but the work is not

 $\Delta T = 188 - 298 = -110$ K and  $w_{ad} = nC_V \Delta T = -0.020 \times 12.48 \times 110 = -27$  J

т	L -	 _	~ L	 	 	

exchange of energy between system and surroundings

a reaction vessel and its contents form a system, and chemical reactions result in

a reaction vessel and its contents form a system, and chemical reactions result in

exchange of energy between system and surroundings
use calorimetry to measure energy supplied or discarded as heat by a reaction

a reaction vessel and its contents form a system, and chemical reactions result in exchange of energy between system and surroundings

use calorimetry to measure energy supplied or discarded as heat by a reaction identify  $q_V=\Delta U$  or  $q_p=\Delta H$ 

a reaction vessel and its contents form a system, and chemical reactions result in exchange of energy between system and surroundings

use calorimetry to measure energy supplied or discarded as heat by a reaction identify  $q_V = \Delta U$  or  $q_p = \Delta H$ 

Conversely, if we know  $\Delta U$  or  $\Delta H$  for a reaction, predict the energy (transferred as heat) the reaction produces

a reaction vessel and its contents form a system, and chemical reactions result in exchange of energy between system and surroundings

use calorimetry to measure energy supplied or discarded as heat by a reaction identify  $q_V=\Delta U$  or  $q_p=\Delta H$ 

Conversely, if we know  $\Delta U$  or  $\Delta H$  for a reaction, predict the energy (transferred as heat) the reaction produces


exothermic process at constant pressure :  $\Delta H < 0$ 

a reaction vessel and its contents form a system, and chemical reactions result in exchange of energy between system and surroundings

use calorimetry to measure energy supplied or discarded as heat by a reaction identify  $q_V = \Delta U$  or  $q_p = \Delta H$ 

Conversely, if we know  $\Delta U$  or  $\Delta H$  for a reaction, predict the energy (transferred as heat) the reaction produces

exothermic process at constant pressure :  $\Delta H < 0$  endothermic process at constant pressure :  $\Delta H > 0$ 



Standard state : standard state of a substance at a specified temperature is its pure form at	t 1	bar

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K: pure liquid ethanol at 298 K and 1 bar

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K: pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K : pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar

Standard enthalpy change,  $\Delta H^{\odot} =$ 

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K : pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar

Standard enthalpy change,  $\Delta H^{\odot} =$  enthalpy of products<sub>standard states</sub> — enthalpy of reactants<sub>standard states</sub>

Standard enthalpy change,  $\Delta H^{\odot} =$ 

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K : pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar  $\frac{1}{2}$ 

enthalpy of products  $_{\rm standard\,states}$  — enthalpy of reactants  $_{\rm standard\,states}$  standard enthalpy of vaporization :  $\Delta_{\rm vap} H^{\odot} = {\rm enthalpy}$  change per mole when a pure liquid at 1 bar vaporizes to a

 $\Delta_{\text{vap}}H^{\ominus}=$  enthalpy change per mole when a pure liquid at 1 bar vaporizes to a gas at 1 bar  $H_2O(I)\longrightarrow H_2O(g)$   $\Delta_{\text{vap}}H^{\ominus}(373\text{K})=40.66 \text{ kJmol}^{-1}$ 

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K : pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar

Standard enthalpy change,  $\Delta H^{\odot} =$  enthalpy of products<sub>standard states</sub> — enthalpy of reactants<sub>standard states</sub> standard enthalpy of vaporization :

 $H_2O(s) \longrightarrow H_2O(l)$   $\Delta_{fiis}H^{\odot}(273K) = 6.01 \text{ kJmol}^{-1}$ 

$$\Delta_{\text{vap}}H^{\odot}=$$
 enthalpy change per mole when a pure liquid at 1 bar vaporizes to a gas at 1 bar  $H_2O(I)\longrightarrow H_2O(g)$   $\Delta_{\text{vap}}H^{\odot}(373\text{K})=40.66 \text{ kJmol}^{-1}$ 

standard enthalpy of fusion:

$$\Delta_{\sf fus} H^{\odot} = {\sf enthalpy}$$
 change per mole when a pure liquid at 1 bar condenses to solid at 1 bar

standard state of a substance at a specified temperature is its pure form at 1 bar ex. liquid ethanol at 298 K : pure liquid ethanol at 298 K and 1 bar solid iron at 500 K is pure iron at 500 K and 1 bar

Standard enthalpy change,  $\Delta H^{\odot} =$  enthalpy of products<sub>standard states</sub> — enthalpy of reactants<sub>standard states</sub> standard enthalpy of vaporization :

 $\Delta_{\sf vap} H^{\odot} = {\sf enthalpy}$  change per mole when a pure liquid at 1 bar vaporizes to a gas at 1 bar


$$H_2O(I) \longrightarrow H_2O(g)$$
  $\Delta_{vap}H^{\odot}(373K) = 40.66 \text{ kJmol}^{-1}$ 

standard enthalpy of fusion:

$$\Delta_{\mathsf{fus}} H^{\odot} = \mathsf{enthalpy}$$
 change per mole when a pure liquid at 1 bar condenses to solid at 1 bar

$$\label{eq:H2O(s)} H_2O(I) \quad \ \Delta_{fus} H^{\scriptsize \bigcirc}(273 \mbox{K}) = 6.01 \mbox{ kJmol}^{-1}$$

standard enthalpies may be reported for any temperature



enthalpy is a state function

states

 $\Delta H$  is independent of path between the two

enthalpy is a state function

 $\Delta H$  is independent of path between the two states


same  $\Delta H^{\odot}$  for change brought about between same initial and final states


e.g., conversion of a solid to a vapour either as

occurring by sublimation  $H_2O(s) \longrightarrow H_2O(l) \quad \Delta_{fus}H^{\odot}$ 

$$H_2O(I) \longrightarrow H_2O(g)$$
  $\Delta_{vap}H^{\ominus}$   
 $H_2O(s) \longrightarrow H_2O(g)$   $\Delta_{sub}H^{\ominus} = ($ 

$$\mathsf{H}_2\mathsf{O}(\mathsf{s}) {\longrightarrow} \ \mathsf{H}_2\mathsf{O}(\mathsf{g}) \quad \ \Delta_{\mathsf{sub}} H^{\circleddash} = (\Delta_{\mathsf{fus}} H^{\circleddash} + \Delta_{\mathsf{vap}} H^{\circleddash}) > \Delta_{\mathsf{vap}} H^{\circleddash}$$






differ in sign

 $\Delta H^{\odot}$  for a forward process and its reverse differ in sign

e.g., conversion of a solid to a vapour either as occurring by sublimation

$$\Delta H^{\odot}(A \rightarrow B) = -\Delta H^{\odot}(B \rightarrow A)$$



Transition	Process	Symbol	
Transition	Phase $\alpha \rightarrow$ phase $\beta$	$\Delta_{ m trs} H$	
Fusion	$s \rightarrow 1$	$\Delta_{ m fus} H$	
Vaporization	$l \rightarrow g$	$\Delta_{ m vap} H$	
Sublimation	$s \rightarrow g$	$\Delta_{ m sub} H$	
Mixing	Pure → mixture	$\Delta_{ ext{mix}}H$	
Solution	Solute $\rightarrow$ solution	$\Delta_{ m sol} H$	
Hydration	$X^{\pm}(g) \rightarrow X^{\pm}(aq)$	$\Delta_{ m hyd} H$	
Atomization	$Species(s, l, g) \rightarrow atoms(g)$	$\Delta_{\rm at}H$	
Ionization	$X(g) \rightarrow X^+(g) + e^-(g)$	$\Delta_{\rm ion}H$	
Electron gain	$X(g) + e^{-}(g) \rightarrow X^{-}(g)$	$\Delta_{ m eg} H$	
Reaction	Reactants $\rightarrow$ products	$\Delta_{ m r} H$	
Combustion	Compounds(s, l, g) + $O_2(g) \rightarrow CO_2(g)$ , $H_2O(l, g)$	$\Delta_c H$	
Formation	Elements $\rightarrow$ compound	$\Delta_{ m f} H$	
Activation Reactants → activated complex		$\Delta^{\ddagger}H$	

Standard reaction enthalpy:	

pure, separate products in standard states

Pure, separate reactants in standard states  $\longrightarrow$ 

change in enthalpy for

change in enthalpy for Pure, separate reactants in standard states  $\longrightarrow$ 

pure, separate products in standard states

Ex.  $CH_4(g)+2O_2(g) \longrightarrow CO_2(g)+2H_2O(I)$   $\Delta_r H^{\odot}=-890 \text{ kJ}$ 

Standard reaction enthalpy : change in enthalpy for

Pure, separate reactants in standard states →

pure, separate products in standard states Ex.  $CH_4(g)+2O_2(g) \longrightarrow CO_2(g)+2H_2O(I)$   $\Delta_r H^{\odot} = -890 \text{ kJ}$ 

Ex.  $CH_4(g)+2O_2(g) \longrightarrow CO_2(g)+2H_2O(1)$   $\Delta_r H^{\odot}=-890 \text{ kJ}$ For the reaction  $2A+B \longrightarrow 3C+D$ 

change in enthalpy for Pure, separate reactants in standard states

Pure, separate reactants in standard states 
$$\longrightarrow$$
 pure, separate products in standard states

Ex.  $CH_4(g)+2O_2(g)\longrightarrow CO_2(g)+2H_2O(l)$   $\Delta_r H^{\odot}=-890 \text{ kJ}$ 

For the reaction 
$$2A+B \longrightarrow 3C+D$$
  

$$\Delta_r H^{\odot} = \{3H_m^{\odot}(C) + H_m^{\odot}(D)\} - \{2H_m^{\odot}(A) + H_m^{\odot}(B)\}$$

change in enthalpy for Pure, separate reactants in standard states  $\longrightarrow$ 

pure, separate products in standard states Ex.  $CH_4(g)+2O_2(g) \longrightarrow CO_2(g)+2H_2O(I)$   $\Delta_r H^{\odot}=-890 \text{ kJ}$ For the reaction  $2A+B \longrightarrow 3C+D$ 

For the reaction 
$$2A+B \longrightarrow 3C+D$$
  

$$\Delta_r H^{\odot} = \{3H_m^{\odot}(C) + H_m^{\odot}(D)\} - \{2H_m^{\odot}(A) + H_m^{\odot}(B)\}$$
generally,  $\Delta_r H^{\odot} = \sum \nu H_m^{\odot} - \sum \nu H_m^{\odot}$ 

nerally, 
$$\Delta_r H^{\odot} = \sum\limits_{\mathsf{products}} 
u H^{\odot}_m - \sum\limits_{\mathsf{reactants}} 
u H^{\odot}_m$$


change in enthalpy for Pure, separate reactants in standard states  $\longrightarrow$ 

pure, separate products in standard states  
Ex. 
$$CH_4(g)+2O_2(g) \longrightarrow CO_2(g)+2H_2O(I)$$
  $\Delta_r H^{\odot} = -890 \text{ kJ}$ 


For the reaction  $2A+B \longrightarrow 3C+D$  $\Delta_r H^{\odot} = \{3H_m^{\odot}(C) + H_m^{\odot}(D)\} - \{2H_m^{\odot}(A) + H_m^{\odot}(B)\}$ 

generally, 
$$\Delta_r H^{\odot} = \sum_{\text{products}} \nu H_m^{\odot} - \sum_{\text{reactants}} \nu H_m^{\odot}$$

standard enthalpy of combustion,  $\Delta_C H^{\odot}=$  standard reaction enthalpy for the complete oxidation of an organic compound to CO<sub>2</sub> gas and liquid water if the compound contains C, H, and O, and to N<sub>2</sub> gas if N is also present



reaction enthalpy in terms of enthalpies of formation



$$\Delta_r H^{\odot} = \sum_{\rm products} \nu \Delta_f H^{\odot} - \sum_{\rm reactants} \nu \Delta_f H^{\odot}$$



Can we construct  $\Delta_f H^{\odot}$  from a knowledge of chemical constitution of the species?

Can we construct  $\Delta_f H^{\odot}$  from a knowledge of chemical constitution of the species? no thermodynamically exact way of expressing enthalpies of formation in terms of contributions from individual atoms and bonds

 $dH = C_p dT \implies H(T_2) = H(T_1) + \int_{T_1}^{T_2} C_p dT$  assuming no phase transition in

$$dH = C_p dI \implies$$


temperature range of interest

 $dH = C_p dT \implies H(T_2) = H(T_1) + \int_{T_1}^{T_2} C_p dT$  assuming no phase transition in

temperature range of interest

### Kirchhoff's law

where 
$$\Delta_r C_p^{\odot} = \sum_{\text{products}} \nu C_{\text{p, m}}^{\odot} - \sum_{\text{reactants}} \nu C_{\text{p, m}}^{\odot}$$



solved prob.:  $\Delta_f H^{\odot}(H_2O(g);298 \text{ K}) = -241.82 \text{ kJ mol}^{-1}$ 

 $C_{p.m}(O_2,g) = 29.37 \text{J K}^{-1} \text{ mol}^{-1}$ 

solved prob.: 
$$\Delta_f H^{\odot}({
m H_2O(g);298~K}) = -241.82~{
m kJ~mol}^-$$
 Estimate  $\Delta_f H^{\odot}$  at  $100^{\circ}{
m C}$ 

given  $C_{p, m}(H_2O,g) = 33.58 \text{ J K}^{-1} \text{mol}^{-1}$ ;  $C_{p, m}(H_2,g) = 28.84 \text{ JK}^{-1} \text{ mol}^{-1}$ ;

solved prob.:  $\Delta_f H^{\odot}(H_2O(g);298 \text{ K}) = -241.82 \text{ kJ mol}^{-1}$ 

solved prob.: 
$$\Delta_f H^\odot(\mathsf{H}_2\mathsf{O}(\mathsf{g});298\;\mathsf{K}) = -241.82\;\mathsf{kJ}\;\mathsf{mol}^-$$
Estimate  $\Delta_f H^\odot$  at  $100^\circ\mathsf{C}$ 

Estimate  $\Delta_f H^{\odot}$  at  $100^{\circ}$ C

 $C_{p,m}(O_2,g) = 29.37 \text{J K}^{-1} \text{ mol}^{-1}$ 

given  $C_{p, m}(H_2O,g) = 33.58 \text{ J K}^{-1} \text{mol}^{-1}$ ;  $C_{p, m}(H_2,g) = 28.84 \text{ JK}^{-1} \text{ mol}^{-1}$ ;

 $\Delta_r C_p^{\odot} = C_{p,m} (H_2O_rg) - \{C_{p,m}(H_2,g) + \frac{1}{2}C_{p,m}(O_2,g) = -9.94 \text{JK}^{-1} \text{ mol}^{-1} \}$ 

solved prob.:  $\Delta_f H^{\odot}(H_2O(g);298 \text{ K}) = -241.82 \text{ kJ mol}^{-1}$ 

Estimate 
$$\Delta_f H^{\odot}$$
 at  $100^{\circ}$ C

given  $C = (H, O, \sigma) = 33.58 \text{ J.K}^{-1} \text{mol}^{-1}$ ;  $C = (H, \sigma) = 33.58 \text{ J.K}^{-1}$ 

Estimate 
$$\Delta_f H^{\odot}$$
 at  $100^{\circ}$ C given  $C_{p, m}(H_2O,g) = 33.58 \text{ J K}^{-1} \text{mol}^{-1}$ ;  $C_{p, m}(H_2,g) = 28.84 \text{ JK}^{-1} \text{ mol}^{-1}$ ;

 $\Delta_r C_p^{\odot} = C_{p,m} (H_2 O,g) - \{C_{p,m} (H_2,g) + \frac{1}{2} C_{p,m} (O_2,g) = -9.94 \text{JK}^{-1} \text{ mol}^{-1} \}$ 

 $= -241.82 - 75 \times 9.94 \times 10^{-3} = -242.6 \text{k L mol}^{-1}$ 

 $\therefore \Delta_r H^{\odot}(T_2) = \Delta_r H^{\odot}(T_1) + (T_2 - T_1) \Delta_r C_n^{\odot}$ 

 $C_{p,m}(O_2,g) = 29.37 \text{JK}^{-1} \text{ mol}^{-1}$