
Operating Systems

Isfahan University of Technology Electrical and Computer Engineering Department 1400-1 semester

Zeinab Zali


Session 7: Inter Process Communication (IPC)



Interprocess Communication


- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
 - Information sharing
 - Computation speedup
 - Modularity
 - Convenience
- Cooperating processes need interprocess communication (IPC)
- Two models of IPC
 - Shared memory
 - Message passing (for small amounts of data)





Communications Models

- (a) Shared memory. (b) Message passing.






Producer-Consumer Problem

- Paradigm for cooperating processes:
 - producer process produces information that is consumed by a consumer process
- Two variations:
 - unbounded-buffer places no practical limit on the size of the buffer:
 - Producer never waits
 - Consumer waits if there is no buffer to consume
 - bounded-buffer assumes that there is a fixed buffer size
 - Producer must wait if all buffers are full
 - Consumer waits if there is no buffer to consume





Interprocess Communication – Shared Memory

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Benefits:
 - Faster than message passing
- Disadvantages:
 - Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.





Bounded-Buffer – Shared-Memory Solution

Shared data

```
#define BUFFER_SIZE 10

typedef struct {
    . . .
} item;

item buffer[BUFFER_SIZE];

int in = 0;

int out = 0;
```

Solution is correct, but can only use BUFFER_SIZE-1 elements





Producer Process – Shared Memory





Consumer Process – Shared Memory

```
item next_consumed;
while (true) {
    while (in == out)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;

    /* consume the item in next consumed */
}
```






What about Filling all the Buffers?

- Suppose that we wanted to provide a solution to the consumerproducer problem that fills all the buffers.
- We can do so by having an integer counter that keeps track of the number of full buffers.
- Initially, counter is set to 0.
- The integer counter is incremented by the producer after it produces a new buffer.
- The integer counter is and is decremented by the consumer after it consumes a buffer.






Producer

```
while (true) {
    /* produce an item in next produced */
    while (counter == BUFFER_SIZE)
       ; /* do nothing */
    buffer[in] = next_produced;
    in = (in + 1) % BUFFER_SIZE;
    counter++;
}
```





Consumer

```
while (true) {
    while (counter == 0)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;
        counter--;
    /* consume the item in next consumed */
}
```





Race Condition

counter++ could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

counter-- could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

Consider this execution interleaving with "count = 5" initially:

```
S0: producer execute register1 = counter {register1 = 5}
S1: producer execute register1 = register1 + 1 {register1 = 6}
S2: consumer execute register2 = counter {register2 = 5}
S3: consumer execute register2 = register2 - 1 {register2 = 4}
S4: producer execute counter = register1 {counter = 6}
S5: consumer execute counter = register2
```






Race Condition (Cont.)

- Question why was there no race condition in the first solution (where at most N - 1) buffers can be filled?
- More in Chapter 6.






Examples of IPC Systems - POSIX

- POSIX Shared Memory
 - Process first creates shared memory segment
 shm_fd = shm_open(name, O CREAT | O RDWR, 0666);
 - Also used to open an existing segment
 - Set the size of the object

```
ftruncate(shm_fd, 4096);
```


- Use mmap () to memory-map a file pointer to the shared memory object
- Reading and writing to shared memory is done by using the pointer returned by mmap().






IPC POSIX Producer

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS":
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";
/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;
   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);
   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);
   /* write to the shared memory object */
   sprintf(ptr, "%s", message_0);
   ptr += strlen(message_0);
   sprintf(ptr,"%s",message_1);
   ptr += strlen(message_1);
   return 0;
```




IPC POSIX Consumer

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;
   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);
   /* read from the shared memory object */
   printf("%s",(char *)ptr);
   /* remove the shared memory object */
   shm_unlink(name);
   return 0:
```




IPC – Message Passing

- Message system processes communicate with each other without sharing the same address space directly
- IPC facility provides two operations:
 - send(message)
 - receive(message)
- The message size is either fixed or variable







Message Passing

- If processes P and Q wish to communicate, they need to:
 - Establish a communication link between them
 - Exchange messages via send/receive
- Implementation issues:
 - How are links established?
 - Can a link be associated with more than two processes?
 - How many links can there be between every pair of communicating processes?
 - What is the capacity of a link?
 - Is the size of a message that the link can accommodate fixed or variable?
 - Is a link unidirectional or bi-directional?





Message Passing model

Physical link

Shared memory, Hardware bus, Network

Logical link

- Naming
 - Direct (name the process), indirect (name the mailbox or link)
- Synchronization
 - Block, Non-block
- Buffering
 - Zero, bounded, un-bounded





Producer-Consumer: Message Passing

Producer

```
message next_produced;
while (true) {
  /* produce an item in next_produced */
  send(next_produced);
}
```

Consumer

```
message next_consumed;
while (true) {
  receive(next_consumed)

/* consume the item in next_consumed */
}
```






Pipes


- Acts as a conduit allowing two processes to communicate
- Issues:
 - Is communication unidirectional or bidirectional?
 - In the case of two-way communication, is it half or full-duplex?
 - Must there exist a relationship (i.e., parent-child) between the communicating processes?
 - Can the pipes be used over a network?
- Ordinary pipes cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created.
- Named pipes can be accessed without a parent-child relationship.





Ordinary Pipes

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe)
- Ordinary pipes are therefore unidirectional
- Require parent-child relationship between communicating processes



Windows calls these anonymous pipes





Named Pipes


- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems






Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls (RPC)








Sockets


- A socket is defined as an endpoint for communication
- Concatenation of IP address and port a number included at start of message packet to differentiate network services on a host
- The socket 161.25.19.8:1625 refers to port 1625 on host 161.25.19.8
- Communication consists between a pair of sockets
- All ports below 1024 are **well known**, used for standard services
- Special IP address 127.0.0.1 (loopback) to refer to system on which process is running
- Three types of sockets
 - Connection-oriented (TCP)
 - Connectionless (UDP)
 - MulticastSocket class— data can be sent to multiple recipients
- Consider this "Date" server in Java:







Socket Communication










Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
 - Again uses ports for service differentiation
- Stubs client-side proxy for the actual procedure on the server
- The client-side stub locates the server and marshalls the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and performs the procedure on the server
- On Windows, stub code compile from specification written in Microsoft Interface Definition Language (MIDL)

Remote Procedure Call (RPC)








Remote Procedure Calls (Cont.)

- Data representation handled via External Data Representation (XDL) format to account for different architectures
 - Big-endian and little-endian
- Remote communication has more failure scenarios than local
 - Messages can be delivered exactly once rather than at most once
- OS typically provides a rendezvous (or matchmaker) service to connect client and server





Execution of RPC





Examples of IPC Applications

- X Server and client
 - Unix-domain sockets, named pipes, ...
- Piping commands in shell
 - pipe
- Database server
 - Socket, RPC
- Web services
 - Kind of RPC
- **-** ...



End of Chapter 3

