Operating Systems

Isfahan University of Technology Electrical and Computer Engineering Department 1400-1 semester


Zeinab Zali

Session 24: Page Replacement and Allocation



First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)




15 page faults

- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
 - Belady's Anomaly
- How to track ages of pages?
 - Just use a FIFO queue






FIFO Illustrating Belady's Anomaly








Optimal Algorithm


- Replace page that will not be used for longest period of time
 - 9 is optimal for the example
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs





Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page



- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?





LRU Algorithm (Cont.)

- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to find smallest value
 - Search through table needed
- Stack implementation
 - Keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed (for 6 virtual page)
 - But each update more expensive
 - No search for replacement
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly







Use Of A Stack to Record Most Recent Page References

reference string





stack before a



stack after b






LRU Approximation Algorithms

- LRU needs special hardware and still slow
- Reference bit
 - With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
 - Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however
- Second-chance algorithm
 - Generally FIFO, plus hardware-provided reference bit
 - Clock replacement
 - If page to be replaced has
 - ► Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules





Second-Chance (clock) Page-Replacement Algorithm







Allocation of Frames

- Each process needs *minimum* number of frames
 - The minimum number of frames is defined by the computer architecture
 - we must have enough frames to hold all the different pages that any single instruction can reference.
- Maximum of course is total frames in the system
- Two major allocation schemes
 - fixed allocation
 - priority allocation
- Many variations





Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$-s_i$$
 = size of process p_i


$$-S = \sum S_i$$

-m = total number of frames

$$-a_i$$
= allocation for $p_i = \frac{s_i}{S} \times m$

$$m=64$$

 $s 1=10$
 $s_2=127$
 $a_1 = \frac{10}{137} \times 62 \approx 4$
 $a_2 = \frac{127}{137} \times 62 \approx 57$



Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process P_i generates a page fault,
 - select for replacement one of its frames (local replacement)
 - select for replacement a frame from a process with lower priority number (global replacement)





Global vs. Local Allocation

- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory






Reclaiming Pages

- A strategy to implement global page-replacement policy
- All memory requests are satisfied from the free-frame list, rather than waiting for the list to drop to zero before we begin selecting pages for replacement,
- Page replacement is triggered when the list falls below a certain threshold.
- This strategy attempts to ensure there is always sufficient free memory to satisfy new requests.





Reclaiming Pages Example









Non-Uniform Memory Access

- So far, we assumed that all memory accessed equally
- Many systems are NUMA speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- NUMA multiprocessing architecture
- Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled









Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
- Thrashing = a process is busy swapping pages in and out






Thrashing (Cont.)








Demand Paging and Thrashing

- Why does demand paging work?
 Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Why does thrashing occur?
 Σ size of locality > total memory size
 - Limit effects by using local or priority page replacement





Locality In A Memory-Reference Pattern







Allocating Kernel Memory

- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - As a result, the kernel must use memory conservatively and attempt to minimize waste due to fragmentation
 - Some kernel memory needs to be contiguous
 - ▶ i.e., for device I/O



End of Chapter 9

