

# **Grid System**

**Bootstrap** 





### Table of Content

Grid System







## Bootstrap (Grid System)

- Bootstrap's grid system uses a series of containers, rows, and columns to layout and align content
- Bootstrap grid system is built with flexbox
- It allows up to 12 columns across the page
- The columns can also be grouped to create wider columns
- Bootstrap grid system is responsive
- Columns are re-arranged automatically based on screen size



# Bootstrap (Grid Classes)

Class Prefix	Target device	Screen width
.col-	Extra small	< 576px
.col-sm-	Small	>= 576px
.col-md-	Medium	>= 768px
.col-lg-	Large	>= 992px
.col-xl-	Extra Large	>= 1200px

\*sm, md, lg or xl represents responsiveness breakpoints



### Bootstrap (Grid - media query)

- Extra small devices (portrait phones, less than 576px)
  - No media query since this is the default in Bootstrap
- Small devices (landscape phones, 576px and up)
  - @media (min-width: 576px) { ... }
- Medium devices (tablets, 768px and up)
  - @media (min-width: 768px) { ... }



## Bootstrap (Grid Classes)

- Large devices (desktops, 992px and up)
  - @media (min-width: 992px) { ... }
- Extra large devices (large desktops, 1200px and up)
  - @media (min-width: 1200px) { ... }



### Bootstrap (Grid - Container)


- Containers provide a means to centre and horizontally pad your site's contents
- A container shall contain rows

Class	Description
.container	For a responsive pixel width
.container-fluid	For 100% width across all viewport and device sizes



#### (Grid - Fix width container)


 Responsive, fixed-width container (meaning its max-width changes at each breakpoint)





#### (Grid - Fluid width container)

- Fluid-width (meaning it's 100% wide all the time)
  - Class ".container-fluid"





### Bootstrap (Grid - Row)

- Rows are wrappers to contain columns
- Padding (container) is counteracted on the rows with negative margins (in row)




## Bootstrap (Grid - Column)

- Column widths are set in percentages, so they're always fluid and sized relative to their parent element
- Each column has horizontal padding (called a gutter) for controlling the space between them
- This way, all the content in columns is visually aligned down the left side
- You can remove the margin from rows and padding from columns with .no-gutters on row




### Bootstrap (Grid – Column with gutter)






### Bootstrap (Grid – Column with no gutter)





# Bootstrap (Grid)





### Bootstrap (Grid – column classes)

Class	Description
col	Classes to create equal size all devices horizontal columns
col-auto	Classes to create columns with natural width of their content
col-{number}	Classes to create equal/unequal size all devices horizontal columns
col-{breakpoint}	Classes to create equal size stackable columns
<pre>col-{breakpoint}- {number}</pre>	Classes to create equal/unequal size stackable columns
col-{breakpoint}- auto	Classes to create stackable columns with natural width of their content



#### (Grid - Breakpoints)

- There are five grid breakpoints, one for each responsive breakpoint
  - All breakpoints (extra small)
  - Small
  - Medium
  - Large
  - Extra large



#### (Grid - Breakpoints)

- Grid breakpoints are based on minimum width media queries
- They apply to that one breakpoint and all those above
- Example : .col-sm-4 applies to small, medium, large, and extra large devices, but not the first xs device



#### (Grid – All breakpoints)


- .col or .col-{number} classes :
  - Number range 1 ~ 12
  - For grids that are the same from the smallest of devices to the largest

```
Example :
  <div class="col"> </div>
  <div class="col-4"> </div>
```



#### (Grid – two equal width columns)


- Column classes indicate the number of columns you'd like to use out of the possible 12 columns per row
- ".col" or ".col-6" can be used for two equal-width columns





#### (Grid – three equal width columns)

- Column classes indicate the number of columns you'd like to use out of the possible 12 columns per row
- ".col" or ".col-4" can be used for three equal-width columns





#### (Grid – Auto-layout columns - Stackable)


- .col-{breakpoint} classes
  - Create a basic grid system that starts out stacked before becoming horizontal with at the breakpoint

```
Example :
<div class="col-sm"> </div>
```



#### (Grid – three equal width stackable columns)

- Add any number of unit-less classes for each breakpoint you need and every column will be the same width
- On mobile phones or screens that are less than 576px wide, the columns will automatically stack on top of each other





#### (Grid – Stackable columns)


- .col-{breakpoint}-{number} classes
  - Number could be 1 ~ 12
  - Create a basic grid system that starts out stacked before becoming horizontal with at the breakpoint

```
Example :
<div class="col-sm-4"> </div>
```




(Grid – three equal columns with breakpoint)

 On mobile phones or screens that are less than 576px wide, the columns will automatically stack on top of each other





(Grid – two unequal columns with breakpoint)





#### (Grid – Variable width content)

- col-{breakpoint}-auto classes :
  - To size columns based on the natural width of their content

```
Example :
<div class="col-md-auto"> </div>
```



#### (Grid – Vertical Alignment)


- Use flexbox alignment utilities to vertically and horizontally align columns
- <div class="row align-items-start">

col-sm col-sm



## Bootstrap (Grid – Vertical Alignment)


<div class="row align-items-center">





## Bootstrap (Grid – Vertical Alignment)


<div class="row align-items-end">





### Bootstrap (Grid – Horizontal Alignment)

<div class="row justify-content-start">





### Bootstrap (Grid – Horizontal Alignment)


<div class="row justify-content-centre">





## Bootstrap (Grid – Horizontal Alignment)

<div class="row justify-content-end">











#83, Farah Towers, 1st floor, MG Road,

Bangalore - 560001

M: +91-80-4128 9576

T: +91-98862 69112

E: info@www.webstackacademy.com









