

What does SevenShield do?

SevenShield encrypts folders and files on your computer. Locked content can only be opened again with your password or the matching recovery key. This also applies if the computer is lost or stolen. Your data never leaves your computer.

The buttons at a glance

If you briefly hover the mouse over a button, SevenShield shows what it does.

	Add folder...	Selects a folder and adds it to the list.
	Add file...	Selects one or more files. Alternatively, you can simply drag folders and files into the window.
	Scan...	Searches a folder for items that are already locked and adds them to the list.
	Remove	Removes the marked items from the list. The folders and files themselves remain unchanged.
	Show password	Shows or hides the password you entered.
	Use existing recovery key	Optional: an existing recovery key is used instead of a new one.
	Lock / Unlock	The main button. The icon shows what happens when you click: closed padlock to lock, open padlock to unlock.

1. Installation and activation

Step 1: Install SevenShield

Run the installer and follow the instructions. At the end, you can start SevenShield right away.

Step 2: Activate the program

On first launch, SevenShield shows a device code. Send it to the seller with “Send by email”. You will receive a license file in return, which you select with “Select license file...”. SevenShield is then ready to use.

2. Lock folders or files

Step 1: Add

Add folders or files using the buttons on the right, or drag them into the window.

Step 2: Set a password

Enter a password with at least 12 characters and repeat it in the second field. The indicator next to the field rates its strength from “Weak” to “Strong”.

Step 3: Lock

Click the blue button with the padlock and confirm the prompt with “Yes”.

Step 4: Save the recovery key

SevenShield then shows a separate recovery key for each item. Save it with “Copy all” or “Save as text file...”, tick the checkbox and click “Close”.

Keep the key separate from the password and not in the same folder as the locked data. It is shown only this one time.

Important: Either the password or the recovery key is enough to unlock. Without either, the data cannot be recovered.

3. Unlock and open

Step 1: Item in the list

Locked items are marked by a closed padlock in the list and in the status line. If the item is missing, bring it into the list with “Add” or “Scan...”.

Step 2: Enter the password

Enter the password that was used to lock the item.

Step 3: Unlock

Click the blue button with the open padlock.

Step 4: Open

Double-click the item to open the file in the matching program or the folder in Explorer. Right-clicking also offers “Show in Explorer”.

4. Several items at once

Hold down the Ctrl key to mark several items and process only those. If nothing is marked, SevenShield processes all items in the list.

- A password only works for items that were locked with exactly this password.
- If locked and unlocked items are mixed, the main button shows two arrows. One click locks the unlocked items and unlocks the locked ones.
- If several items are newly locked, you get an overview of all new recovery keys at the end.

5. Forgot your password?

If exactly one locked item is in the list, the link “Forgot your password? Unlock with recovery key” appears below the password field. Click it and enter the saved key. Remove any other items from the list first with “Remove”.

Good to know

- While SevenShield is working, the program cannot be closed. This way, no half-processed data is left behind.
- The language follows your Windows setting: German, English, French or Italian.

In short

- **Lock:** Add → set password → padlock button → save key
- **Unlock:** item in the list → enter password → padlock button → double-click to open
- **Forgot your password:** use the recovery key