
This website stores cookies on your computer. These cookies are used to improve your website experience and provide more personalized services to you, both on this website and through other media. To find out more about the cookies we use, see our Privacy Policy.

We won't track your information when you visit our site. But in order to comply with your preferences, we'll have to use just one tiny cookie so that you're not asked to make this choice again.

Accept

Decline

July 12, 2021



By the next release (1.5), the Istio operator command was added to the Istio CLI, and the Istio operator is the topic of this blog post.


What is an Istio operator?

The operators and the operator pattern are a way to automate repeatable tasks. In Kubernetes, an operator uses custom resources and a controller to manage applications and their components.



Istio operator manages all aspects of the Istio service mesh installations. Instead of manually maintaining the Istio mesh installation and Istio CLI versions, you can use the Istio operator.

Istio operator consists of an application deployed to the Kubernetes cluster and a custom resource called IstioOperator that describes the desired state of your Istio installation. The operator uses the IstioOperator resource to manage and maintain your Istio service mesh installation.



Initializing the operator using Istio CLI

Using the Istio CLI and the *istioctl operator init* command, we can deploy the Istio operator controller to the Kubernetes cluster.

Running the *init* command creates the custom resource definition for the operator, the operator controller deployment, the service to access operator metrics, necessary Istio operator role-based access control (RBAC) rules, and the namespaces the operator is supposed to watch.

What can be configured?

As part of the initialization, we can configure the following:

 Namespace in which the operator gets installed (by default, it's installed in the istio-operator namespace)

- Namespaces the operator watches (if not provided, istio-system is the only watched namespace)
- Revision and tag strings for the operator

Once the operator is installed and running, it needs a custom resource to tell it how to install Istio. This resource is called IstioOperator, and it tells the operator how to install Istio.

Here's an example of an IstioOperator resource:

```
1apiVersion: install.istio.io/v1alpha1
2kind: IstioOperator
3metadata:
4 namespace: istio-system
5 name: custom-minimal-installation
6spec:
7 profile: minimal
8 hub: grc.io/my-custom-istio
9 tag: 1.0.1
10revision: custom-1-0-1
11meshConfig:
12 accessLogEncoding: JSON
13components:
14 pilot:
      k8s:
15
16
        resources:
17
           requests:
             memory: 3072Mi
iop-example1.yaml hosted with ♥ by GitHub
                                                                                             view raw
```

With the resource, we can configure which Istio installation profile we want to use, a custom Istio Docker image, global mesh settings, and settings for each component, such as the gateways and the pilot.




What are Istio installation configuration

profiles?


The installation profiles are built-in configuration profiles we can use to install Istio. There are six different profiles: default, demo, minimal, external, empty, and preview. Each of the profiles provides customization of the Istio control plane and the sidecars. You can read more about the differences between profiles in the Installation Configuration Profiles documentation.


For the operator to install Istio, we have to deploy the IstioOperator into one of the Istio operator controller watches. If we don't provide the watched namespaces explicitly, the Istio operator controller will monitor the *istio-system* namespace. That means we can deploy the IstioOperator resource to the *istio-system* namespace.



Istio operator controller watching IstioOperator resources in the watched namespaces

The controller gets notified of the new IstioOperator resource in the namespace. It will process it to figure out what it needs to install or update and begin installing the Istio service mesh based on the resource configuration.





Controller updating Istio installation

Usually, it takes at most 90 seconds for the controller to pick up the changes from the resource and then about two minutes for it to completely install lstio.


You can monitor the progress by listing the IstioOperator resource as shown in the example below:


```
$ kubectl get iop --all-namespaces
NAMESPACE NAME REVISION STATUS A
istio-system my-installation HEALTHY 1
```

Additionally, if we want to see more details, we can look at the logs from the Istio operator deployment.

Controlling Istio installation using the operator

This shouldn't come as a surprise, but you can control every aspect of your Istio installation through the operator. For example, do you want to switch the installation from the demo profile to the default profile? It's straightforward. Update the *profile* field in the IstioOperator and re-deploy the resource. The controller will do the job of bringing the existing Istio installation to the desired state, expressed in the IstioOperator resource.





Removing an egress gateway

Consider the diagram above where we decided to disable the egress gateway by setting the enabled field to false. After we've deployed the updated IstioOperator resource, Kubernetes notified the Istio operator controller about the change in the resource. Then it went to work to remove the egress gateway while keeping the rest of the components intact.

How to configure the Istio operator

Let's take a look at which aspects of the Istio installation we can configure in the operator resource by breaking it down into three sections:

- · Global configuration
- Mesh configuration
- Component configuration

One way to discover the configuration of different Istio profiles is by running the *istioctl profile dump* command. This command will output the YAML representation of any Istio installation profile, and it can give us insight into different configurations.

Global configuration

The global configuration includes the top-most fields in the resource. It allows us to configure things such as the installation profile name, the path to the installation package, the root Docker image path, Docker image tags, the namespace to install control plane resources into, revision, and others.

1apiVersion: install.istio.io/v1alpha1

2kind: IstioOperator

3metadata:

4 namespace: istio-system

```
5 name: custom-minimal-installation
6spec:
7 profile: minimal
8 hub: grc.io/my-custom-istio
9 tag: 1.0.1
10 revision: custom-1-0-1

iop-example-global.yaml hosted with ♥ by GitHub
```

For example, the IstioOperator resource above will use the minimal profile, a custom Docker registry, and revision.

Mesh configuration

The mesh configuration or the settings under the *meshConfig* field contain the internal configuration of the control plane components.

For example, you could configure things such as the access log format, log encoding, enable or disable tracing, or change the root namespace.

```
1apiVersion: install.istio.io/v1alpha1

2kind: IstioOperator

3metadata:

4 namespace: istio-system

5 name: demo-installation

6spec:

7 profile: demo

8 meshConfig:

9 accessLogEncoding: JSON

wiew raw
```

The *meshConfig* is also the spot where you could set the default Envoy proxy configuration, things such as outbound traffic policy, discovery selectors, inbound and outbound cluster stat prefixes, trust domains, and more.

Component configuration

The component configuration allows us to adjust Kubernetes resource settings, enable or disable individual components and configure component-specific settings. The components we can configure are the following:

- Pilot (pilot)
- Container network interface (cni)

- Ingress gateways (ingressGateways)
- Egress gateways (egressGateways)

Each component also has a *k8s* field that allows us to configure Kubernetes resource settings. We can configure resource requests and limits, update annotations and environment variables in the Kubernetes deployment, configure readiness probes, replica counts, and anything else you could configure in the Kubernetes resource.

Additionally, we can provide a list of patches for the Istio operator to apply to the resource through overlays.

```
1apiVersion: install.istio.io/v1alpha1
2kind: IstioOperator
3metadata:
4 namespace: istio-system
5 name: custom-install
6spec:
   profile: default
   components:
     pilot:
       k8s:
10
         resources:
11
12
            requests:
              memory: 2048Mi
13
     ingressGateways:
     - name: istio-ingressgateway
       enabled: false
iop-example2.yaml hosted with ♥ by GitHub
                                                                                              view raw
```

The example above shows how to modify the memory requests for the pilot component and disable the ingress gateway.

How to install an internal ingress gateway using Istio operator

Let's look at an example of how to use the Istio operator to install Istio. After installing Istio, we'll create a second IstioOperator to install an additional internal ingress gateway.

The example assumes that you have access to a Kubernetes cluster.

To get started, we'll initialize the Istio operator first. To do that, we can run the following command:

```
$ istioctl operator init
Installing operator controller in namespace: istio-operator using im
Operator controller will watch namespaces: istio-system
✓ Istio operator installed
✓ Installation complete
```

The init command will create the operator in the *istio-operator* namespace and the namespaces for the operator to watch. Since we haven't provided any namespaces for the operator to manage, it defaults to the *istio-system* namespace.

If you list the Pods in the *istio-operator* namespace using `kubectl get po -n istio-operator` you'll see the Pod that runs the Istio operator controller.

Creating the IstioOperator resource

Next, we can create the IstioOperator resource to install Istio. We'll use the *default* profile. The default profile includes the Istio control plane (*istiod*) and a public ingress gateway (*istio-ingressgateway*):

```
1apiVersion: install.istio.io/v1alpha1

2kind: IstioOperator

3metadata:

4 namespace: istio-system

5 name: default-installation

6spec:

7 profile: default

default-iop.yaml hosted with ♥ by GitHub

view raw
```

Save the above YAML to the *default-installation.yaml* file and create the resource with *kubectl apply -f default-installation.yaml*.

To check the status of the Istio operator installation, you can list the Istio operator

```
$ kubectl get iop -A
NAMESPACE NAME REVISION STATUS A
istio-system default-installation HEALTHY 2
```

Once the status of the Istio operator resource changes to HEALTHY, we can create a namespace called *internal* and an IstioOperator resource to install an internal gateway into that namespace.

```
$ kubectl create ns internal
namespace/internal created
```

Now we can create another operator that installs an internal gateway to that namespace:

```
1apiVersion: install.istio.io/v1alpha1
2kind: IstioOperator
3metadata:
4 namespace: istio-system
5 name: internal-gw
6spec:
7 profile: empty
   components:
9
     ingressGateways:
10
        - namespace: internal
          name: ilb-gateway
11
          enabled: true
12
          label:
13
            istio: internal-ingressgateway
14
15
          k8s:
             serviceAnnotations:
16
17
               networking.gke.io/load-balancer-type: "Internal"
internal-gw-iop.yaml hosted with \bigcirc by GitHub
                                                                                                view raw
```

Save the above YAML to *internal-gw.yaml* and deploy it using *kubectl apply -f internal-gw.yaml*.

Just like before, we can check the status by listing the operator resources in all namespaces with *kubectl get iop -A*.

```
$ kubectl get iop -A
NAMESPACE NAME REVISION STATUS AGE
istio-system default-installation HEALTHY 73s
istio-system internal-gw HEALTHY 14s
```

If we look at the services with *kubectl get svc -n internal* you'll notice that the external IP address is a private IP address that's only accessible within the same network.

Let's also create a Gateway resource for this internal ingress gateway:

```
1apiVersion: networking.istio.io/v1alpha3
2kind: Gateway
3metadata:
4 name: internal-gateway
5 namespace: internal
6spec:
7 selector:
     istio: internal-ingressgateway
9 servers:
10
   - port:
        number: 80
11
        name: http
12
        protocol: HTTP
13
     hosts:
14
         _ 1*1
internal-gw.yaml hosted with ♥ by GitHub
                                                                                        view raw
```

Save the above YAML to the *internal-gateway.yaml* file and create it using *kubectl* apply -f internal-gateway.yaml.

We'll use the *httpbin* as an example workload in the *internal* namespace. Let's label the namespace for injection and then deploy httpbin to that namespace:

```
kubectl label ns internal istio-injection=enabled
kubectl apply -f https://raw.githubusercontent.com/istio/istio/maste
```

Finally, we can create the VirtualService and attach the *internal-gateway* resource to it:

```
1apiVersion: networking.istio.io/v1alpha3
2kind: VirtualService
3metadata:
4 name: httpbin
5 namespace: internal
6spec:
7 hosts:
9 gateways:
    - internal-gateway
11 http:
12
     - route:
        - destination:
13
             host: httpbin.internal.svc.cluster.local
14
             port:
15
               number: 8000
16
vs-httpbin.yaml hosted with \bigcirc by GitHub
                                                                                                view raw
```

Save the above YAML to *httpbin-vs.yaml* file and create it using *kubectl apply -f httpbin-vs.yaml*.

We've now created an internal ingress gateway that's only accessible through the same network your Kubernetes cluster is running in.

To test the internal gateway, you can create a VM instance, SSH into the instance, and run *curl* [internal-gateway-IP] to access the httpbin service running in the cluster.



Conclusion

The Istio installation experience has come a long way. The latest iteration of the experience involves a custom resource called IstioOperator. Using the operator removes the need for managing different CLI versions and delegates this responsibility to an operator running within the Kubernetes cluster. This blog post explained what Istio operator is, how it works, and what components can be configured within the IstioOperator resources. To learn more about the Istio operator and how it works, check out one of these resources:

- Istio operator documentation
- Istio operator source code

Author(s)




Peter Jausovec

You May Also Like









ISTIO, MTLS, SERVICE MESH, ZERO TRUST

How Istio's mTLS
Traffic Encryption
Works as Part of a
Zero Trust Security
Posture

BY JIMMY SONG , DECEMBER 7, 2022



ISTIO, SERVICE MESH

L7 Traffic Path in Ambient Mesh

BY JIMMY SONG , DECEMBER 6, 2022



AWS, ISTIO, ISTIO DISTRO, SERVICE MESH

Announcing Tetrate
Istio Distro
Deployment through
EKS add-ons:
Simplifying Istio on
EKS

BY PETR MCALLISTER, NOVEMBER 28, 2022



Products

Tetrate Service Bridge

Tetrate Istio Subscription

Resources

Tetrate Academy

Tetrate Library

Zero Trust Architecture

Free eBook: SkyWalking

Blog

Company				
About Us				
Partners				
Events				
Open Source				
Press				
Contact Us				
Сор	vright © Tetrate 2023. All rigl	nts reserved. <u>Terms</u>	and Conditions and	<u>Privacy</u>