

COURSE NOTES

FOUNDATIONS OF SOLID MECHANICS

Hanfeng Zhai

Disclaimer: These notes are intended solely for personal reference and study purposes. They represent my own understanding of the course material and may contain errors or inaccuracies. The content presented here should not be considered as an authoritative source, and reliance solely on these materials is not recommended. If you notice any materials that potentially infringe upon the copyright of others, please contact me at hz253@cornell.edu so that appropriate action can be taken. Your feedback is greatly appreciated.

2021

Week 1: Mon: 8/29/2021


Vectors & tensors. \rightarrow Cartesian.

in Physics, we are familiar with

$$\left\{ \begin{array}{l} \nabla \times \vec{E} = 0 \\ \nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0} \end{array} \right. \Rightarrow \text{Electro- statics}$$

which is, independent of coordinate system

in a RH coordinate,



$$\vec{v} = \sum_{i=1}^3 v_i \vec{e}_i$$

Index subscript $\leftarrow \vec{e}_i \cdot \vec{e}_j = \delta_{ij} = \begin{cases} 1, & i=j \\ 0, & i \neq j \end{cases}$

Called Kronecker delta.


(in orthonormal basis).

Here, v_i is component of \vec{v}


with a basis $\{\vec{e}_i\}$.

$$= \sum_{j=1}^3 v_j \vec{e}_j$$

transformation of basis.



summation convention



term: subscripts. $a_{ij} b_k c_m \rightarrow$ free indices.

Summing over j

contraction, if $i=m$.

$\alpha_{ip} b_k c_p \rightarrow$ double summation

*** A dummy index cannot repeat more than 2!!!

$$\delta_{ij} \delta_{jk} = \delta_{ik} = \delta_{ik}$$

$$\begin{aligned} \text{e.g. } \delta_{ij} \delta_{jk} &= \delta_{ii} \delta_{kk} + \delta_{i2} \delta_{2k} + \delta_{i3} \delta_{3k} \\ &= \delta_{kk} \end{aligned}$$

δ_{2k} ($i=2$), δ_{3k} ($i=3$).

$$\begin{aligned} \vec{v} \cdot \vec{w} &= v_i \vec{e}_i \cdot w_j \vec{e}_j = v_i w_j (\vec{e}_i \cdot \vec{e}_j) \\ &\quad \underbrace{\delta_{ij}}_{= v_i w_i = v_j w_j} \end{aligned}$$

usual dot product


Cross product

$$\vec{v} \times \vec{w} = v_i \vec{e}_i \times w_j \vec{e}_j = v_i w_j \vec{e}_i \times \vec{e}_j \quad (a)$$

$$\vec{e}_i \times \vec{e}_j = [(\vec{e}_i \times \vec{e}_j) \cdot \vec{e}_k] \vec{e}_k$$

free index on two sides of Eqn. must
be equal !!! $= \epsilon_{ijk}$ (Permutation symbol)

e.g.



$$(\vec{e}_1 \times \vec{e}_2) \cdot \vec{e}_3 = 1.$$

$$w_{ijk} = 1, (1, 2, 3), (3, 1, 2), (2, 3, 1).$$

$$= -1, (2, 1, 3), (1, 3, 2), (3, 2, 1).$$

$$= 0, \text{ otherwise}.$$

Review ~~on~~ undergrad linear algebra
 $\det(\sim)$.

Eq. (a) writes. $v_i w_j w_{ijk} \vec{e}_k$
 $\Rightarrow w_{ijk} v_i w_j \vec{e}_k$
 $= w_{klj} v_i w_j \vec{e}_k$

Q. $\vec{a} \times (\vec{b} \times \vec{c}) = ?$

$$\begin{aligned} &= a_k \vec{e}_k \times (b_i c_j \vec{e}_i \times \vec{e}_j) \\ &= a_k \vec{e}_k \times (b_i c_j w_{ijm} \vec{e}_m) \\ &= a_k b_i c_j (\delta_{iw} \delta_{jk} - \delta_{ik} \delta_{jw}) \vec{e}_m \end{aligned}$$

$$= (a_i \vec{e}_i) \times [w_{ijk} b_j c_k \vec{e}_p]$$

$$= (\delta_{ij} \delta_{ik} - \delta_{ik} \delta_{ij}) a_i b_j c_k \vec{e}_p$$

$$= (b_s a_k c_k - b_i a_i c_s) \vec{e}_p$$

$$= [b_s (\vec{a} \cdot \vec{c}) = (\vec{a} \cdot \vec{b}) c_s] \vec{e}_p$$

$$= (\vec{a} \cdot \vec{c}) b_s - (\vec{a} \cdot \vec{b}) c_s$$

• How vectors transform? (on basis)

$$\vec{v} = v_i \vec{e}_i = v'_j \vec{e}'_j$$

$$v'_j = (\vec{v} \cdot \vec{e}'_j) = (v_i \vec{e}_i \cdot \vec{e}'_j)$$

$$= v_i (\vec{e}_i \cdot \vec{e}'_j)$$

$$P_{ji} \equiv \vec{e}'_j \cdot \vec{e}_i$$

projection of one basis on another basis.

$$\vec{v}' = P_{ji} \cdot \vec{v} = \vec{v}$$

$$\vec{v}' = \begin{pmatrix} v'_1 \\ v'_2 \\ v'_3 \end{pmatrix} \quad \vec{v} = \begin{pmatrix} v_1 \\ v_2 \\ v_3 \end{pmatrix} \quad \vec{P} = [P_{ji}]$$

$$\vec{v}' = \vec{P} \vec{v}$$

$$\vec{v} = \vec{P}^{-1} \vec{v}'$$

$$\vec{P}^{-1} = \vec{P}^t$$

Week 1:, Wed.

9/1/2021


Second order Tensor $\underline{\underline{A}}$.

A 2nd order tensor is a linear transformation from E^3 to E^3

$\underline{\underline{A}}$ T = a special kind of mapping $E^3 \rightarrow E^3$
properties:

$\underline{\underline{A}}(\underline{u})$ to some vector

$\underline{\underline{A}}: (\underline{u}) \rightarrow \underline{\underline{A}}(\underline{u}).$



$$\rightarrow \underline{\underline{A}}(a\underline{u}) = a \underline{\underline{A}}(\underline{u}).$$

\nwarrow real No.

$$\rightarrow \underline{\underline{A}}(\underline{u} + \underline{w}) = \underline{\underline{A}}(\underline{u}) + \underline{\underline{A}}(\underline{w}).$$

↑

$$\underline{\underline{A}}(au + bw) = a\underline{\underline{A}}(\underline{u}) + b\underline{\underline{A}}(\underline{w}).$$

$\forall \underline{u}, \underline{w} \in E^3$ and a, b .

$$\underline{\underline{A}}(\underline{0}) = \underline{\underline{0}}.$$

Example rigid body rotation about a fixed point.

Defination gradient tensor

Stress tensor

$$\underline{x} = x_i \vec{e}_i$$

$$\underline{A}(\underline{x}) = \underline{A}(x_j \vec{e}_j)$$

$$= \sum x_j \underline{A}(\vec{e}_j)$$

this tells us that a linear transformation is completely determined by its action on the basis vectors.

$$\underline{A}(\vec{e}_j) = a_{ij} \vec{e}_i$$

$$a_{ij} \vec{e}_i (\vec{e}_j \cdot \underline{x})$$

$$\underline{A}(x_j \vec{e}_j) = \sum x_j \underline{A}(\vec{e}_j) = a_{ij} x_j \vec{e}_i$$

$$\underline{A}(\vec{e}_1) \cdot \underline{e}_1 = a_{11}$$

$$\underline{A}(\vec{e}_1) \cdot \underline{e}_2 = a_{12}$$

$$\underline{A}(\vec{e}_1) \cdot \underline{e}_3 = a_{13}$$

$$A = \begin{bmatrix} Aa_{11} & a_{12} & a_{13} \\ a_{21} & Aa_{22} & a_{23} \\ a_{31} & a_{32} & Aa_{33} \end{bmatrix}$$

$$\underline{A}(\underline{x}) = a_{ij} \vec{e}_i (\vec{e}_j \cdot \underline{x})$$

$$= a_{ij} \underbrace{\vec{e}_i \vec{e}_j}_{\underline{A}} \cdot \underline{x}$$

Define \underline{ab} as the linear transformation

$$(\underline{ab})(\underline{x}) = a(b \cdot \underline{x}). \quad ??$$

check: this is - a LT.

$$= \underline{A} \cdot \underline{x} \quad (\text{we can skip the dot}). \quad ??$$

$\underline{ab} \rightarrow$ dyad

*** Any linear transformation can be written as sum of dyad

$\underline{ab} \Leftrightarrow \underline{a} \otimes \underline{b} \rightarrow$ linear transformation

A simple representation: $\underline{A} = a_{ij} \vec{e}_i \vec{e}_j$

$\underline{ab} \neq \underline{ba}$

$$\underline{e}_i \rightarrow \underline{e}'_i$$

$$\underline{A} = a_{ij} \underline{e}_i \underline{e}_j = a_{rs} \underline{e}'_r \underline{e}'_s$$

$$= a_{ij} (\underbrace{\underline{e}_i \cdot \underline{e}'_r}_{\underline{e}_i} \underbrace{\underline{e}'_r \cdot \underline{e}'_s}_{\underline{e}_j}) \underline{e}'_s$$

$$= a_{ij} (\underbrace{\underline{e}_i \cdot \underline{e}'_r}_{P_{ri}}) (\underbrace{\underline{e}'_r \cdot \underline{e}'_s}_{P_{sj}})$$

$$= a'_{rs} \underline{e}'_r \underline{e}'_s$$

$$a'_{rs} = a_{ij} P_{ri} P_{sj}$$

$$[\underline{P}\underline{A}]_j [\underline{P}^T]_{js}$$

$$\underline{A}' = \underline{P}\underline{A}\underline{P}^T \quad \underline{P}^T\underline{A}'\underline{P} = \underline{A}$$

$$\underline{[a'_{rs}]}$$

$$\underline{\underline{A}}(\underline{x}) = \underline{\underline{y}}$$

$$\det \underline{\underline{A}} \equiv \det A$$

$$\begin{aligned} \det A &= \det (\underline{P}^T \underline{A}' \underline{P}) = \det \underline{P}^T \det \underline{A}' \det \underline{P} \\ &= \det (\underline{P}^T \underline{P}) \det \underline{A}' \\ &\quad \text{I} \\ &= \det \underline{A}' \end{aligned}$$

$\star \star \star$ Det is invariant

$$(\underline{a}\underline{A} + \underline{b}\underline{B})(\underline{x}) \equiv a\underline{A}(\underline{x}) + b\underline{B}(\underline{x})$$

composition $\underline{\underline{A}}^{-1}$ of mapping.

$$(\underline{A} \circ \underline{B})(\underline{x}) \equiv \underline{A}(\underline{B}(\underline{x}))$$

$$= \underline{A} \circ (\underline{B} \circ \underline{x}).$$

$$\underline{B} \cdot \underline{x} = b_{ij} \underline{e}_i \underline{e}_j \cdot \underline{x}$$

$$\underline{A} \cdot (\underline{B} \cdot \underline{x}) = (a_{rs} \underline{e}_r \underline{e}_s) \cdot b_{ij} \underline{e}_i \underline{e}_j \cdot \underline{x}$$

$$= a_{rs} \underline{e}_r \underbrace{b_{ij} (\underline{e}_s \cdot \underline{e}_i)}_{\delta_{si}} \underline{e}_j \cdot \underline{x}$$

$$= a_{rs} b_{sj} \underline{e}_r \underline{e}_j \cdot \underline{x}$$

$$[\underline{C}] = C \quad C = AB$$

$$\underline{\underline{A}}^{-1} \circ \underline{\underline{A}} = \underline{\underline{I}}$$

$$\underline{\underline{I}} = \delta_{ij} \underline{e}_i \underline{e}_j = \underline{e}_i \underline{e}_i$$

↓
identity tensor.

$\underline{\underline{A}}^T$: transpose of $\underline{\underline{A}}$.

$$\underline{v} \cdot \underline{\underline{A}}^T \cdot \underline{u} = \underline{u} \cdot \underline{\underline{A}} \cdot \underline{v}$$

for all \underline{u} & \underline{v} in \mathbb{R}^3

$$\underline{u} = \underline{e}_j$$

$$\underline{v} = \underline{e}_i$$

$$\left\{ \begin{array}{l} \underline{e}_j \cdot \underline{\underline{A}} \cdot \underline{e}_i \\ = \underline{e}_j \cdot \text{ars} \underbrace{\underline{e}_r \underline{e}_s}_{\delta_{ri}} \cdot \underline{e}_i \\ = \text{ars} \delta_{jr} \delta_{si} = a_{ji}. \end{array} \right.$$

$$\underline{e}_i \cdot \underline{\underline{A}}^T \cdot \underline{e}_j = \underline{a}_{ij}^T = a_{ji}.$$

true for 1 coord.

true for all ~

$$(\underline{\underline{A}} + \underline{\underline{B}})^T = \underline{\underline{A}}^T + \underline{\underline{B}}^T$$

$$(\underline{\underline{A}}^T)^T = \underline{\underline{A}}$$

$$(\underline{\underline{A}}^{-1})^T = (\underline{\underline{A}}^T)^{-1}$$

$$(\underline{\underline{A}} \circ \underline{\underline{B}})^T = \underline{\underline{B}}^T \circ \underline{\underline{A}}^T$$

$$\underline{\underline{A}}^T = \underline{\underline{A}} \quad \text{symmetric}$$

$$\underline{\underline{A}}^T = -\underline{\underline{A}} \quad \text{asymmetric} \rightarrow \text{mechanics of solids.}$$

*** Eigenvalue of asymmetric tensor

$$\det(\underline{\underline{A}} - \lambda \underline{\underline{I}}) \rightarrow \text{independent of basis}$$

$$= \det(\underline{\underline{A}}' - \lambda \underline{\underline{I}})$$

$$= \det \left[\underbrace{\underline{\underline{P}} \underline{\underline{A}} \underline{\underline{P}}^T}_{\underline{\underline{A}}'} - \lambda \underline{\underline{I}} \right]. \quad \underline{\underline{P}} \underline{\underline{P}}^T = \underline{\underline{I}}$$

$$= \det \left[\underline{\underline{P}} (\underline{\underline{A}} - \lambda \underline{\underline{I}}) \underline{\underline{P}}^T \right]$$

$$= \underbrace{\det[\underline{\underline{P}} \underline{\underline{P}}^T]}_I \det(\underline{\underline{A}} - \lambda \underline{\underline{I}})$$

$$= \det(\underline{\underline{A}} - \lambda \underline{\underline{I}}).$$

$$\det(\underline{\underline{A}} - \lambda \underline{\underline{I}})$$

$$= P_3(\lambda) = -(-\lambda)^3 + I_1 \lambda^2 - I_2 \lambda + \det \underline{\underline{A}}$$

$$I_1 = \frac{1}{2} [(\text{tr}(\underline{\underline{A}}))^2 - \text{tr}(\underline{\underline{A}}^2)] \quad I_2 = a_{11} = \text{tr}(\underline{\underline{A}}). \quad \hookrightarrow a_{11} + a_{22} + a_{33}.$$

$$I_1, I_2, \det A$$

are scalar movement of the Tensor $\underline{\underline{A}}$

$$\underline{\underline{A}} = \lambda_1 \underline{\underline{E}_1} \underline{\underline{E}_1} + \lambda_2 \underline{\underline{E}_2} \underline{\underline{E}_2} + \lambda_3 \underline{\underline{E}_3} \underline{\underline{E}_3}$$

$$\underline{\underline{D}} = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_2 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix} = \underbrace{\{\underline{\underline{E}_i}\}}_{\text{eigenvectors of } \underline{\underline{A}}}$$

$$\det A = \lambda_1 \lambda_2 \lambda_3$$

$$I_2 = \lambda_1 + \lambda_2 + \lambda_3$$

$$I_1 = \lambda_1 \lambda_2 + \lambda_2 \lambda_3 + \lambda_1 \lambda_3$$

* how to diagonalize 3×3 matrix.

(Labor day - Monday).

Week 2: Wed

(Review)

$$\underline{\underline{A}}(\underline{v}) = \underline{\underline{A}} \cdot \underline{v}$$

$$\underline{\underline{A}} = a_{ij} \underline{\underline{e}_i} \underline{\underline{e}_j}$$

$$\underline{\underline{A}}(\underline{v}) = a_{ij} v_j \underline{\underline{e}_i}$$

$$= a_{ij} \underbrace{\underline{\underline{e}_i} \underline{\underline{e}_j} \cdot \underline{v}}_{\underline{v}_j}$$

$$(\underline{\underline{A}} \circ \underline{\underline{B}})(\underline{v}) = \underline{\underline{A}}(\underline{\underline{B}}(\underline{v}))$$

$$= (a_{ij} \underline{\underline{e}_i} \underline{\underline{e}_j})(b_{kl} v_k \underline{\underline{e}_l})$$

$$= a_{ij} b_{kl} v_k \underline{\underline{e}_i} \delta_{jk}$$

$$= a_{ij} b_{ji} v_k \underline{\underline{e}_i}$$

in other words,

$$\underline{\underline{A}} \circ \underline{\underline{B}} = a_{ij} b_{ji} \underline{\underline{e}_i} \underline{\underline{e}_l}$$

$$= \underline{\underline{A}} \otimes \underline{\underline{B}} =$$

$$\underline{\underline{A}} = a_{ij} \underline{\underline{e}_i} \underline{\underline{e}_j}, \quad \underline{\underline{B}} = b_{kl} \underline{\underline{e}_k} \underline{\underline{e}_l}$$

$$\underline{\underline{A}} \cdot \underline{\underline{B}} = a_{ij} \underline{\underline{e}_i} \underline{\underline{e}_j} \cdot b_{kl} \underline{\underline{e}_k} \underline{\underline{e}_l}$$

$$\underline{\underline{AB}} = \underline{\underline{A}} \circ \underline{\underline{B}}$$

AB

$$\underline{AB} : \underline{cd} \equiv (\underline{a} \cdot \underline{c})(\underline{b} \cdot \underline{d}).$$

$$\underline{ab} \cdots \underline{cd} \equiv (\underline{a} \cdot \underline{d})(\underline{c} \cdot \underline{b}).$$

$$\underline{A} = a_{ij} \underline{e}_i \underline{e}_j$$

$$\underline{B} = b_{kl} \underline{e}_k \underline{e}_l$$


$$\underline{A} : \underline{B} = (a_{ij} \underline{e}_i \underline{e}_j) : (b_{kl} \underline{e}_k \underline{e}_l).$$

$$\underline{A} : \underline{B} = a_{ij} b_{kl} (\underbrace{\underline{e}_i \cdot \underline{e}_k}_{\delta_{ik}})(\underbrace{\underline{e}_j \cdot \underline{e}_l}_{\delta_{jl}}).$$

$$= a_{kj} b_{kj} \rightarrow \text{scalar}$$

Can be extended to 2 angular relations of linear transformations.

e.g. for vectors



tr(A)

$$= a_{ij} (\underbrace{\underline{e}_i \cdot \underline{e}_j}_{\delta_{ij}}) = a_{ii}.$$

$$\underline{\text{tr}}(\underline{A} + \underline{B}) = \underline{\text{tr}} \underline{A} + \underline{\text{tr}} \underline{B}.$$

$$\underline{\text{tr}}(a \underline{A}) = a \underline{\text{tr}} \underline{A}.$$

$$\underline{\text{tr}}(\underline{A}^T) = \underline{\text{tr}} \underline{A}.$$

$$\underline{\text{tr}}(\underline{A} \circ \underline{B}) = \underline{\text{tr}}(\underline{B} \circ \underline{A})$$

Tensor field


Scalar field $f(\underline{x})$

$$df = \frac{\partial f}{\partial x_i} dx_i.$$

$$= \frac{\partial f}{\partial x_i} (\underline{e}_i \cdot d\underline{x}).$$

$$\nabla f = \frac{\partial f}{\partial x_i} \underline{e}_i$$

$$= \nabla f \cdot d\underline{x}$$



$$\nabla u = ?$$

$$\lim \left(\frac{u(x+tv) - u(x)}{t} \right) \leftarrow (\nabla u) \cdot v \equiv \lim u(x+tv)$$

$$= \left[u(x) + \frac{\partial u}{\partial x_i} + v_i \right] - u_i(x).$$

$$- \frac{u(x)}{t}$$

$$= -\frac{\partial \underline{u}}{\partial x_k} \underline{v}_k$$

$$= \frac{\partial(u_i e_i)}{\partial x_k} v_k = \frac{\partial u_i}{\partial x_k} e_i (\underline{e}_k \cdot \underline{v})$$

$$= \left(\frac{\partial u_i}{\partial x_k} \underline{e}_i \underline{e}_k \right) \cdot \underline{v}$$

$\nabla \underline{u}$

$\nabla \underline{u} = \frac{\partial u_i}{\partial x_k} \underline{e}_i \underline{e}_k \rightarrow$ bump up by 1 order
(w/ gradients).

$$\nabla \underline{P} = \frac{\partial \underline{P}}{\partial x_k} \underline{e}_k$$

$$= \frac{\partial P_{ij}}{\partial x_k} \underline{e}_i \underline{e}_j \underline{e}_k$$

$$\operatorname{tr}(\nabla \underline{u}) = \frac{\partial u_i}{\partial x_k} (\underline{e}_i \cdot \underline{e}_k)$$


$$= \frac{\partial u_i}{\partial x_i}$$

$$= \nabla \cdot \underline{u}$$

$$\nabla \cdot \underline{P} = \frac{\partial P_{ij}}{\partial x_k} \underline{e}_i (\underline{e}_j \cdot \underline{e}_k) = \frac{\partial P_{ij}}{\partial x_j} \underline{e}_i$$

δ_{jk}

$\underline{n} \rightarrow$ unit normal.



$$\iiint_V f_i dV = \iint_S f n_i dS$$

Green's theorem.


$$f_i = \frac{\partial f}{\partial x_i}$$

$$\int_V u_{j,i} dV = \int_S u_j n_i dS \quad \}$$

$$\int_V T_{k,i} dV = \int_S T_{k,i} n_i dS \quad \}$$


Mechanics.

$\left\{ \begin{array}{l} \text{kinematics. } \checkmark \quad (\text{geometry}). \\ \text{Balance laws } \checkmark \quad (\text{forces, moments, ...}) \\ \text{Constitutive laws } \leftarrow \begin{array}{l} \text{"Research"} \\ \text{connect. k.} \end{array} \end{array} \right.$



Week 3: Mon.

kinematics.




Material point is labeled by its coordinate \underline{X}_0 or \underline{X} .

(Ref. config.).

Ω_0 is the configuration of the Body at $t=0$.

Normally we choose Ω_0 to be the undeformed state of the body.

$$\underline{x} - \underline{\bar{x}} = \underline{u}(\underline{\bar{x}}, t)$$



$t > 0$. Body deforms and occupies Ω_t .

$\underline{\bar{x}} \rightarrow \underline{x}$
mapping.

this is a mapping:

$$\begin{aligned} \underline{x} &= \underline{\bar{x}}(\underline{\bar{x}}, t) \\ &= \underline{x}(\underline{\bar{x}}, t). \end{aligned}$$

function "kai."

$$\underline{u} = \underline{x} - \underline{\bar{x}} \rightarrow \text{displacement vector.}$$

Always assume mapping \underline{x} is one-one points

given one point

Another point associated w/
it.

*** Some simple examples: (motion).

$$\underline{x} = \underline{\bar{x}} + \underline{c}(t). \quad \text{Rigid body translation.}$$

\underline{x} interesting cuz no deformation.

*** e.g. 2.

rectangular cross section.

Let \underline{s}_{20} be a bar, (straight bar)

$$\text{We define } \underline{x} = \underline{\bar{x}} + \sum_{k=1}^3 (\lambda_k - 1) \underline{x}_k \underline{e}_k.$$

(remember)


$$\underline{u} = \underline{x} - \underline{\bar{x}}$$

$$\underline{u} = \sum_{k=1}^3 (\lambda_k - 1) \underline{x}_k \underline{e}_k$$

real positive numbers.

$\lambda_k = 1$: no displacements \rightarrow body remain initial state.

$\lambda_k \neq 1$: stretch & compress in $\underline{e}_1, \underline{e}_2, \underline{e}_3$ directions
stretch ratios



$$\lambda_k = \frac{L}{L_0}.$$


* You can always impose a displacement field on a body.

Rigid body rotation

$$\underline{x} = \underline{\bar{x}} + \underline{R}(\underline{\theta}) \underline{e}_k.$$


$$\underline{\theta}_k \rightarrow \underline{R}(\underline{\theta}_k)$$

$$\boxed{\underline{R} = \underline{n}_k \underline{\theta}_k} \leftrightarrow \text{rotation.}$$



linear trans. \rightarrow completely det. by action on its basis

does not increase any definition



$$d\underline{x} = \frac{\partial \underline{x}}{\partial \underline{X}_j} d\underline{X}_j \quad (\text{def of grad.}),$$

$$= \underbrace{\nabla_{\underline{X}} \underline{x}}_F \cdot d\underline{X}.$$

$\underline{F} = \nabla_{\underline{X}} \underline{x} \rightarrow$ deformation gradient tensor.

↳ contains all the information on local deformation $\underline{F}(\underline{X}, t)$

$$\underbrace{\nabla_{\underline{X}} \underline{x}}_F = \frac{\partial (x_i e_i)}{\partial \underline{X}_j} e_j$$

$$\underline{F} = \frac{\partial x_i}{\partial \underline{X}_j} e_i e_j$$

$$[\underline{F}] = \begin{bmatrix} \frac{\partial x_1}{\partial \underline{X}_1} & \frac{\partial x_1}{\partial \underline{X}_2} & \frac{\partial x_1}{\partial \underline{X}_3} \\ \vdots & \vdots & \vdots \end{bmatrix}$$

respect to the basis e_i, e_j

$$d\underline{x} = \underline{F} \cdot d\underline{X}.$$

change of length (fiber)

$$d\underline{x} \cdot d\underline{x} - d\underline{X} \cdot d\underline{X}$$

$$= (\underline{F} \cdot d\underline{X}) \cdot (\underline{F} \cdot d\underline{X}) - d\underline{X} \cdot d\underline{X}$$

$$= d\underline{X} \cdot \underbrace{(\underline{F}^T \cdot \underline{F})}_{C} \cdot d\underline{X} - d\underline{X} \cdot d\underline{X}$$

C is the Cauchy-Green Tensor

$$= d\underline{X} \cdot (C - I) \cdot d\underline{X},$$

$$I \cdot d\underline{X} = d\underline{X} \quad \downarrow \quad I$$

$$\frac{\|d\underline{x}\|^2}{\|d\underline{X}\|^2} = \left(\frac{\|d\underline{x}\|}{\|d\underline{X}\|} \right)^2 \text{ Lagrangian Strain Tensor}$$

$$\frac{d\underline{x} \cdot d\underline{x}}{\|d\underline{X}\|^2} = 1$$

$$\frac{d\underline{x}}{\|d\underline{X}\|} \cdot C \cdot \frac{d\underline{X}}{\|d\underline{X}\|} = 1$$

$$= \underbrace{\frac{N \cdot C}{\|d\underline{X}\|}}_N - 1$$



stretch ratio

unit vector

\underline{X}, t

Solid: $\underline{X} \rightarrow$ reference configuration

Fluid: $\underline{x} \rightarrow$ spatial \rightarrow current coordinates



$$\text{Ex 1: } \underline{u} = \sum_{k=1}^3 (\lambda_k - 1) \otimes x_k e_k \quad \text{don't use summation with } \lambda \text{!!!}$$

$$[F] = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_2 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix} \quad F = \lambda_1 e_1 e_1 + \lambda_2 e_2 e_2 + \lambda_3 e_3 e_3$$

$$F = \lambda_1 e_1 e_1 + \lambda_2 e_2 e_2 + \lambda_3 e_3 e_3$$

$$\lambda_1 = \lambda_2 = \lambda_3 > 1$$

Uniform expansion.

$$\lambda_1 = \lambda_2 = \lambda_3 < 1$$

Uniform compression

$$[F] = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_2 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix}$$

$$\det F = J$$

Invariant.

$$= \lambda_1 \lambda_2 \lambda_3$$

Rubber is almost incompressible,

$$\text{so } J \approx 1.$$


In general, $\det F = \frac{dV}{dV_0}$ the deform of the volume over the reference (original) volume.

always true.

$$= \frac{V_{\text{new}}}{V_0}$$

reference volume

in a tension bar:



$$E = \epsilon_{ij} e_i e_j$$

$$\epsilon_{ij} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) + \frac{1}{2} \left(\frac{\partial u_k}{\partial x_i} \cdot \frac{\partial u_k}{\partial x_j} \right)$$

$$\epsilon_{ij}$$

small strain tensor
(1% ~ 2%).

effect of
large defor.
quadratic term.

$$10^{-2} \cdot 10^{-2} = 10^{-4}$$

$$(10^{-2}\% \sim 4 \cdot 10^{-2}\%)$$

Week 3.

Sep. 15th (Wed.)

Review: \underline{F} Deformation Gradient Tensor

completely characterize the local deformation at a point \underline{x} .

$\underline{F}(\underline{x}, t)$, \underline{x}, t , independent variables.

Material description.

$$\underline{C} = \underline{F}^T \underline{F}$$
 Right Cauchy-Green Tensor

$$\underline{E} = \underline{F}^T \underline{F} - \underline{\mathbb{I}}.$$

$$d\underline{x} \cdot d\underline{x} = d\underline{x} \cdot \underline{C} \cdot d\underline{x}$$

\underline{N} is a unit vector.

$$\frac{\|d\underline{x}\|^2}{\|d\underline{x}\|^2} = \frac{\|d\underline{x}\|}{\|d\underline{x}\|} \cdot \underline{C} \cdot \frac{\|d\underline{x}\|}{\|d\underline{x}\|}.$$

$$\frac{\|d\underline{x}\|}{\|d\underline{x}\|} = \lambda.$$

Stretch Ratio. = $\frac{\text{length of mat. line ele. in the Ref. configuration.}}{\text{length of mat. line ele. in the current configuration.}}$



$$\lambda_n^2 = \underline{N} \cdot \underline{C} \cdot \underline{N}.$$

$$\underline{N} \cdot \underline{E} \cdot \underline{N} = \lambda_n^2 - 1. \quad \downarrow \quad \text{measure the deformation.}$$

Lagrangian Strain tensor

$$E_{ij} = \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right] + \frac{1}{2} \left[\frac{\partial u_k}{\partial x_i} + \frac{\partial u_k}{\partial x_j} \right]$$

E_{ij}

Remember:

$$\underline{x} = \underline{x} + \underline{u}(\underline{x}, t).$$

Both \underline{C} & \underline{E} are symmetric Tensors.

$$\underline{C}^T = \underline{C}. \quad \text{Recall } \underline{F} \text{ is revertible.}$$

$$\underline{F}^T \underline{F} = \underline{C}.$$

\downarrow \underline{C} is positive definite
revertible

identical (exactly) $d\underline{x} \cdot \underline{C} \cdot d\underline{x} \geq 0$ only when $d\underline{x} = 0$.
 $\rightarrow \|F \cdot d\underline{x}\|^2 \geq 0$. $d\underline{x} \neq 0$. Real.

\underline{C} symmetric implies that \underline{C} has \checkmark eigenvalues

$$\lambda_1^2 > \lambda_2^2 > \lambda_3^2 \in \lambda_1, \lambda_2, \lambda_3$$

\underline{C} positive definite implies $\lambda_i^2 > 0$.

$i=1, 2, 3$.

\underline{C} can be diagonalized.

that is, \underline{C} can be written as

$$\underline{C} = \lambda_1^2 \underline{n}_1 \underline{n}_1 + \lambda_2^2 \underline{n}_2 \underline{n}_2 + \lambda_3^2 \underline{n}_3 \underline{n}_3$$

\underline{n} are orthonormal eigen vectors of \underline{C}

$$\text{that is } \underline{n}_i \cdot \underline{n}_j = \delta_{ij}$$

THIS $\lambda_1, \lambda_2, \lambda_3$ are called principal stretches.

\underline{n}_i are the principal direction.

Polar Decomposition Theorem

$$\underline{F} = \underline{R} \underline{U} = \underline{V} \underline{R}$$

\underline{R} is a rigid body rotation tensor, $\underline{R}^T = \underline{R}^{-1}$

$$\underline{R}^T \underline{R} = \underline{R} \underline{R}^T = \underline{I}$$

\underline{U} is symmetric, positive definite.

$$\text{and } \underline{U}^2 = \underline{C} \quad \& \quad \underline{U} = \sqrt{\underline{C}}$$

$$\underline{U} = \lambda_1 \underline{N}_1 \underline{N}_1 + \lambda_2 \underline{N}_2 \underline{N}_2 + \lambda_3 \underline{N}_3 \underline{N}_3$$

$$\text{check } \underline{U} \cdot \underline{U} = \underline{U}^2 = \underline{C}$$

\underline{F} can be decompose into two simple tensor,

where first tensor, $\underline{U} \rightarrow$ stretch tensor



it stretch the material

point in principal directions

the it rotate with \underline{R} .

$$\underline{F} = \underline{R} \underline{U} \cdot \underline{R} \rightarrow \text{this a local theorem}$$

\underline{U} comes first, and \underline{R} comes second.



$$n_i = R(N_i)$$

* Only need to prove

$$\underline{\underline{R}} = \underline{\underline{F}} \underline{\underline{U}}^{-1} \text{ is a rotation.}$$

$$\underline{\underline{R}}^T \underline{\underline{R}} = \underline{\underline{I}}.$$

$$\underline{\underline{R}}^T \underline{\underline{R}} = (\underline{\underline{F}} \underline{\underline{U}}^{-1})^T (\underline{\underline{F}} \underline{\underline{U}}^{-1}).$$

$$= (\underline{\underline{U}}^T \underline{\underline{F}}^T) (\underline{\underline{F}} \underline{\underline{U}}^{-1}) = \underline{\underline{U}}^{-1} \underline{\underline{F}}^T \underline{\underline{F}} \underline{\underline{U}}^{-1}$$

symmetric \downarrow

$$\underline{\underline{U}}^{-1} = \underline{\underline{U}}^{-1} \underline{\underline{U}} \underline{\underline{U}}^{-1} \underline{\underline{U}} \underline{\underline{U}}^{-1}$$

$$\text{Therefore we prove: } \underline{\underline{R}}^T \underline{\underline{R}} = \underline{\underline{R}}^T \underline{\underline{R}} = \underline{\underline{I}}.$$

$$\underline{n}_i = \underline{\underline{R}}(\underline{n}_i).$$

$$\underline{\underline{R}} = \underline{n}_i \underline{n}_i = \underline{n} \underline{n}_1 + \underline{n}_2 \underline{n}_2 + \underline{n}_3 \underline{n}_3.$$

*** Decomposition is unique.

if we define: $\underline{\underline{V}} = \lambda_1 \underline{n}_1 \underline{n}_1 + \lambda_2 \underline{n}_2 \underline{n}_2 + \lambda_3 \underline{n}_3 \underline{n}_3$.

$$\underline{\underline{V}} \underline{\underline{R}} = (\lambda_1 \underline{n}_1 \underline{n}_1 + \lambda_2 \underline{n}_2 \underline{n}_2 + \lambda_3 \underline{n}_3 \underline{n}_3) \cdot (\underline{n}_1 \underline{n}_1 + \underline{n}_2 \underline{n}_2 + \underline{n}_3 \underline{n}_3).$$

$$= \lambda_1 \underline{n}_1 \underline{n}_1 + \lambda_2 \underline{n}_2 \underline{n}_2 + \lambda_3 \underline{n}_3 \underline{n}_3$$

\Downarrow then we can check:

$$\underline{\underline{F}} \underline{\underline{U}} = \underline{\underline{V}} \underline{\underline{R}}.$$

[IN CASE] in mechanics theorem paper,

someone writes:

$$\underline{\underline{F}} = \underline{\underline{F}}_{\underline{\underline{A}}} \underline{\underline{e}}$$


$\underline{\underline{F}}_{\underline{\underline{A}}} \underline{\underline{e}}_i \underline{\underline{e}}_A \rightarrow$ two point tensor

$$\underline{\underline{e}}_i \cdot \underline{\underline{e}}_j = \delta_{ij}$$

$$\underline{\underline{e}}_A \cdot \underline{\underline{e}}_B = \delta_{AB}$$

in the ref. config. $\underline{\underline{e}}_1, \underline{\underline{e}}_2, \underline{\underline{e}}_3$

current config.



Simple Shear Deformation.

$$\begin{cases} x_1 = \underline{x}_1 + I \tan \gamma \\ x_2 = \underline{x}_2 \\ x_3 = \underline{x}_3 \end{cases} \quad \begin{matrix} \text{fixed number} \\ (0, \pi/2). \end{matrix}$$

$$\underline{x} = x_i \underline{\underline{e}}_i \quad [\underline{\underline{E}}] = \begin{bmatrix} 1 & \tan \gamma & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

$$\underline{F} = \underline{e}_1 \underline{e}_1 + \tan \gamma \underline{e}_1 \underline{e}_2 + \underline{e}_2 \underline{e}_2 + \underline{e}_3 \underline{e}_3$$



$$\det \underline{F} = 1$$

$$\hookrightarrow \det(\underline{R} \underline{U}) = \det \underline{R} + \det \underline{U} \rightarrow \lambda_1, \lambda_2, \lambda_3$$

$$= 1$$

$$\frac{V}{V_0}$$

$$\underline{F} =$$



Office How:

$$\underline{F} = (\delta_{ij} + u_{ij}) \underline{e}_i \underline{e}_j$$

$$\underline{\epsilon} = \frac{1}{2} [u_{ii,j} + u_{jj,i} + u_{kk,i} u_{kk,j}]$$

$$ij = \frac{\partial}{\partial x_j}$$

Week 4 (3). Non.

Linear Theory. (small deformation).

↪ perturbation theory.

geometry change small.

(gradients of displacements small, $\ll 1$).

$$\underline{\underline{E}} = \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right].$$

$$\underline{u} = u_k e_k.$$

higher order terms.

$$\approx \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right].$$

leading order terms

$$\underline{\underline{C}} - \underline{\underline{I}} \equiv 2\underline{\underline{E}} = \underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}}.$$

$$\underline{\underline{F}} = \underline{\underline{I}} + \frac{\partial u_i}{\partial x_j} e_i e_j = \underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}}$$

$$\frac{\partial u_i}{\partial x_j} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) + \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right)$$

sym anti-sym

$$G_{ij} = (\delta_{ij} + \epsilon_{ij} + \omega_{ij}) (\delta_{ij} + \epsilon_{ij} + \omega_{ij})$$

$$= \delta_{ij} \delta_{ij} + \delta_{ij} \epsilon_{ji} + \delta_{ij} \omega_{ji} + \epsilon_{ij} \delta_{ij} +$$

$$+ \epsilon_{ij} \epsilon_{ji} + \epsilon_{ij} \omega_{ji}$$

$$+ \omega_{ij} \delta_{ij} + \omega_{ij} \epsilon_{ji} + \omega_{ij} \omega_{ji}$$

$$+ \omega_{ij} \epsilon_{ij}$$

$$\underline{\underline{C}} = (\underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}})^T (\underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}})$$

$$= (\underline{\underline{I}} + \underline{\underline{\epsilon}} - \underline{\underline{\omega}}) (\underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}})$$

$$= \underline{\underline{I}} + 2\underline{\underline{\epsilon}} + \text{H.O.T.}$$

$$\underline{\underline{C}} = \underline{\underline{U}}^2 \quad (\text{??})$$

$$\underline{\underline{\epsilon}} \approx \underline{\underline{I}} + 2\underline{\underline{\epsilon}}$$

$$\underline{\underline{U}} = \underline{\underline{I}} + \underline{\underline{\epsilon}} - \underline{\underline{U}}^2 = \underline{\underline{I}} + 2\underline{\underline{\epsilon}} + \underline{\underline{\epsilon}} \underline{\underline{\epsilon}}$$

$$\underline{\underline{U}}^T \approx \underline{\underline{I}} - \underline{\underline{\epsilon}}$$

$$\underline{\underline{F}}^T = \underline{\underline{R}} \underline{\underline{U}}$$

$$\underline{\underline{R}} = \underline{\underline{F}} \underline{\underline{U}}^T \quad \underline{\underline{R}} \approx (\underline{\underline{I}} + \underline{\underline{\epsilon}} + \underline{\underline{\omega}})(\underline{\underline{I}} - \underline{\underline{\epsilon}})$$

$$\underline{\underline{V}} = \frac{\partial \underline{x}}{\partial t} = \begin{vmatrix} \frac{\partial x_1}{\partial t} & \frac{\partial x_2}{\partial t} \\ \vdots & \vdots \\ \frac{\partial x_n}{\partial t} & \frac{\partial x_n}{\partial t} \end{vmatrix}_{\underline{x} \text{ fix.}} = \underline{\underline{I}} - \underline{\underline{\epsilon}} + \underline{\underline{\omega}}$$

↪ (at a fixed material point).

$$\underline{x} = \underline{x} + \underline{u}(\underline{x}, t)$$

$$\underline{\underline{A}} = \frac{\partial^2 \underline{x}}{\partial t^2} \Big|_{\underline{x}} = \begin{vmatrix} \frac{\partial^2 x_1}{\partial t^2} & \frac{\partial^2 x_2}{\partial t^2} \\ \vdots & \vdots \\ \frac{\partial^2 x_n}{\partial t^2} & \frac{\partial^2 x_n}{\partial t^2} \end{vmatrix}_{\underline{x}}$$

$$\underline{V}(\underline{x}, t)$$

mechanics: quantities in spatial descrip.

density

$$\rho(\underline{x}, t)$$

the material derivative:

$$\dot{f}(\underline{x}, t) = f(\underline{\chi}(\underline{x}, t), t)$$

$$\frac{D}{Dt} f = \dot{f} \quad \text{Fixed } \underline{x}$$

$$= \frac{\partial f}{\partial \underline{x}_i} \frac{\partial \underline{\chi}_i}{\partial t} + \frac{\partial f}{\partial t} \Big|_{\underline{x}}$$

velocity:

$$\underline{v}_i(\underline{x}, t)$$

$$= \frac{\partial f}{\partial \underline{x}_i} \underline{v}_i(\underline{x}, t) + \frac{\partial f}{\partial t} \Big|_{\underline{x}} = \nabla_{\underline{x}} f \cdot \underline{v} + \frac{\partial f}{\partial t} \Big|_{\underline{x}}$$

$$\nabla_{\underline{x}} f = \frac{\partial f}{\partial \underline{x}_j} \underline{e}_j$$

$$\nabla_{\underline{x}} g = \frac{\partial g}{\partial \underline{x}_j} \underline{e}_j$$

$$\underline{V} = \underline{V}(\underline{x}, t) = \frac{\partial \underline{\chi}}{\partial t} \Big|_{\underline{x}}$$

$$\underline{v} = \underline{V}(\underline{\chi}^{-1}(\underline{x}, t), t) \cdot \underline{x} = \underline{\chi}^{-1}(\underline{x}, t)$$

in the spatial configuration.

$$\underline{a} = \underline{A}(\underline{\chi}^{-1}(\underline{x}, t), t)$$

$$\underline{a} = \underline{v} \cdot \nabla_{\underline{x}} \underline{v} + \frac{\partial \underline{v}}{\partial t} \Big|_{\underline{x}}$$


Concept of Stress

If given displacement field, & ref. config.

then we can calculate everything.

Assumption: Cauchy's hypothesis.

$\Delta A / A$ small \rightarrow force almost uniform
AS.



Surface interactions

Important: orientation \rightarrow X shape


$$\underline{\tau} = \frac{\sigma f}{\Delta S} \quad \Delta S \rightarrow 0 \\ = \underline{\tau}(n, \underline{x}, t)$$

\underline{n} → outward unit normal vector in the current configuration.

\underline{t} → traction vector (stress).

* if we know traction in 3D, then we know the stress at this point.

Cauchy's theorem.



Body forces: → depends on volume of element.

ρ = mass per unit volume in current configuration.

Body forces per unit volume in linear momentum balance.

$$\underline{t} dA - t_1 dA_1 - t_2 dA_2 - t_3 dA_3 + \rho \underline{b} dV$$

$$= m \underset{dV}{\cancel{\int}} (\rho dV) \underline{a}.$$

$\cancel{\int}$ is the volume of small pyramid
 dV .

$$dA \gg dV, \quad \frac{dV}{dA} \rightarrow 0.$$

(in small pyramid).

$$\underline{t} = t_1 \frac{dA_1}{dV} + t_2 \frac{dA_2}{dV} + t_3 \frac{dA_3}{dV}$$

$$\underline{t} = \cancel{t_1 e_1 + t_2 e_2 + t_3 e_3}$$

$$t_1 e_1 \cdot \underline{n} + t_2 e_2 \cdot \underline{n} + t_3 e_3 \cdot \underline{n}$$

$$t_1 = \sigma_i e_i$$

$$t_k = \sigma_k e_k, \quad k = 1, 2, 3.$$


$$t_j = \sigma_{ij} e_i$$

$$= \sigma_{ij} e_i e_j \cdot \underline{n}. \quad (\text{other text book: } \underline{t} = \underline{\sigma}^T \cdot \underline{n}).$$

$\underline{\sigma}$ = Cauchy or True stress tensor

$$t_j = \sigma_{ji} n_i$$

$$\underline{t} = \underline{\sigma} \cdot \underline{n}.$$




$$t_2 = \sigma_{12} e_1 + \sigma_{22} e_2 + \sigma_{32} e_3.$$

Week 4, Wed.

$\underline{\sigma}$ = True stress tensor in current config.
Cauchy

$\underline{\sigma} \cdot \underline{n} = \underline{t} \rightarrow$ traction vector.



* Equilibrium equation - Deformed configuration
(LMB)

↓
Linear momentum balance.

Key Results.

$$\nabla_x \cdot \underline{\sigma} + \rho b = \rho \cdot \underline{a}$$

Body force acceleration

spatial. Divergence.

$$\frac{\partial \sigma_{ij}}{\partial x_j} + \rho b_i = \rho a_i \dots (N1)$$

Current config. ||

In real-world applications, cuz you didn't know
current config.

in elastic prob., we use reference config.

In Ref config.

Eq. (N1) become:

$$\nabla_{\underline{x}} \cdot \underline{P} + p_0 \underline{B} = p_0 \underline{A}.$$

$$\frac{\partial P_{ij}}{\partial x_j} + p_0 B_i = p_0 A_i. \quad \underline{A} = \underline{A}(\underline{x}, t).$$

First Piola Tensor \Rightarrow Nominal Stress tensor

AMB Angular momentum balance.


AMB.

$$\underline{P}^T = \underline{F}^T \underline{P}^T.$$

Derivation:

METHOD I:

Forces acting on Σ_{2t} .



(Force balance) integral of $\int_{\Sigma_{2t}} \underline{P} \cdot \underline{n} d\underline{s}$

$$+ \int_{\Sigma_{2t}} \underline{\Omega} \cdot \underline{n} d\underline{s} \quad (\text{traction}) \quad (F.1)$$

AMB

(Newton's law)

$$+ \frac{D}{Dt} \int_{\Sigma_{2t}} \underline{P} \underline{V} dV \quad \text{cannot take inside.}$$

$\rho dV = \rho_0 dV_0$ conservation of mass

$$\rho \frac{dV}{dV_0} = \frac{\rho_0}{\rho} = \det F.$$

Jacobian.

Eq. (F.1) becomes

$$\frac{D}{Dt} \int_{\Sigma_{2t}} \rho \underline{V} \cdot d\underline{V} = \frac{D}{Dt} \int_{\Sigma_{2t}} \rho_0 \underline{V}_0 \cdot d\underline{V}_0.$$

fixed

So can take $\frac{D}{Dt}$ inside

$$= \int_{\Sigma_{2t}} \rho_0 \underline{A} \cdot \underline{V} \cdot d\underline{V}_0.$$

$$= \int_{\Sigma_{2t}} \rho \underline{a} \cdot d\underline{V}$$

$$\int_{\Sigma_{2t}} \underline{\Omega} \cdot \underline{n} d\underline{s} + \int_{\Sigma_{2t}} (\rho b - \rho a) dV.$$

Divergence theorem

$$\int_{\Sigma_{2t}} \nabla_{\underline{x}} \cdot \underline{\Omega} \cdot d\underline{V}$$


$$\int_{\Sigma_{2t}} (\nabla_{\underline{x}} \cdot \underline{\Omega} + \rho b - \rho a) dV = 0$$

This is true for any $\Sigma_{2t} \Rightarrow$

$$\Rightarrow \nabla_x \cdot \underline{\sigma} + p_b = p_a$$

$$[\sigma_{33}(x,t) + \frac{\partial \sigma_{33}}{\partial x_3} \frac{dx_3}{2}]$$

FINISHED!!!




Net force in 1D,

$$\left[\frac{\partial \sigma_{22}}{\partial x_2} + \frac{\partial \sigma_{33}}{\partial x_3} + \frac{\partial \sigma_{11}}{\partial x_1} \right] dx_1 dx_2 dx_3$$

$$+ p_b dx_1 dx_2 dx_3 = p_a dx_1 dx_2 dx_3$$


$$\frac{\partial \sigma_{ij}}{\partial x_j} + p_{bi} = p_{ai}$$

△ → total force.




$$\sigma_{ij} = T_{ji}$$

$$\int_{\Omega_0} p_0 \underline{B} dV_0 + \int_{\partial R_t} \underline{\sigma} \cdot \underline{n} dS = \int_{\Omega_0} p_0 \underline{A} dV_0$$



$$I = \underline{\sigma} \cdot \underline{n} = \frac{df}{dS_t} \Rightarrow I dS_t = df$$



$$dV = \underline{n} \cdot dS_t \cdot d\underline{x} = \underline{n} \cdot dS_t \cdot \underline{F} \cdot d\underline{x}$$

$$dV_0 = \underline{N} \cdot dS_0 \cdot d\underline{x}$$

$$\frac{dV}{dV_0} = \det \underline{F} \equiv J$$

$$\underline{n} \cdot dS_t \cdot \underline{F} \cdot d\underline{x} = J \underline{N} \cdot dS_0 \cdot d\underline{x}$$

$$d\underline{x} \cdot dS_t \underline{F}^T \cdot \underline{n} = d\underline{x} \cdot J \underline{N} \cdot dS_0$$

$d\underline{x}$ is solitairy!

$$dS_t \cdot \underline{F}^T \cdot \underline{n} = J \underline{N} \cdot dS_0$$

$$\underline{F}^T \cdot \underline{n} \cdot dS_0 = J \underline{N} \cdot dS_0$$

Substitute
 $\int \underline{\Sigma} \cdot \underline{n} \cdot d\underline{S}$

Nansen's formula
 Nansen's.


$$\underline{n} \cdot dS_0 = J \underline{F}^T \cdot \underline{N} \cdot dS_0$$

By definition

$$\underline{P} = \underline{J} \underline{\Sigma} \underline{F}^{-T}$$

Divergence

$$\int_{S_0} \nabla_{\underline{x}} \cdot \underline{P} dV_0 \rightarrow \nabla_{\underline{x}} \cdot \underline{P} + \oint_{S_0} \underline{B} = \underline{S}_0 \underline{A}$$



$$\underline{t} \times dS_0 = d\underline{f} = \underline{t} \cdot dS_t$$

$\underline{P} \cdot \underline{n} = \underline{t}$

\downarrow

not a symmetric tensor

$$\underline{P} = \underline{J} \underline{\Sigma} \underline{F}^{-T}$$

\downarrow

not symmetric
 symmetric

AMB

$$-\underline{(\underline{P} \underline{F}^T)^T} = \frac{\underline{P} \underline{F}^T}{J} \Rightarrow \underline{\underline{F} \underline{P}^T} = -\underline{\underline{P} \underline{F}^T}$$

In fluid mech, use current config. or variables.

Basic balance laws of continuum mechanics.

(Derived in current configuration)

Office hour Fri. 3:30pm

HW #2

$$\underline{A} = a_{ij} \underline{e}_i \underline{e}_j$$

$\{\underline{e}_i\}$ original basis.

$\{\underline{\bar{e}}_j\}$ New

$$\begin{pmatrix} a_{11} & a_{12} & a_{13} \\ a_{21} & a_{22} & a_{23} \\ a_{31} & a_{32} & a_{33} \end{pmatrix}$$

whole num.

λ_i : eigenvalues

Symmetry

$$\rightarrow A \text{ in new basis: } \underline{A} = \lambda_1 \underline{\bar{e}}_1 \underline{\bar{e}}_1 + \lambda_2 \underline{\bar{e}}_2 \underline{\bar{e}}_2 + \lambda_3 \underline{\bar{e}}_3 \underline{\bar{e}}_3$$

$$\Rightarrow \begin{pmatrix} 6 & -2 & -1 \\ -2 & 6 & -1 \\ -1 & -1 & 3 \end{pmatrix}$$

$$+ \lambda_3 \underline{\bar{e}}_3 \underline{\bar{e}}_3$$

↑

$$\text{eigenvalues: } \lambda_1 = 8, \lambda_2 = 6, \lambda_3 = 3$$

Original one: $\underline{A} = 6\underline{e}_1 \underline{e}_1 - 2\underline{e}_2 \underline{e}_2 - 1\underline{e}_3 \underline{e}_3$

↳ So, $\underline{A} = 8\underline{\bar{e}}_1 \underline{\bar{e}}_1 + 6\underline{\bar{e}}_2 \underline{\bar{e}}_2 + 3\underline{\bar{e}}_3 \underline{\bar{e}}_3$

↑

what is $\underline{\bar{e}}_1$?

Original tensor $\underline{A} = a_{ij} \underline{e}_i \underline{e}_j$.

$$= \lambda_1 \underline{\bar{e}}_1 \underline{\bar{e}}_1 + \lambda_2 \underline{\bar{e}}_2 \underline{\bar{e}}_2 + \lambda_3 \underline{\bar{e}}_3 \underline{\bar{e}}_3$$

$$\underline{\bar{e}}_1 \cdot \underline{\bar{e}}_1 = 1, \underline{\bar{e}}_2 \cdot \underline{\bar{e}}_1 = 0, \underline{\bar{e}}_3 \cdot \underline{\bar{e}}_1 = 0$$

need to normalize to 1

$$(a_{ij} \underline{e}_i \underline{e}_j) \cdot \underline{\bar{e}}_1 = \lambda_1 \underline{\bar{e}}_1$$

$$\underline{e}_i \cdot \underline{e}_j = P_{ij}$$

$$a_{ij} \underbrace{\underline{e}_i (\underline{e}_j \cdot \underline{\bar{e}}_1)}_{P_{ij}} = \lambda_1 \underline{\bar{e}}_1$$

↓

$$\underline{\bar{e}}_1 = P_{1i} \underline{e}_i$$

$$a_{ij} P_{ij} \underline{e}_i = \lambda_1 \underline{\bar{e}}_1 = \lambda_1 P_{ii} \underline{e}_i$$

or $[a_{ij} P_{ij} - \lambda_1 P_{ii}] \underline{e}_j = 0$

$$\Rightarrow a_{ij} \vec{p}_j - \lambda \vec{p}_{i,i} = 0 \quad i=1,2,3$$

$$A = [a_{ij}] \quad A \vec{p}_i - \lambda \vec{p}_i = 0$$

eigen vector
of \underline{A} for $\underline{\lambda}$

$$\vec{p}_i = \begin{bmatrix} p_{i1} \\ p_{i2} \\ p_{i3} \end{bmatrix}$$

$$\text{or } (A - \lambda I) \vec{p}_i = 0$$

$\lambda_i \rightarrow$ eigenvalue of \underline{A}

\vec{p}_i is a eigen vector for A (λ_i).

$$\underline{e}_i = P_{ii} \underline{e}_i$$

$$\underline{e}_i \cdot \underline{e}_i = 1. \quad P_{ii} P_{ii} = 1$$

Same idea applies to \underline{e}_2

$$\underline{e}_2 = P_{22} \underline{e}_2 \leftarrow \lambda_2$$

$\underline{e}_3 \dots$

$$\underline{A} \cdot (\underline{e}_1 + \underline{e}_2) = \dots$$

* get the same as matter which basis

$$\underline{A} = (\underline{e}_1 \underline{e}_2)$$

MATRIX

linear transformation

$\underline{A} \cdot \underline{e}_1 =$ first column of \underline{A}

$$(\underline{e}_1 \underline{e}_2) \cdot \underline{e}_1 = 0$$

$$A = \begin{pmatrix} 0 & 1 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix}$$

$$\underline{A} \cdot \underline{e}_2 = (\underline{e}_1 \underline{e}_2) \cdot \underline{e}_2 = \underline{e}_1 (\underline{e}_2 \cdot \underline{e}_2) = \underline{e}_1$$

$$= 1 \underline{e}_1 + 0 \underline{e}_2 + 0 \underline{e}_3$$

$$\underline{A} \cdot \underline{e}_3 = 0$$

→ w.r.t basis

$\{\underline{e}_1, \underline{e}_2, \underline{e}_3\}$

$$\underline{A} = a_{ij} \underline{e}_i \underline{e}_j$$

$$[\underline{e}_1 \underline{e}_2] = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 0 \end{pmatrix}$$

$$[A] = \begin{pmatrix} a_{11} & 0 & 0 \\ 0 & a_{22} & 0 \\ 0 & 0 & a_{33} \end{pmatrix} + \begin{pmatrix} 0 & a_{12} & 0 \\ 0 & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix} + \dots$$

$$= a_{11} \underline{e}_1 \underline{e}_1 + \dots$$

$$\underline{V} = V_1 \underline{e}_1 + V_2 \underline{e}_2 + V_3 \underline{e}_3$$

$$\underline{E}_1 = \begin{pmatrix} 1 \\ 0 \\ 0 \end{pmatrix}$$

$$\underline{V} = \begin{pmatrix} V_1 \\ V_2 \\ V_3 \end{pmatrix}$$

$$\rightarrow V_1 \begin{pmatrix} 1 \\ 0 \\ 0 \end{pmatrix} + V_2 \begin{pmatrix} 0 \\ 1 \\ 0 \end{pmatrix} + \dots$$

$$\underline{V} = \underline{e}_1$$

$$\underline{e}_1 \underline{e}_1$$

$$\underline{A} = a_{11} \underline{e}_1 \underline{e}_1 + a_{12} \underline{e}_1 \underline{e}_2 + a_{13} \underline{e}_1 \underline{e}_3 + \dots$$

$$[\underline{A}] = \begin{pmatrix} a_{11} & a_{12} & a_{13} \\ a_{21} & a_{22} & a_{23} \\ a_{31} & a_{32} & a_{33} \end{pmatrix}$$

break it down into simple linear trans.

$$\underline{V} = V_1 \underline{e}_1 + V_2 \underline{e}_2 + V_3 \underline{e}_3$$

* Eigenvalues \rightarrow invariants

Eigen vectors \rightarrow be care of the basis !!!

$$\{\underline{e}_1, \underline{e}_2, \underline{e}_3\} \rightarrow \underline{E}_i = P_{ij} \underline{e}_j$$

$$\{\underline{E}_1, \underline{E}_2, \underline{E}_3\}$$

$$\underline{P}_1 = \begin{pmatrix} P_{11} \\ P_{12} \\ P_{13} \end{pmatrix}$$

with respect to this basis.

associated with P_{ij} .

\underline{W} = Skew. Symmetric.

$$\underline{\underline{W}} \cdot \underline{v} = \frac{\underline{w}}{\uparrow} \times \underline{v}$$

expand: *** need to tell what \underline{w} is

$$\underline{\underline{W}} = w_{12} \underline{e}_1 \underline{e}_2 + w_{21} \underline{e}_2 \underline{e}_1 + \dots$$

$$w_{11}, w_{22}, w_{33}, = 0,$$

$$\underline{\underline{W}} \cdot \underline{v} = \underline{P} \times \underline{v}.$$

$$w_{21} = -w_{12}$$

$$= w_{12} \underline{e}_1 \underline{e}_2 - w_{12} \underline{e}_2 \underline{e}_1 + \dots$$

$$\underline{\underline{W}} \cdot \underline{v} \Rightarrow \underline{v} = v_i \underline{e}_i$$

$$\underline{P} \times \underline{v} = \dots v_1 \dots v_2 \dots v_3$$

$$P_1 = w_{32}$$

$$P_2 = w_{13},$$

$$P_3 = w_{21}.$$

$$\nabla P = w_{32} \underline{e}_1 + w_{13} \underline{e}_2 + w_{21} \underline{e}_3.$$

Sep 27. Week 3.

- Personal Review - So-far

→ Cartesian Tensors.

- Review on Notation

- Summation Convention (Indical notation)

- Permutation symbol

- Transformation Rule for vectors

▷ Second Order tensors

▷ Transpose of tensor

Symmetric & Skew-Symmetric tensor

Tensor transformation (basis, ...)

Operation of tensors: (products, ...)

Symmetric tensors: Diagonalization.

High order tensor

Trace of second order tensor

High order tensor

Tensor fields

Kinematics

Sep 27, Week 5. Mon.

Review: Last lecture: Balance laws.

True stress tensor $\underline{\underline{\sigma}}$ current coordinate.

$$\rightarrow \nabla_{\underline{x}} \cdot \underline{\underline{\sigma}} + \rho \underline{b} = \rho \underline{a} \quad \text{invariate form}$$

$$\frac{\partial \sigma_{ij}}{\partial x_j} + \rho b_i = \rho a_i, \quad i=1, 2, 3. \quad (\times \text{ config. influence})$$

3 PDEs. in the current coordinate
~~Amb~~

Independent spatial variable are x_i .

$$\underline{\underline{\sigma}} = \underline{\underline{\sigma}}_i, \quad \underline{\underline{\sigma}} = \underline{\underline{\sigma}}^T$$

Balance law in reference configuration, independent variables are \underline{x}_i .

$\underline{\underline{P}}$ (Nominal or 1st Piola stress tensor)

$$(II). \quad \underline{\underline{P}} = J \underline{\underline{\sigma}} \underline{F}^{-T} \quad \rightarrow J = \det \underline{F}$$

$$\underline{\underline{\sigma}} = \frac{1}{J} \underline{\underline{P}} \underline{F}^T \quad \text{true stress.} \quad \underline{\underline{\sigma}} (\underline{x} = \chi(\underline{x}_i, t), t).$$

$$\nabla_{\underline{x}} \underline{\underline{P}} + \rho_0 \underline{B}_0 = \rho_0 \underline{A}$$

$$\frac{\partial P_{ij}}{\partial x_j} + \rho_0 B_{0i} = \rho_0 A_i$$

$\underline{\underline{P}}$ is not always symmetric

$$\text{So. an. } (\underline{\underline{\text{AMB}}}) \quad \underline{\underline{P}} \underline{F}^T = \underline{F} \underline{\underline{P}}^T$$

Proof.

$$\det \underline{F} = J = \frac{dV}{dV_0}, \quad \rho_0 dV_0 = \rho dV$$

$$\frac{\rho_0}{\rho} = \frac{dV}{dV_0} = J = \det \underline{F}$$

Material is called incompressible if $J=1$, $\forall \underline{x}$


Review Part

$$\underline{\underline{P}} \cdot \underline{N} dS_0 = \underline{\underline{\sigma}} \cdot \underline{N} dS_0$$

Simple example. $\underline{\underline{\sigma}} = \sigma_{ii} e_i e_i$

$$\sigma_{ii} = \frac{F}{A}$$

$$\rho_0 = \frac{F}{A_0}$$



Incompressible solid. $J = \lambda_1 \lambda_2 \lambda_3 = 1$.

$$\lambda_1 = \lambda_2 = \lambda_3. \quad \lambda = \frac{1}{J \lambda_1}$$

Plane stress

$$\sigma_{13} = \sigma_{23} = \sigma_{33} = 0, \forall x_3$$

$$\text{Sym} \rightarrow \sigma_{31} = \sigma_{32} = 0.$$

None-vanishing
stress state
(atmosphere)

$$\sigma_{11}, \sigma_{12} = \sigma_{21}, \sigma_{22}$$

$$\sigma_{\alpha\beta}, \alpha, \beta = 1, 2.$$

Assumption: $\sigma_{\alpha\beta}(x_1, x_2, t)$ independent of x_3

$$\text{Equilibrium Eq: } \frac{\partial \sigma_{\alpha\beta}}{\partial x_\beta} + p b_\alpha = 0$$

Divergent static problem


↳ Reduce to a 2D problem

Pure shear:

$$\underline{\sigma} = \sigma_{12} e_1 e_2 + \sigma_{21} e_2 e_1$$

$$= T(e_1 e_2 + e_2 e_1)$$

Eg.



(no external traction)

(no disp.).



$$u_3(x_1, x_2, x_3=0) = 0$$

(no shear)

$$T_{21} = T_{12} = 0, \text{ on } x_3 = 0$$

$$(x_1^2 + x_2^2) / a = 1$$

→ Solve the shape of gel.



Hooke - Young equation.

Equilibrium.


$$Y_w \cos \theta - Y_s = Y_v$$

$$\frac{Y}{G a} = \text{elastoplasticity}$$

shear typical length scale
modulus.


water leak out → poroelasticity

EASY WAY TO DO THIS:



$$\nabla_{\bar{x}} P = -\rho \underline{B}$$

$$\text{glued. } \rightarrow u_3 = -\rho g e_3$$



3 equations \rightarrow 6 unknowns ($\underline{\sigma}_{ap}$)

3 unknowns \rightarrow \hat{u}

9 unknowns.

Nonlinear Elasticity

Continuum Mechanics.

Sep 29, Wed Week 5.

Constitutive law.

$$\underline{\sigma} = \Psi(\underline{F}(t), -\infty < t' \leq t).$$

$$\underline{\sigma}(t)$$

Follow - the whole deformation history.

how to obtain the function $\rightarrow \Psi$.

∇ Hyperelasticity (Green's elasticity).

Elasticity $\underline{\sigma}$ depends only on $\underline{F}(t)$.

$$\underline{\sigma} = \Psi(\underline{F}(t))$$

↳ response function.

Mathematically,

$$\underline{P} = \frac{\partial w(\underline{F})}{\partial \underline{F}} \quad \text{energy per unit volume}$$



* the definition of hyperelastic materials.

$$P_{ij} = \frac{\partial w}{\partial F_{ij}}$$

$$dW = \frac{\partial W}{\partial F_{ij}} dF_{ij} = \frac{\partial W}{\partial F} : dF$$

$$= P_{ij} df_{ij} = P : dF \quad \text{work}$$

$$d\phi = -\underline{E} : d\underline{F} \quad \text{potential}$$



external work rate

$$= \int_{\partial\Omega_t} (\underline{\Omega} : \underline{n}) \cdot \underline{v} ds + \int_{\Omega_t} \underline{f} \cdot \underline{b} \cdot \underline{v} dV.$$

in the reference configuration

$$\begin{aligned} (\text{Piola Stress}) \int_{\partial\Omega_0} (\underline{P} \cdot \underline{N}) \cdot \underline{v} &= dS_0 + \int_{\Omega_0} P_0 b_0 \cdot \underline{v} dV_0 \end{aligned}$$

$$\int_{\partial\Omega_0} (\underline{P} \cdot \underline{N}) dS_0 = \int_{\partial\Omega_0} P_{ij} N_j V_i dS_0$$

div. Theo.

$$= \int_{\partial\Omega_0} (P_{ij} V_i)_{ij} dV_0. \quad ij = \frac{\partial}{\partial x_j}$$

$$= \int_{\partial\Omega_0} P_{ij,j} V_i dV_0 + \int_{\partial\Omega_0} P_{ij} V_{i,j} dV_0$$

↓ LMB

$$P_{ij,j} = -P_0 B + P_0 A_i$$

$$\dot{E}_{WR} = \int_{\Omega_0} P_0 A \cdot \underline{v} dV_0 + \int_{\Omega_0} P_{ij} V_{i,j} dV_0.$$

$$F_{ij} = \delta_{ij} + u_{i,j}$$

$$V_{i,j} = \frac{\partial}{\partial x_j} \left[\frac{\partial u_i}{\partial t} \Big|_{x_i} \right]$$

$$= \frac{\partial F_{ij}}{\partial t} \Big|_{\underline{x}}$$

$$\frac{D F_{ij}}{D t} = \dot{F}_{ij}$$

Kinetic Energy, (KE)

$$= \frac{1}{2} \frac{D}{Dt} \int_{\Omega_0} P_0 (\underline{V} \cdot \dot{\underline{V}}) dV_0$$

in the reference configuration

(completely general)

$$+ \int_{\Omega_0} \underline{P} : \dot{\underline{F}} dV_0$$

→ deform the body.

weak note

there could be dissipation in the process.

$$\frac{\partial W}{\partial F_{ij}} = \underline{P}$$

★ hyperelastic

assume $P_{ij} = \frac{\partial W}{\partial F_{ij}}$

$$\underline{P} = \int_{\Omega_0} W(\underline{F}) dV_0$$

$$dW = \frac{\partial W}{\partial F_{ij}} dF_{ij}$$

~~$$(dw) = \frac{\partial W}{\partial F_{ij}} dF_{ij}$$~~

$$\frac{Dw}{Dt} = \frac{\partial W}{\partial F_{ij}} \frac{DF_{ij}}{Dt} \rightarrow F_{ij}$$

$\checkmark P_0$

$t_1 \rightarrow t_2$ have to integrate the rate to time

Total work from $t_1 \rightarrow t_2$

$$\int_{t_1}^{t_2} EWP dt = \int_{t_1}^{t_2} \frac{D}{Dt} \int_{\Omega_0} P(\underline{V})^T dV_0 dt$$

$$+ \int_{t_1}^{t_2} \frac{D}{Dt} \left(\int_{\Omega_0} W(E) \cdot dV_0 \right) dt$$

$$t_1: \underline{E}_1 \cdot \underline{V}_1$$

$$t_2: \underline{E}_2 \cdot \underline{V}_2$$

$$\underline{F}_2 = \underline{V}$$

$$\int_{\Omega_0} W(\underline{F}_2) dV_0$$

$$- \int_{\Omega_0} W(\underline{F}_1) dV_0 = 0$$

Motivation for Hyper elasticity

↳ No energy loss during loading

Objectivity

$$\underline{W}(\underline{\underline{F}}) = \underline{W}(\underline{\underline{Q}}\underline{\underline{F}})$$



rigid body rotation

$$\underline{\underline{Q}} = \text{rotation}$$

$$\begin{pmatrix} \text{any} \end{pmatrix}$$

$$\underline{\underline{F}} = \underline{\underline{R}} \underline{\underline{U}}$$

only depends
on stretch
tensor


$$W(\underline{\underline{F}}) = W(\underline{\underline{R}}^T \underline{\underline{R}} \underline{\underline{U}}) = W(\underline{\underline{U}}).$$

~~Only~~ only the stretching parts make a diff


$$\hat{W}(\underline{\underline{C}}). (\because \underline{\underline{U}}^2 = \underline{\underline{C}}).$$

$$\underline{P} \Rightarrow \underline{P}_{ij} = \frac{\partial W}{\partial F_{ij}} = \frac{\partial \hat{W}}{\partial C_{ijkl}} \frac{\partial C_{kl}}{\partial F_{ij}}$$

$$\underline{\underline{F}} = \underline{\underline{F}} \frac{\partial \hat{W}}{\partial G_{ij}} (\text{H.W})$$



Not isotropic.



$$W(\underline{\underline{F}}) = W(\underline{\underline{F}} \underline{\underline{Q}})$$

~~Only for isotropic~~

Isotropic: true for all $\underline{\underline{Q}}$

depends on the symmetry of the materials

Oct. 9, Mon, Week 6.

$$\underline{x} = \underline{\underline{x}} + \underline{u}(\underline{x}, t)$$

$$\underline{\underline{x}} = \underline{x}^{-1}(\underline{x}, t).$$

$$\underline{u}(\underline{x}^{-1}(\underline{x}, t)) = \underline{a}(\underline{x}, t).$$

$$\underline{x} - \underline{\underline{x}} = \underline{y} \quad \frac{\partial u_i}{\partial \underline{x}_j} = \frac{\partial u_i}{\partial x_k} \cdot \frac{\partial x_k}{\partial \underline{x}_j}$$

$$\frac{\partial u_i}{\partial \underline{x}_j} = \frac{\partial \tilde{u}_i}{\partial x_k} \cdot \frac{\partial x_k}{\partial \underline{x}_j}.$$

$$\underline{x} - \underline{\underline{x}} = \underline{y}.$$

$$\underline{\underline{x}} - d\underline{x} = \underline{y}$$

$$\det(\underline{\underline{I}} + d\underline{\underline{B}}) = 1 + \frac{1}{R} (d\underline{\underline{B}}) + O(d\underline{\underline{B}})^2$$

$$\begin{aligned} d(\det \underline{\underline{A}}) &= \det \underline{\underline{A}} \cdot (1 + \frac{1}{R} (d\underline{\underline{A}}^T \cdot d\underline{\underline{A}})) - \det \underline{\underline{A}} \\ &= (\det \underline{\underline{A}}) \operatorname{tr}(d\underline{\underline{A}}^T \cdot d\underline{\underline{A}}) \\ &= -(\det \underline{\underline{A}})(\underline{\underline{A}}^{-T} \cdot d\underline{\underline{A}}) \end{aligned}$$

$$= \frac{\partial \det \underline{\underline{A}}}{\partial \underline{\underline{A}}} : d\underline{\underline{A}}$$

↪ hold true for all $d\underline{\underline{A}}$.

$$\Rightarrow \frac{\partial \det \underline{\underline{A}}}{\partial \underline{\underline{A}}} = (\det \underline{\underline{A}}) \underline{\underline{A}}^{-T}$$

$$\frac{\partial (\det \underline{\underline{A}})}{\partial A_{ij}} = (\det \underline{\underline{A}}) A_{jk}^{-1}$$

$$\begin{aligned} \hookrightarrow P &= \frac{\partial W}{\partial F} = \frac{\partial \hat{W}}{\partial C} = \frac{\partial \hat{F}}{\partial I_1} \left[\frac{\partial \Phi}{\partial I_1} \frac{\partial I_1}{\partial C} \right] + \frac{\partial \Phi}{\partial I_2} \frac{\partial I_2}{\partial C} \\ &\quad + \left[\frac{\partial \Phi}{\partial I_3} \frac{\partial I_3}{\partial C} \right] \end{aligned}$$

1st Piola stress.

$$\underline{P} = 2 \left(\left(\frac{\partial \Phi}{\partial I_1} + I_1 \frac{\partial \Phi}{\partial I_2} \right) \underline{F} + \frac{\partial \Phi}{\partial I_2} \underline{F}^T + I_3 \frac{\partial \Phi}{\partial I_3} \underline{F}^{-T} \right)$$

$$\underline{F} \underline{C}^{-T} = \underline{F} (\underline{F}^T \underline{F})^{-1}$$

$$= \underline{F} (\underline{E} + \underline{E}^T)$$

$$= \underline{F}^{-T}$$

Recall

$$\underline{D} = \frac{1}{J} \underline{P} \underline{F}^T$$


$$\text{implies. } J = \det \underline{F}$$

$$\hookrightarrow \frac{1}{J} \left[\left(\frac{\partial \Phi}{\partial I_1} + I_1 \frac{\partial \Phi}{\partial I_2} \right) \underline{E} \underline{F}^T - \frac{\partial \Phi}{\partial I_2} (\underline{E} \underline{F}^T)^T + I_3 \frac{\partial \Phi}{\partial I_3} \right] = 0.$$

Tension Test

$$\underline{F} \rightarrow \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_1 & 0 \\ 0 & 0 & \lambda_2 \end{bmatrix}$$

$$\underline{E} = \lambda_1 e_1 e_1 + \lambda_2 e_2 e_2 + \lambda_3 e_3 e_3$$



$$\underline{F}^T \underline{F} \Rightarrow \begin{pmatrix} \lambda_1^2 & 0 & 0 \\ 0 & \lambda_1^2 & 0 \\ 0 & 0 & \lambda_3^2 \end{pmatrix}$$

$$\text{tr}(\underline{C}) = \lambda_1^2 + \lambda_1^2 + \lambda_3^2$$

$$\lambda_1 = \lambda_2 = \lambda$$


$$\Rightarrow \det \underline{C} = \lambda^4 \lambda_3^2$$

$$\underline{P} = \underline{D} / \lambda$$

$$P_{33} = \frac{D_{33}}{\lambda}, \quad D_{ij} = 0, \quad j, i \neq 3$$

$$\lambda \rightarrow I_1, I_2, I_3$$

loading $\rightarrow \lambda \rightarrow$ curve.



strain ener. dens.
function.

$$\underline{\sigma} = C_1 (I_1 - 3 - 2 \log(J)) + C_2 (\ln J)^2$$

$\det \underline{F}$

(C_1, C_2 are material constants.)


common model

locally linear model:

$$\underline{\sigma} \rightarrow \bar{\underline{\sigma}}$$

Simple tensile & simple shear

determine different parameters,



As Temperature is ~~raise~~ increase

↔ entropy.

Incompressible

$$\frac{dV}{dV_0} = \frac{J}{\det \underline{F}} = I$$

Isotropic deformation

Define new energy function

$$W_{\text{new}} = W(\underline{F}) - P(J-1)$$

Lagrangian multiplier

(impose constraints)

$$\begin{aligned} P &= \frac{\partial W_{\text{new}}}{\partial \underline{F}} = \frac{\partial W}{\partial \underline{F}} - P \cdot \frac{\partial \det(\underline{F})}{\partial \underline{F}} \\ &= \frac{\partial W}{\partial \underline{F}} - P(\det \underline{F}) \underline{F}^{-T}. \end{aligned}$$

$$J=1$$

$$\underline{\sigma} = P \underline{F}^T$$

$$\boxed{\underline{\sigma} = \frac{\partial W}{\partial \underline{F}} \underline{F}^T - PI} \rightarrow \text{model.}$$

$$I_3 = \det \underline{G} = \det(\underline{F}^T \underline{F}) = \det(\underline{F}^T) \det \underline{F} = 1$$

Isotropic incompressible solid

$$W = \Phi(I_1 - I_3)$$

$$\underline{\sigma} = \left[\left(\frac{\partial \Phi}{\partial I_1} + I_2 \frac{\partial \Phi}{\partial I_2} \right) \underline{E} - \frac{\partial \Phi}{\partial I_2} \underline{b}^2 \right] - P \underline{I}$$

Corrected Note: (Based on Wiley books)

Review.

$$\text{Hyperelasticity} \rightarrow \underline{P} = \frac{\partial W(\underline{E})}{\partial \underline{F}}$$

\rightarrow gradient of strain energy density with respect to \underline{F} .

\rightarrow end exactly where u start.

$$\text{Objectivity} \sim W(\underline{F}) = \hat{W}(\underline{C}) \neq \hat{W}(\underline{E}).$$

$$\underline{C} = \underline{F}^T \underline{F}$$

$$\text{Isotropic Material} \sim W(\underline{F}) = W(\underline{F} \underline{Q}),$$

∇ orthogonal tensor \underline{Q}

Define $\underline{F} = \underline{F} \underline{Q}$ \sim if isotropic.

$$W(\underline{F}) = W(\underline{F}) \quad \nabla \underline{Q}$$

$$\text{Objectivity} \sim W(\underline{F}) = \hat{W}(\underline{C}) = W(\underline{F}^T \underline{F})$$

$$= \hat{W}(\underline{F} \underline{Q})^T (\underline{F} \underline{Q}) = \hat{W}(\underline{Q}^T \underline{C} \underline{Q}).$$

\hat{W} is a scalar invariant of Tensor \underline{C} .

$$\det[\underline{C} - \lambda \underline{I}] = (-)^3 + I_1 \lambda^2 - I_2 \lambda + I_3$$

Independent of \underline{Q} .

$$\rightarrow \begin{cases} I_1 = \text{tr} \underline{C} \\ I_2 = \frac{1}{2} [(\text{tr} \underline{C})^2 - \text{tr} \underline{C}^2] \\ I_3 = \det \underline{C} \end{cases}$$

\rightarrow for isotropic material.

$$\hat{W} = \Phi(I_1, I_2, I_3).$$

isotropic

$$\begin{aligned} \rightarrow \underline{P} &= \frac{\partial \hat{W}}{\partial \underline{F}} = 2 \underline{F} \frac{\partial \hat{W}}{\partial \underline{C}} \\ &= 2 \underline{F} \left[\frac{\partial \Phi}{\partial I_1} \left(\frac{\partial I_1}{\partial \underline{C}} \right) + \frac{\partial \Phi}{\partial I_2} \left(\frac{\partial I_2}{\partial \underline{C}} \right) + \frac{\partial \Phi}{\partial I_3} \left(\frac{\partial I_3}{\partial \underline{C}} \right) \right] \\ &\quad \downarrow \quad \downarrow \quad \downarrow \\ &\quad I_1 \underline{I}_2 - \underline{C} \quad I_3 \underline{C}^{-T} = I_3 \underline{C}^{-1} \end{aligned}$$

$$I_3 = \det \underline{C}.$$

most general: how to find $\frac{\partial \det \underline{A}}{\partial \underline{A}}$

$$d(\det \underline{A}) = \frac{\partial \det \underline{A}}{\partial \underline{A}} : d\underline{A}$$

$$= \frac{\partial (\det \underline{A})}{\partial A_{ij}} dA_{ij}.$$

$$d(\det \underline{A}) = \det(\underline{A} + d\underline{A}) - \det(\underline{A})$$

$$= \det(\underline{A} (\underline{I} + \underline{A}^{-1} d\underline{A})) - \det \underline{A}$$

$\checkmark \underline{d}\underline{B}$

$$\underline{I} + d\underline{B} \rightarrow \begin{bmatrix} 1 + dB_{11} & dB_{12} & \dots \\ \dots & 1 + dB_{22} & \dots \\ \dots & \dots & 1 + dB_{33} \end{bmatrix}$$

$$\det(\underline{I} + d\underline{B}) = 1 + \text{tr}(d\underline{B}) + O(d\underline{B})^2.$$

$$\begin{aligned} d(\det(d\underline{B})) &= \det \underline{A} (1 + \text{tr}(\underline{A}^{-1} d\underline{A})) - \det \underline{A} \\ &= (\det \underline{A}) \text{tr}(\underline{A}^{-1} d\underline{A}). \\ &= (\det \underline{A}) \cdot (\underline{A}^{-T} \cdot d\underline{A}) = \frac{\partial \det \underline{A}}{\partial \underline{A}} : d\underline{A} \end{aligned}$$

$$\Rightarrow \frac{\partial \det \underline{A}}{\partial \underline{A}} = (\det \underline{A}) \underline{A}^{-T}.$$

$$\dots + \frac{\partial \Phi}{\partial I_3} \frac{\partial I_3}{\partial \underline{C}} \rightarrow I_3 \underline{C}^{-T} = I_3 \underline{C}^{-1}$$

$I_3 = \det \underline{C}$.

$$\underline{P} = 2 \left[\left(\frac{\partial \Phi}{\partial I_1} + I_4 \frac{\partial \Phi}{\partial I_2} \right) \underline{F} - \frac{\partial \Phi}{\partial I_2} f_C + I_3 \frac{\partial \Phi}{\partial I_3} \underline{F}^{-T} \right]$$

$$\text{Recall: } \underline{\sigma} = \frac{1}{J} \cdot \underline{P} \underline{F}^T \rightarrow \text{True Stress.}$$

Allison Carter

SOS 278-5794.

Detective Todd.

-Mike Hughes → detective

Tension Test


$$\underline{F} = \begin{bmatrix} \lambda_1 \\ \lambda_2 \\ \lambda_3 \end{bmatrix}$$

$$\underline{E} = \lambda_1 \underline{e}_1 \underline{e}_1 + \lambda_2 \underline{e}_2 \underline{e}_2 + \lambda_3 \underline{e}_3 \underline{e}_3$$

$$I_1 = \text{tr} \underline{F} = \text{tr}(\underline{F}^T \underline{F}) = 2\lambda_1^2 + \lambda_3^2$$

$$I_3 = \det \underline{F} = \lambda_1^2 \lambda_3^2$$

$$I_2 = \cancel{\lambda_2^2} = \cancel{\frac{\lambda_3^2}{\lambda_1}} \quad P_{33} = \frac{\lambda_3^2}{\lambda_1}$$



common model

$$\rightarrow \Phi = C_1 (I_1 - 3 - 2 \ln J) + C_2 (\ln J)^2$$

$J = \det \underline{F}$. $\sim C_1, C_2$ material constants.

compressible isotropic materials.

Incompressible Solid.

$$\frac{dV}{dV_0} = \det \underline{F} = 1. \quad \text{"Isotropic Deformation"}$$

$$W_N = W(\underline{F}) - P(J-1).$$

$$\underline{P} = \frac{\partial W_N}{\partial \underline{F}} = \frac{\partial W}{\partial \underline{F}} - P(J-1) = \frac{\partial W}{\partial \underline{F}} - P(\det \underline{F})(\underline{F}^{-T})$$

Lagrangian multiplier

$$J=1 \Rightarrow \underline{\Omega} = \underline{P} \underline{F}^T = \frac{\partial W}{\partial \underline{F}} \underline{F}^T - \rho \underline{I}$$

$$d(\det(\underline{d}\underline{F})) = \det \underline{A} (1 + \text{tr}(\underline{A}^{-1} d\underline{A})) - \det \underline{A}$$

$$= (\det \underline{A}) \text{tr}(\underline{A}^{-1} d\underline{A})$$

$$= (\det \underline{A}) (\underline{A}^{-1} d\underline{A})$$

$$\leq \frac{\partial \det \underline{A}}{\partial \underline{A}} : d\underline{A}$$

$$\rightarrow \frac{\partial \det \underline{A}}{\partial \underline{A}} = (\det \underline{A}) \underline{A}^{-T}$$

$$\dots + \frac{\partial \Phi}{\partial I_3} \frac{\partial I_3}{\partial \underline{C}} \rightarrow I_3 \underline{C}^{-T} = I_3 \underline{C}^{-1}$$

$$I_3 = \det \underline{C}$$

$$\underline{P} = 2 \left[\left(\frac{\partial \Phi}{\partial I_2} + I_1 \frac{\partial \Phi}{\partial I_2} \right) \underline{F} - \frac{\partial \Phi}{\partial I_2} \underline{F}^{-1} \underline{C} + \left(\frac{\partial \Phi}{\partial I_3} \underline{F}^{-T} \right) \right]$$

$$\underline{\Omega} = \frac{1}{J} \underline{P} \underline{F}^T \rightarrow \text{true strss.}$$

Tension Test

For isotropic:

$$\underline{\Omega} = 2 \left[\left(\frac{\partial \Phi}{\partial I_1} + I_1 \frac{\partial \Phi}{\partial I_2} \right) b - \frac{\partial \Phi}{\partial I_2} b^2 \right] - \rho \underline{I}$$

7. Wed, Week
Incompressible hyperelasticity.

- kinematics - quantities deformation.

\underline{C} , $\underline{\epsilon}$, \underline{U} strain measures.

- Balance laws - stresses.

\underline{P} , $\underline{\Omega}$, ... other stresses measures.

e.g. 2nd Piola stress.

Biot stress.

- Constitutive Model.

Relationship Stress - strain.


$$\underline{P} = -\underline{P} \underline{F}^{-T} + 2 \left[\left(\frac{\partial \Phi}{\partial I_1} + I_1 \frac{\partial \Phi}{\partial I_2} \right) \underline{F} \right]$$

Recall I_1, I_2 are invariants of \underline{C} . $\frac{\partial \Phi}{\partial I_2} \underline{F}^{-1} \underline{C}$

$$I_1 = \text{tr} \underline{C}, \quad I_2 = \sqrt{\left[(\text{tr} \underline{C})^2 - \text{tr}(\underline{C}^2) \right]} \quad (1)$$

Lagrange multiplier enforce $\det \underline{F} = J = 1$.

E.g. Uniaxial Tension or Compression test.



$L_0 \rightarrow W_0$ and t_0 , Tension test.

$\underline{P} \cdot \underline{N}$ on all lateral surface is 0.

Ref. config. $\underline{N} = \underline{e}_2$ or \underline{e}_3 .

Undeformed lateral surfaces \leftrightarrow $P_{13} = P_{23} = P_{33} = 0, P_{12} = P_{22} = P_{32} = 0$

$\nabla \underline{x} \cdot \underline{P} = 0$. \leftrightarrow Balance law.

Simples model: $\Phi = \frac{\mu}{2} (L_i - 3)$


ideal rubber \rightarrow Neo-Hookean solid.
 $= \frac{\mu}{2} (\lambda_1^2 + \lambda_2^2 + \lambda_3^2 - 3)$

Principal coordinate.

Principal stretches.

Eqn (1): \rightarrow

$$\underline{P} = -P \underline{F}^{-T} + \mu \underline{F} \quad \leftarrow \text{Material model. (constitutive)}.$$



$$u = \lambda_1 - 1 \underline{x}_1.$$

$$u_2 = u_3 = (\lambda_2 - 1) \underline{x}_2$$

$$\rightarrow (\lambda_2 - 1) \underline{x}_3$$

$$\lambda_2 = \lambda_3$$

$$\underline{F} = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_2 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix}$$

$$\det \underline{F} = 1, \quad \lambda_1 \lambda_2 \lambda_3 = 1. \rightarrow \lambda_2 = \frac{1}{\sqrt{\lambda_1 \lambda_3}}$$

incompressibility.

Subs. into constitutive model.
make sure you satisfy boundary conditions.

* Not satisfy balance law \rightarrow Non-equilibrium states.

$$[\underline{F}] = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \frac{1}{\sqrt{\lambda_1}} & 0 \\ 0 & 0 & \frac{1}{\sqrt{\lambda_1}} \end{bmatrix}$$

$$\begin{aligned} P_{11} &= -P \lambda_1 + \cancel{\mu} \lambda_2 \cancel{\lambda_3} \lambda_1, \\ P_{22} &= -P \sqrt{\lambda_1} + \cancel{\mu} \cancel{\sqrt{\lambda_1}} \lambda_3 = P_{33}, \end{aligned}$$

$$[\underline{F}^{-T}] = \begin{bmatrix} \frac{1}{\lambda_1} & 0 & 0 \\ 0 & \sqrt{\lambda_1} & 0 \\ 0 & 0 & \sqrt{\lambda_1} \end{bmatrix}$$

$$\begin{aligned} P_{12} &= P_{21} = P_{23} = P_{32} \\ &= P_{13} = P_{31} = 0. \end{aligned}$$

$\lambda_1 = \text{const.} \Rightarrow$ equilibrium equation automatically satisfied.

B.C. are automatically satisfied.

Now, determine P .

$$B.C. = P_{22} = P_{33} = 0 \Rightarrow P\sqrt{\lambda_1} = \mu/\sqrt{\lambda_1}$$

$$\Rightarrow P = \frac{\mu}{\lambda_1}$$


Substitute back to σ_{11} .

$$\sigma_{11} = -\frac{\mu}{\lambda_1^2} + \mu\lambda_1.$$

$$\underline{\sigma} = \underline{P} \underline{F}^T$$

$$\sigma_{11} = P_{11}\lambda_1$$

$$\sigma_{11} = -\frac{\mu}{\lambda_1} + \mu\lambda_1^2.$$



$$\lambda_1 \approx 1 + \varepsilon. \quad \sigma_{11} = -\frac{\mu}{1+\varepsilon} + \mu(1+\varepsilon)^2$$

$$\varepsilon \ll 1 \quad \approx -\mu(1-\varepsilon) + \mu(1+2\varepsilon) = 3\mu\varepsilon$$

$$\mu = E/3.$$

$$\frac{E}{2(1+\nu)} = \mu$$


$$\nu = \frac{1}{2}.$$

Poisson ratio.

Plane stress deformation

(Surface traction free).

$$B.C.: P \cdot e_3 = 0, \text{ on surface}$$



$$\{ u_1(x_1, x_2), u_2(x_1, x_2)$$

$$u_3(x_1, x_2)$$

(Assumption).

$P_{13} = P_{23} = P_{33} = 0$, in the region (everywhere).

↳ Plane stress assumption.

$$\underline{F} = \begin{bmatrix} 1 + \frac{\partial u_1}{\partial x_1} & \frac{\partial u_1}{\partial x_2} & 0 \\ \frac{\partial u_2}{\partial x_1} & 1 + \frac{\partial u_2}{\partial x_2} & 0 \\ 0 & 0 & \frac{\partial u_3}{\partial x_2} \end{bmatrix}$$

~~$\frac{\partial u_3}{\partial x_1}$~~ → wrong

$\lambda_3 \rightarrow \lambda_3(x_1, x_2)$

$1 + \frac{\partial u_3}{\partial x_3}$

$$\underline{\underline{P}} = -P \underline{\underline{F}}^{-T} + \mu \underline{\underline{F}}$$

$$[\underline{\underline{P}}] = -P \begin{bmatrix} 1 + \frac{\partial u_2}{\partial \underline{x}_3} & -\frac{\partial u_1}{\partial \underline{x}_1} & 0 \\ -\frac{\partial u_1}{\partial \underline{x}_2} & 1 + \frac{\partial u_1}{\partial \underline{x}_1} & 0 \\ 0 & 0 & \frac{1}{\lambda_3} \end{bmatrix}$$

$\underline{\underline{F}}^{-T}$

$$+ \mu \begin{bmatrix} 1 + \frac{\partial u}{\partial \underline{x}_1} & 0 & 0 \\ 0 & \ddots & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix} \underline{\underline{F}} = \frac{\mu}{2} (\underline{\underline{I}}_1 - \underline{\underline{I}})$$

$$P_{33} = -\frac{P}{\lambda_3(\underline{x}_1, \underline{x}_2)} + \mu \lambda_3(\underline{x}_1, \underline{x}_2) = 0.$$

equilibrium

$$\boxed{\begin{aligned} \frac{\partial P_{11}}{\partial \underline{x}_1} + \frac{\partial P_{12}}{\partial \underline{x}_2} + \frac{\partial P_{13}}{\partial \underline{x}_3} &= 0 \\ \frac{\partial P_{21}}{\partial \underline{x}_1} + \frac{\partial P_{22}}{\partial \underline{x}_2} &= 0. \end{aligned}}$$

$$P_{11} = \mu \lambda_3^3 \cdot \left(1 + \frac{\partial u_2}{\partial \underline{x}_3}\right) + \mu \left(1 + \frac{\partial u}{\partial \underline{x}_1}\right).$$

Oct. 13, 2021. Wed.

Review:

plane stress: incompressible neo-Hookean solid

$\underline{\underline{F}}$ for plane stress.

$$[\underline{\underline{F}}] = \begin{bmatrix} x_{1,1} & x_{1,2} & 0 \\ x_{2,1} & x_{2,2} & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix} \quad \underline{\underline{F}}_{in} = \begin{bmatrix} x_{1,1} & x_{1,2} \\ x_{2,1} & x_{2,2} \\ 0 & 0 \end{bmatrix}, \alpha = \frac{\partial}{\partial \underline{x}_\alpha}$$

$$x_\alpha = \underline{x}_\alpha + u_\alpha(\underline{x}_1, \underline{x}_2), \quad \alpha = 1, 2.$$

Independent of \underline{x}_3 .

λ_3 is the out-of-plane stretch ratio,

$$\lambda_3(\underline{x}_1, \underline{x}_2).$$

$$\underline{\underline{F}}_{in} = X_\alpha \beta \underline{\underline{e}}_\alpha \underline{\underline{e}}_\beta$$

neo-Hookean

$$\underline{\underline{P}} = -P \underline{\underline{F}}^{-T} + \mu \underline{\underline{F}}$$

for tiny incompressibility

$$J = \det \underline{\underline{F}} = 1 = (\det \underline{\underline{F}}_{in}) \lambda_3 = 1$$

$$\Rightarrow \det \underline{\underline{F}}_{in} = \frac{1}{\lambda_3}$$

$$(x_{1,1}x_{2,2} - x_{1,2}x_{2,1})$$

$$\begin{bmatrix} F \\ F \end{bmatrix} = \begin{bmatrix} x_{2,2}\lambda_3 & -x_{2,1}\lambda_3 & 0 \\ -x_{1,2}\lambda_3 & x_{1,1}\lambda_3 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix}$$

(*) Next Step:

$$P_{11} = -P x_{2,2} \lambda_3 + \mu x_{1,1}$$

$$P_{22} = -P \lambda_3 x_{2,1} + \mu x_{1,2}$$

$$P_{21} = -P \lambda_3 x_{1,2} + \mu x_{2,1}$$

$$P_{12} = -P \lambda_3 x_{1,1} + \mu x_{2,2}$$

$P_{13} = P_{23} = P_{31} = P_{32} = 0$, consistent with the plane stress assumption.

$$P_{33} = 0 = -P \frac{1}{\lambda_3} + \mu \lambda_3 = 0$$

$$\therefore P = \mu \lambda_3^2$$

Substitute

use LMB: (ignore body forces.)
& acceleration

$$P_{11,1} + P_{12,2} = 0$$

$$(P \lambda_3^2 x_{2,2})_1 + \mu x_{1,11} + (\mu \lambda_3^2 x_{1,2})_{12} + \mu x_{1,22} = 0$$


$$0 = P_{21,1} + P_{22,2} = (\mu \lambda_3^3 + x_{1,2})_{21} + \mu x_{2,11} - (\mu \lambda_3^3 x_{1,1})_{12} + \mu x_{2,22} = 0$$

$$\mu \nabla_x^2 x_1 + \mu ((\lambda_3^3 x_{1,2})_2 - (\lambda_3^3 x_{2,2})_1) = 0$$

$$\mu \nabla_x^2 x_2 + \mu [] = 0$$

$$\lambda_3 = \frac{1}{x_{1,1} x_{2,2} - x_{2,1} x_{1,2}}$$

coupled PDEs for unknowns x_1, x_2



BCs. $\bar{x}_2 = \pm l_0$,
 $u_1 = 0$. $u_2 = \pm \frac{A}{l_0}$

on lateral sides:

$$\bar{x}_1 = -l_0 \quad P_{11} = P_{21} = 0$$

$$\bar{x}_1 = l_0 \quad P_{11} = P_{21} = 0$$

on crack faces. $-l_0 \leq \bar{x}_1 \leq l_0$, $P_{12} = P_{22} = 0$


$$P_{12} = P_{22} = 0$$

Plane Strain

Assumption:

$$\left\{ \begin{array}{l} u_1 = u_1(\bar{x}_1, \bar{x}_2) \text{ imply} \\ u_2 = u_2(\bar{x}_1, \bar{x}_2) \\ u_3 = 0 \end{array} \right. \Rightarrow \underline{\underline{F}} = \begin{bmatrix} x_{1,1} & x_{1,2} & 0 \\ x_{2,1} & x_{2,2} & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

$$\det \underline{\underline{F}} = 1. \rightarrow \text{to determine } \underline{\underline{P}}$$



linear elasticity

kinematics.

$$\underline{\underline{\epsilon}} = \frac{u_{i,j} + u_{j,i}}{2} \quad \rightarrow i = \frac{\partial}{\partial x_i}$$

one simple strain measure, only).

Small strain tensor

$$\frac{\partial \bar{u}_j}{\partial x_j} = -P_i \bar{B}_i \quad \text{Equilibrium}$$

All you need, is constitutive model.

large deformation $\xrightarrow{\text{linearize}}$ constitutive model.

$$\frac{\partial W(\underline{\underline{\epsilon}})}{\partial \underline{\underline{\epsilon}}} = 0 \quad \text{small for all in linear stage} \quad (\hat{w} = \bar{w} = w)$$

$$\underline{\underline{\sigma}}_{ij} = k_{ijkl} \underline{\underline{\epsilon}}_{kl} \quad \text{(Expect)}$$

independent of strain tensor

$$\underline{\underline{\sigma}}_{ij} = \frac{\partial W}{\partial \underline{\underline{\epsilon}}_{ij}} \quad \text{quadratic function of strain}$$

$$(\text{try}) \quad W = \frac{1}{2} K_{ijkl} \epsilon_{ij} \epsilon_{kl}$$

$$\text{Ors} \quad \left(\frac{\partial W}{\partial \epsilon_{0is}} \right) = \frac{1}{2} \underbrace{K_{ijkl} \delta_{ir} \delta_{js} \epsilon_{kl}}_{K_{rskl}} + \underbrace{K_{ijkl} \epsilon_{ij}}_{K_{jirs} (\delta_{kr} \delta_{ls})}$$

$$\sigma_{rs} = \frac{1}{2} [K_{rskl} \epsilon_{kl} + K_{jirs} \epsilon_{ij}]$$

$$= \frac{1}{2} [K_{rskl} \epsilon_{kl} + K_{kirs} \epsilon_{ki}]$$

$$\sigma_j = \frac{1}{2} [K_{ijkl} \epsilon_{kl} + K_{klij} \epsilon_{kl}]$$

$$\sigma_j = \frac{1}{2} [K_{ijkl} \epsilon_{kl} + K_{klij} \epsilon_{kl}]$$

$\overbrace{K}^{=}$

$$K_{ijkl} = K_{klij} \quad \text{Symmetric in } kl, ij$$

\downarrow
81 component
elements

Symmetry of $\sigma_j \Rightarrow K_{ijkl} = K_{jikl}$

Symmetry of $\epsilon_{kl} \Rightarrow K_{ijkl} = K_{jikl}$.

$$9 \times 9 \rightarrow 6 \times 6$$

\downarrow

36 independent components

The existence of W .

$$\sigma_{ij} = \frac{\partial W}{\partial \epsilon_{ij}}$$

implies $K_{ijkl} = K_{jikl}$

$$\downarrow$$

~~21~~
21 ind. comp.

$$\downarrow$$

most common

model for elastic

Oct. 15, office hours.

C_1, C_2 , & shear modulus }
Poisson's ratio. }

letting $\lambda \rightarrow 1$

at very small \rightarrow agrees with Hooke's law.

Plot the curve.

normalize the stress for shear modulus

other terms & ratio of C_1, C_2

function only of the
Poisson's ratio

reasonable choice $\nu = 0.45$

0.5 (incompressible).

a lot of curve with different

Poisson's ratio.

* normalized shear modulus G .

Piola & Cauchy normalized by

You can normal the stress by G .

λ_1, λ_3

$$\frac{\lambda^2}{\lambda_3} + 1 + \frac{C_2}{C_1} \ln(\lambda_1 \lambda_3) = 0$$

$$-\lambda^2 - 1 + \left(\frac{C_2}{C_1} \right) \ln(\lambda_1 \lambda_3) = 0$$

$f(2) \leftarrow$ incompressible $\frac{C_2}{C_1} \rightarrow$ huge
 $\downarrow G$.

$\lambda_1 \lambda_3 = 1$. \leftarrow Lambert function

1st order expansion

John Hutchinson

λ

λ_1, λ_3

λ

$1 \ln - 0.45 \lambda_3 = 0$

$\lambda_1 = 0.95 \lambda$

Oct. 18th, 2021, Mon.

Review.

Linear Elasticity:

$$W = \frac{1}{2} k_{ijkl} \epsilon_{ij} \epsilon_{kl}$$

$$\sigma_{ij} = \frac{\partial W}{\partial \epsilon_{ij}}$$

k_{ijkl} has 21 independent constants.

$$k_{ijkl} = k_{jilm} = k_{ijlk} = k_{mlij}$$

Anisotropic:

$$\sigma_{ij} = k_{ijkl} \epsilon_{kl}$$

$$W = \frac{1}{2} \sigma_{ij} \epsilon_{ij} = \frac{1}{2} \underline{\sigma} \cdot \underline{\epsilon}$$

Isotropy solids:

$$k_{ijkl} = \lambda \delta_{ij} \delta_{kl} + \mu (\delta_{ik} \delta_{jl} + \delta_{il} \delta_{jk})$$

λ, μ are constants.

General form of isotropic 4th order Tensor

"Introduction to Cartesian Tensors"

Jim ~~Khader~~

Knowles

$$\sigma_{ij} = \lambda \delta_{ij} \epsilon_{kk} + \mu [\epsilon_{ij} + \epsilon_{ji}]$$

$$= 2\mu \epsilon_{ij} + \lambda \epsilon_{kk} \delta_{ij}$$

Generalized Hooke's Law

μ, λ are called lame constants.

$$\sigma_{kk} = 2\mu \epsilon_{kk} + 3\lambda \epsilon_{kk}$$

$$\sigma_{kk} = (2\mu + 3\lambda) \epsilon_{kk}$$

$$2\mu \epsilon_{ij} + \lambda \frac{\sigma_{kk}}{(2\mu + 3\lambda)} \delta_{ij} = \sigma_{ij}$$

$$\epsilon_{ij} = \frac{\sigma_{ij}}{2\mu} - \frac{\lambda \sigma_{kk}}{(2\mu + 3\lambda)} \cdot \frac{1}{2\mu} \delta_{ij}$$

$$\epsilon_{ij} = \frac{(1+\nu)}{E} \sigma_{ij} - \frac{2\nu \sigma_{kk}}{E} \delta_{ij}$$

ν - Poisson's ratio.

E - Young's Modulus

$$\frac{1}{2\mu} = \frac{1+2\nu}{E} \Rightarrow \mu = \frac{E}{2(1+2\nu)}$$

Shear Modulus. $\frac{1}{E} = \frac{\lambda}{(2\mu + 3\lambda) 2\nu}$

Tension test

$$\sigma_{ii} = \sigma, \quad \sigma_{ij} = 0, \quad (i, j \neq 1)$$

$$\epsilon_{ii} = \frac{\sigma_{ii}}{E}$$

\hookrightarrow tension modulus

$$\epsilon_{ii} = \epsilon_{33} = -\frac{\nu}{E} \sigma_{ii}$$

$$-\frac{\epsilon_{ii}}{\sigma_{ii}} = \nu,$$

Poisson's ratio ≥ 0 .

There are negative Poisson's ratio material but anisotropic.

Apply a pure hydrostatic tension.

$$\epsilon_{ij} \leftarrow \epsilon_{kk} = -\frac{(1+\nu)}{E} P \delta_{ij} + \frac{3\nu}{E} \delta_{ij}$$

if $\sigma_{ij} = -P \delta_{ij}$.

$$\epsilon_{ii} = \epsilon_{ii} = \epsilon_{33} = -\frac{(1+2\nu)}{E} P$$

$$\text{Bulk Modulus} = -\frac{1}{K} P \rightarrow -P/K$$

~~$$k = \frac{E}{(1+2\nu)(1-2\nu)}$$~~

$$\nu \rightarrow \frac{1}{2}, \quad k \rightarrow \infty$$

\downarrow
 $\tau_{ii} = 0$: incompressible solid

$$\sigma_{ij} = 2\mu \epsilon_{ij} + \lambda \epsilon_{kk} \delta_{ij}$$

~~$$\sigma_{ij} = 2\mu \epsilon_{ij} \rightarrow \sigma_{ij} = 2\mu \epsilon_{ij} - P \delta_{ij}$$~~

~~$$\lambda = \frac{EV}{(1+\nu)(1-2\nu)}$$~~

General form relation for linear elasticity

$$\begin{aligned} \textcircled{1} \quad \epsilon_{ij} &= \frac{u_{ij} + u_{ji}}{2} \\ \textcircled{2} \quad \sigma_{ij}, j &= -P B_i \\ \textcircled{3} \quad \sigma_{ij} &= \sigma_{ji} \\ \textcircled{4} \quad \sigma_{ij} &= 2\mu \epsilon_{ij} + \lambda \epsilon_{kk} \delta_{ij} \end{aligned}$$

- Substitute $\textcircled{1}$ into $\textcircled{4}$ to express strains in terms of displacements.


- Substitute stress into $\textcircled{2}$ to obtain

$$G \nabla^2 u + (\lambda + G) \nabla(\nabla \cdot u) = -P B$$

\hookrightarrow Navier's equation (3 PDEs)

Subject Navier's Eq. to BCs

Typical e.g.



σ_n


traction is prescribed.

Mixed BCs

Displacement prescribed.


$$\{ \sigma_{ij} n_j = T_i(\underline{x}), \underline{x} \in S_T \}$$

$$S_u: u_i = f_i(\underline{x}), \underline{x} \in S_v$$




$$[2\mu \left[\frac{u_{i,j} + u_{j,i}}{2} \right] + \lambda u_{kk} \delta_{ij}]_{nj} = T_i(\underline{x}).$$

fixed boundary




(a)

In linear elasticity.



\Leftrightarrow
equiv



Build up complex solutions from simple ones.

$$\sigma_{ij}, j = -P_0 B_i$$

Suppose we guess a solution for σ that also satisfies the Boundary Conditions (BC) (traction BC).



$$B = g \mathbb{E}_3$$

If we guess: σ_{ij}^* .

compute displacement.

$$u_{ij}^* = \frac{(1+\nu)}{E} \sigma_{ij}^* - \frac{\nu}{E} \sigma_{kk}^* \delta_{ij}$$

Integrate strain ϵ^* to get displacement field

There are three unknown disp.

$u_1, u_2, u_3 \rightarrow$ (position).

I guess $\sigma_{ij}^* \rightarrow \epsilon_{ij}^*$

$$\epsilon_{ij}^* = \frac{u_{ij} + u_{j,i}}{2}$$

6 equations here

6 equations, & 3 unknowns.

the solutions may not exists, if e.
not unique.

Plane strain.

linear elas.

$$u_3 = 0, \quad \epsilon_{11} = \frac{\partial u_1}{\partial x_1} = u_{1,1}$$

$$\epsilon_{22} = \frac{\partial u_2}{\partial x_2} = u_{2,2}$$

$$\epsilon_{12} = \frac{1}{2} \left(\frac{\partial u_1}{\partial x_2} + \frac{\partial u_2}{\partial x_1} \right) = \frac{u_{1,2} + u_{2,1}}{2}$$

$$\epsilon_{ij} (\text{rest}) = 0$$

$u_3 = 0, \quad u_{1,2} \text{ depends on } x_1, x_2 \text{ only.}$

You can show that

$$-\epsilon_{12,22} + \epsilon_{11,22} + \epsilon_{22,11} = 0$$

$$\frac{\partial^2 \epsilon_{ij}}{\partial x_1 \partial x_2} = (\epsilon_{12})_{12}$$

↳ compatibility equation for plane strain

: puts a constraint on the strain

$$1 - \epsilon_{ij} = \frac{\sigma_{ij} (1+\nu)}{E} - \frac{\nu \sigma_{kk} \delta_{ij}}{E}$$

↳ you will find this:

$$\nabla^2 (\sigma_u + \sigma_v) = \frac{1}{(1-\nu)} \nabla \cdot (\rho_0 \mathbf{k})$$

compatibility equation for stress

Wed., Oct. 20, 2021. Week 9 (?)

Linear Elasticity

6 Eqs: $\epsilon_{ij} = \frac{u_{ij} + u_{ji}}{2}$ - kinematics.

3 Eqs: $\nabla_j \cdot j = -\rho_0 B_i$ - Balance laws.

6 Eqs: $\epsilon_{ij} = \frac{(1+\nu) \sigma_{ij}}{E} = \frac{\nu \sigma_{kk}}{E} \delta_{ij}$

Constitutive model.

15 Eqs.

unknowns: $\epsilon_{ij}, \sigma_{ij}, u_i, \sigma_{ij}$. 15 unknowns.

Navier Eqs. (Displacement formulation).

$$G \nabla^2 u + (\lambda + G) \nabla (\nabla \cdot u) = -\rho_0 B$$

3 Eqs, & 3 unknowns. u_1, u_2, u_3 .

Independent variables, x_i .
positions.

dependent is u_i .

Most useful when body is subject to BCs.

Antiplane shear deformation.

$u_\alpha \equiv 0$. $\alpha = 1, 2$. No in-plane disp.

$u_3 = u(I_1, I_2)$. independent of I_3 .



$$\epsilon_{\alpha\beta} = 0, \alpha = 1, 2$$

$$\epsilon_{33} = \frac{\partial u_1}{\partial I_3} = 0$$

Only non-vanishing strain are.

engineering strain $\epsilon_{13} = \epsilon_{31} = \frac{1}{\sqrt{I_1}} \frac{\partial u}{\partial I_1} = \frac{1}{\sqrt{I_1}} \gamma_1$
 $\epsilon_{23} = \epsilon_{32} = \frac{1}{\sqrt{I_2}} \frac{\partial u}{\partial I_2} = \frac{1}{\sqrt{I_2}} \gamma_2$

Constitutive model.

$\sigma_{\alpha\beta} = 0$ in-plane stress

$$\sigma_{33} = 0$$

$$\left\{ \begin{array}{l} \sigma_{13} = \sigma_{31} = G \gamma_1 \\ \sigma_{23} = \sigma_{32} = G \gamma_2 \end{array} \right.$$

Equilibrium Eqs are identically satisfied in
1 & 2 directions ($B_1 = B_2 = 0$)

$$\frac{\partial \sigma_{31}}{\partial x_1} + \frac{\partial \sigma_{32}}{\partial x_2} = 0$$

↓

$$\frac{\partial T_1}{\partial x_1} + \frac{\partial T_2}{\partial x_2} = 0 \quad (\Rightarrow) \quad \nabla_x \cdot \vec{T} = 0. \quad \textcircled{1}$$

no body force.

$$T = T_1 e_1 + T_2 e_2.$$

T_1 & T_2 must satisfy the fact that,

$$T_1 = \frac{\partial w}{\partial x_1}, \quad T_2 = \frac{\partial w}{\partial x_2} \Rightarrow \frac{\partial T_1}{\partial x_2} = \frac{\partial T_2}{\partial x_1}.$$

Stress compatibility

the eqn. int. $\frac{\partial T_1}{\partial x_2} = \frac{\partial T_2}{\partial x_1}. \quad \textcircled{2}$

Introduce a stress function ϕ .

$$T_1 = \frac{\partial \phi}{\partial x_2} \quad T_2 = -\frac{\partial \phi}{\partial x_1}. \quad \textcircled{3}$$

Subs. $\textcircled{3}$ into $\textcircled{1}$, we see that

$\textcircled{1}$ is satisfied automatically.

$$\frac{\partial T_1}{\partial x_1} = \frac{\partial^2 \phi}{\partial x_1 \partial x_2} \quad \frac{\partial T_2}{\partial x_2} = \frac{\partial^2 \phi}{\partial x_2 \partial x_1}$$

Substitute $\textcircled{3}$ into $\textcircled{2}$.

$$\frac{\partial^2 \phi}{\partial x_2} + \frac{\partial^2 \phi}{\partial x_1} = 0 \quad \text{or} \quad \nabla_x^2 \phi = 0.$$

3

Replace Eqn. in $\textcircled{2}$.

Stress function approach

Disp. Formulation. $T_1 = G \frac{\partial w}{\partial x_1}$.

$$T_2 = G \frac{\partial w}{\partial x_2} \quad \nabla_x^2 w = 0.$$

Substitute into $\textcircled{1}$.



Simpliest form of
Navier's Equation.

$$\phi + i \cdot w = f(z).$$



$$\phi + i \cdot w$$

* Anti-plane shear.



Reminder: Plane strain

$$U_\alpha(X_1, X_2), \quad \alpha = 1, 2$$

$$\epsilon_3 = 0$$

$\epsilon_{11}, \epsilon_{22}, \epsilon_{33}$ (all others strain components = 0).

Compatibility.

$$\frac{\partial^2 \epsilon_{11}}{\partial X_2^2} - \frac{\partial^2 \epsilon_{12}}{\partial X_1 \partial X_2} + \frac{\partial^2 \epsilon_{21}}{\partial X_1^2} = 0$$

Note

$\frac{\partial \sigma_{33}}{\partial X_1} = 0$, is automatically satisfied.

$\sigma_{31} = \sigma_{32} = 0$, σ_{33} is independent of X_3 .

$$\epsilon_{33} = 0 \Rightarrow \frac{\sigma_{33}}{E} - \frac{\nu(\sigma_{11} + \sigma_{22})}{E} = 0$$

$$\boxed{\sigma_{33} = \nu(\sigma_{11} + \sigma_{22})}$$

Equilibrium equation is identically satisfied
in 3 direction..

$$\text{Therefore: } \frac{\partial \sigma_{11}}{\partial X_1} + \frac{\partial \sigma_{22}}{\partial X_2} = \rho_b B_1$$

$$\frac{\partial \sigma_{11}}{\partial X_1} + \frac{\partial \sigma_{22}}{\partial X_2} = \rho_b B_2$$

Equilibrium Eqs (LMB) $\rightarrow (4a, b)$

Assuming $B = 0$.

Airy stress function, ϕ .

$$\sigma_{11} = -\frac{\partial^2 \phi}{\partial X_2^2}$$

$$\sigma_{22} = -\frac{\partial^2 \phi}{\partial X_1^2}$$

$$\sigma_{12} = \frac{\partial^2 \phi}{\partial X_1 \partial X_2}$$

(5)

Substitute (5) into (4a, b).

$$\epsilon_{11} = \frac{\sigma_{11}}{E} - \frac{\nu(\sigma_{11} + \sigma_{22})}{E}$$

$$\epsilon_{22} = \frac{\sigma_{22}}{E} - \frac{\nu(\sigma_{11} + \sigma_{22})}{E} \quad \boxed{\sigma_{33} = \nu(\sigma_{11} + \sigma_{22})}$$

$$\epsilon_{12} = \frac{\sigma_{12}}{E} - \frac{\nu(\sigma_{11} + \sigma_{22})}{E} \quad \frac{\sigma_{12}}{E} \rightarrow T \cdot \boxed{1}$$

Simplified plane

$$\epsilon_{11} = \frac{1+\nu}{E} [(1-\nu)\sigma_{11} - \nu\sigma_{22}] \quad \text{strain constitutive model}$$


$$T = \frac{G}{E} \quad \epsilon_{22} = \frac{1+\nu}{E} [(1-\nu)\sigma_{22} - \nu\sigma_{11}]$$

Non-zero Inplane stress fields are



$$\sigma_{11}, \sigma_{22}, \sigma_{12}$$

Non-zero Out-of-plane stress.

$$\sigma_{33} = -\nu(\sigma_{11} + \sigma_{22})$$




S_T : Traction Boundary Conditions,



Stresses \propto stress function

$$\left\{ \begin{array}{l} \sigma_{11} = \frac{\partial^2 \phi}{\partial x_1^2} \\ \sigma_{22} = \frac{\partial^2 \phi}{\partial x_2^2} \\ \sigma_{12} = -\frac{\partial^2 \phi}{\partial x_1 \partial x_2} \end{array} \right.$$

Plane stress (finite deformation).



$t \ll L$, and other in-plane dimensions.

$\sigma_{13} = \sigma_{23} = \sigma_{33} = 0 \rightarrow$ three non zero stresses
 $\sigma_{11}, \sigma_{22}, \sigma_{12}$

$$\varepsilon_{13} = \varepsilon_{23} = \varepsilon_{32} = \varepsilon_{31} \approx 0.$$

ε_{xy} is approx. independent of x_3 .

$$\frac{\nabla V}{V} = \varepsilon_{11} + \varepsilon_{22} + \varepsilon_{33} \approx 0$$

↓
incompressible

Constitutive model

Plane stress. $\sigma_{13} = \sigma_{23} = \sigma_{33} = 0$.

$$\varepsilon_{11} = \frac{\sigma_{11}}{E} - \nu \left(\frac{\sigma_{22} + \sigma_{33}}{E} \right) = \frac{\sigma_{11}}{E} - \frac{2\nu\sigma_{22}}{E}$$

$$\varepsilon_{12} = \frac{\sigma_{12}}{2G}$$

$$\cancel{\varepsilon_{22}} = \frac{\sigma_{22}}{E} - \nu \left(\frac{\sigma_{11} + \sigma_{33}}{E} \right) = \frac{\sigma_{22}}{E} - \frac{2\nu\sigma_{11}}{E}$$

Plane strain

$$\varepsilon_{11} = \frac{\sigma_{11}}{E} - \frac{\nu(\sigma_{22} + \sigma_{33})}{E}$$


$$= \frac{\sigma_{11}}{E} - \frac{\nu(\sigma_{22} + \nu(\sigma_{11} + \sigma_{22}))}{E}$$

$$= \frac{(1-\nu^2)\sigma_{11}}{E} - \frac{\nu(1+\nu)\sigma_{22}}{E}$$

Compatibility & equilibrium.

$$\nabla^4 \phi = 0. \quad (\text{No body force}).$$


$$\begin{array}{c} v \\ \text{plane stress} \end{array} \longrightarrow \begin{array}{c} v \\ \text{plane strain} \end{array}$$



$$\underline{\varepsilon} = \frac{\nabla u + (\nabla u)^T}{2}$$

$$\varepsilon_{ij} = \frac{u_{ij} + u_{ji}}{2}$$

$$\underline{u} = u_r \underline{e}_r + u_\theta \underline{e}_\theta$$



$$\begin{cases} \underline{e}_r = \cos\theta \underline{e}_1 + \sin\theta \underline{e}_2 \\ \underline{e}_\theta = -\sin\theta \underline{e}_1 + \cos\theta \underline{e}_2 \end{cases}$$

$$(\sim -\frac{u_0}{r}) e_0 e_0$$

In Cartesian coordinates

$$\nabla u = \frac{\partial u_i}{\partial x_j} e_i e_j$$

$$\nabla u = \frac{\partial u_i}{\partial x_j} e_i e_j$$

$$\nabla u = \frac{\partial u_i}{\partial x_j} e_j e_i = (\nabla u)^T$$

$$\nabla = e_r \frac{\partial}{\partial r} + e_\theta \frac{\partial}{\partial \theta}$$

$$e_r \frac{\partial}{\partial r} + \frac{e_\theta}{r} \frac{\partial}{\partial \theta}$$

$$\nabla u = \left(e_r \frac{\partial}{\partial r} + \frac{e_\theta}{r} \frac{\partial}{\partial \theta} \right) (u_r e_r + u_\theta e_\theta)$$

$$= e_r \cdot \frac{\partial (u_r e_r)}{\partial r} + e_r \cdot \frac{\partial (u_\theta e_\theta)}{\partial r}$$

$$= e_r \cdot \frac{\partial u_r}{\partial r} e_r + e_r \left(\frac{\partial u_\theta}{\partial r} e_\theta \right)$$

$$+ \frac{e_\theta}{r} \left(\frac{\partial u_r}{\partial \theta} e_r + u_r \frac{\partial e_r}{\partial \theta} \right)$$

$$+ \frac{e_\theta}{r} \frac{\partial u_\theta}{\partial \theta} e_\theta + \frac{e_\theta}{r} u_\theta (e_r)$$

$$\frac{\partial e_\theta}{\partial \theta} = -\cos \theta e_1 - \sin \theta e_2 = -e_r$$

$$\nabla u = \frac{\partial u_r}{\partial r} e_r e_r + \frac{\partial u_\theta}{\partial r} e_\theta e_\theta + \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} e_\theta e_r$$

$$+ \left[\frac{u_r}{r} \cdot e_0 e_0 + \frac{1}{r} \cdot \frac{\partial u_\theta}{\partial \theta} \right] e_0 e_0$$

$$\varepsilon = \frac{\partial u_r}{\partial r} e_r e_r + \left[\frac{u_r}{r} + \frac{1}{r} \cdot \frac{\partial u_\theta}{\partial \theta} \right] e_0 e_0$$

$$+ \frac{1}{r} \left[\frac{\partial u_\theta}{\partial r} - \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} - \frac{u_r}{r} \right] e_0 e_r + \underbrace{[]}_{e_{0r}} []$$

e_{0r}

∇u (Cartesian) $\{e_1, e_2\}$

\downarrow

u_r, u_θ, u_{00} polar coordinates

$\{e_r, e_\theta\}$

Oct. 27, 2021. Wed

★ $\{$ Anti-plane shear, Plane strain, Plane stress $\}$ Stress functions.

$\nabla^2 \phi = 0$ harmonic
 $\nabla^4 \phi = 0$ biharmonic

$$u = u_r e_r + u_\theta e_\theta$$

$$e_r = \cos\theta e_1 + \sin\theta e_2$$

$$e_\theta = -\sin\theta e_1 + \cos\theta e_2$$

$$\sigma = \sigma_{ij} e_i e_j = \sigma_{rr} e_r e_r + \dots$$

$\nabla \cdot \underline{\sigma} \rightarrow$ Easy in Cartesian Coordinate

Plane strain or plane stress

$$\left\{ \frac{\partial \sigma_{rr}}{\partial r} + \frac{1}{r} \cdot \frac{\partial \sigma_{\theta\theta}}{\partial \theta} + \frac{\sigma_{rr} - \sigma_{\theta\theta}}{r} = 0, \right.$$

$$\left. \frac{1}{r} \cdot \frac{\partial \sigma_{\theta\theta}}{\partial \theta} + \frac{\partial \sigma_{\theta\theta}}{\partial r} + \frac{\partial \sigma_{rr}}{\partial r} = 0 \right.$$

Derive

THIS ONE!!!!

Third eqn. automatically satisfied.

$$\sigma_{rr} = \frac{\phi_r}{r} + \frac{\phi_{r,\theta\theta}}{r}$$



$$\phi_{r,\theta\theta} = \phi_{,rr} \quad \sigma_{\theta\theta} = -(\phi_{,\theta}/r), r$$

$$\nabla^4 \phi = 0 = \left[\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2}{\partial \theta^2} \right] \left[\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2}{\partial \theta^2} \right] \phi = 0$$


Technique of solution

① Fourier transform.

[Strip or half space problem]



② superposition. (Simple idea x technique)



③ separation of variables.

(works for simple geometry)

Complex variable method

function theory

(Antiplane shear).

$$\nabla^2 \phi = 0 \quad \text{and} \quad \nabla^2 w = 0.$$

$$\boxed{\begin{aligned} \phi_{,x} &= -\sigma_{3z}, & \phi_{,y} &= \sigma_{3x} \end{aligned}} \quad \boxed{\phi}$$

$$x = x_1, \quad y = x_2 \quad (\text{stress function})$$

$$\boxed{\begin{aligned} \sigma_{13} &= G \frac{\partial w}{\partial x} = G w_{,x} \\ \sigma_{23} &= G \frac{\partial w}{\partial y} = G w_{,y} \end{aligned}} \quad \boxed{②}$$

①, ②,

$$\Rightarrow \phi_{,x} = G w_{,y} \quad \boxed{③}$$

$$\phi_{,y} = -G w_{,x}$$

Define a complex function.

$$f(z) = \phi + iGw$$

\uparrow imaginary part of f
real part of f .

③ is a rotation between real part of f and its imaginary parts

③ is called the Cauchy-Riemann Eqs.

$$h(z) = u + iv. \quad \text{CR}$$

$$\begin{cases} u_{,x} = v_{,y} \\ u_{,y} = -v_{,x} \end{cases}$$

Any function with Real & Imaginary parts that satisfies the CR Eqs is called an analytic function in a Domain D .

$$\begin{cases} \phi_{,xx} = G w_{,xy} \\ \phi_{,xy} = -G w_{,xy} \\ \nabla^2 \phi = 0 \end{cases}$$

$$\cos x \leftarrow \text{Replace } x \text{ by } z. = \cos z.$$

$$\frac{e^x + e^{-x}}{2}$$

$$e^z = e^{x+iy} = e^x e^{iy}$$

$$(e^{x\cos y} + ie^{x\sin y}) = e^x [\cos y + i \sin y]$$

$$+ e^{x\cos y} (e^{x\sin y} - i e^{-x\sin y}) = e^x \cos y + i e^x \sin y$$

$$= \frac{(e^x + e^{-x}) \cos y + i(e^x - e^{-x}) \sin y}{2}$$

$$= \underbrace{\cosh x \cos y}_{u} + i \underbrace{\sinh x \sin y}_{v} = \omega z.$$

$$\begin{cases} u_{,x} = v_{,y} \\ u_{,y} = -v_{,x} \end{cases} \quad \checkmark \rightarrow \text{CR}$$

$$f(z) = \sum_{n=0}^{\infty} a_n (z - z_0)^n \rightarrow a_n = \frac{1}{n!} f^{(n)}(z_0)$$

analytic solution.

$$= \frac{\frac{d}{dz} f(z)}{z - z_0} \Big|_{z_0}$$

$$f(z) = \sum_{n=0}^{\infty} a_n n(z - z_0)^{n+1}$$

$$\begin{aligned} f'(z) &= \phi_x + iGw_x \\ &= \frac{\phi_y}{i} + \frac{iGw_y}{i} \\ &= -i\phi_y + Gw_y \end{aligned}$$

$$\boxed{\phi = \operatorname{Re} [\bar{z}\varphi(z) + \chi(z)]}$$

Analytic

$$\bar{z} = x - iy.$$

take this methods.

displacements:

$$2G(u_1 + iu_2) = x\varphi(z) - \bar{z}\varphi'(z) - \bar{\psi}(z)$$

$$\psi(z) = \chi'(z) = \frac{d\chi}{dz}.$$

$\chi = 3 - 4\nu$. plane strain

$$= \frac{3-\nu}{1+\nu} \quad \text{stress}$$

$$\sigma_{11} + \sigma_{22} = 2[\varphi'(z) + \bar{\psi}'(z)]$$

$$\sigma_{22} + i\sigma_{12} = \varphi'(z) + \bar{\psi}'(z) + \bar{z}(\varphi''(z) + \bar{\psi}'(z))$$

$$\frac{dz^n}{dz} = n z^{n-1}$$

* Any rule with different factors can be applied
→ complex variable theory

(doesn't depend on the hole size).

$$\frac{\sigma_{11}^*}{\sigma_{\infty}} = \text{const. independent}$$

of σ_{∞}

(far-away)

$$\sigma_{11} = \sigma_{\infty} f(\frac{x}{a}, 0)$$

$$= \sigma_{\infty} f(\frac{x}{a}, \frac{y}{a})$$

$$\frac{\sigma_{11}^*}{\sigma_{\infty}} = f(0, 1)$$

(infinite). $\rightarrow w \gg a$.

$$\underset{BC}{=} \sigma_{11} = \sigma_{\infty}, \quad \text{as } |x| \rightarrow \infty$$

$$\text{I \& II. } \sigma_{21} = 0, \quad \text{as } |x| \rightarrow \infty$$

$$\text{III \& IV: } \sigma_{12} = 0, \quad \text{as } |y| \rightarrow \infty$$

$$\sigma_{22} = 0, \quad \text{as } |y| \rightarrow \infty$$

$$\underset{BC \text{ on hole}}{=} \underline{\sigma} \cdot \underline{n} = 0 \quad \text{on hole.}$$

$$\underline{n} = \underline{e}_r = \cos \theta \underline{e}_r + \sin \theta \underline{e}_\theta$$

$$\sigma_{11} n_\beta = 0 \rightarrow r = a = \sqrt{x^2 + y^2}$$

$$\sigma_{11} \cos \theta + \sigma_{12} \sin \theta = 0.$$


$$\sigma_{21} \cos \theta + \sigma_{22} \sin \theta = 0$$

$$|\theta| \leq \pi.$$

∴ linear problem

$$1: \sigma_{ij} \underset{\sigma_{11}}{\sim} \sigma_{11} \text{ independent of } G, \nu.$$

$$\rightarrow \sigma_{11} \text{ proportional to } \sigma_{\infty}$$




Mon. Nov. 1st, Week 11

Theory of Tension


Semi-inverse Method

① Guess a form for the disp. field.



Check the BCs are satisfied.

* Cylinder with a uniform cross-section.



parameterize by

\mathbf{u} is the displacement field.

$$u_1 = -\alpha x_1 x_3 \quad u_2 = \alpha x_1 x_3 \quad u_3 = w(x_1, x_2)$$

α : a constant.

walking function.

To motivate this, look at a special case

Bar is circular.

$$w=0, \quad \mathbf{u} = \mathbf{u}_1 \mathbf{e}_1 + \mathbf{u}_2 \mathbf{e}_2 = u_r \mathbf{e}_r + u_\theta \mathbf{e}_\theta$$



$$\mathbf{e}_r = e_1 \cos \theta \mathbf{e}_1 + e_2 \sin \theta \mathbf{e}_2$$

$$\tau_{r\theta} = -e_1 \sin \theta + e_2 \cos \theta \tau_{\theta\theta}$$

$$u_r = \mathbf{u} \cdot \mathbf{e}_r \quad u_\theta = \mathbf{u} \cdot \mathbf{e}_\theta$$


$$u_r = -\alpha \sin \theta x_3 \quad u_\theta = \alpha \cos \theta x_3$$

$$u_r = 0, \quad u_\theta = \alpha r x_3$$



$$\text{on surface: } u_\theta = \alpha R x_3$$

$$(R=L)$$



$$u_\theta = \alpha r L = r \theta_0$$

$$M = \theta \theta_0, \quad \alpha = \frac{\theta \theta_0}{L} \quad \text{the unit of trace per unit length}$$

Strain tensor in cylindrical coordinate

the strain due to $\epsilon_{rr} = \epsilon_{\theta\theta} = \epsilon_{\theta\theta} = \epsilon_{zz} = 0$

$$\epsilon_{rr} = \frac{1}{2} \alpha r$$

$$? = R \theta_0 \quad ? = \frac{R \theta_0}{L} = Ra$$

$$\tau_{r\theta} = \frac{G}{2} \alpha r$$

only non-trivial stress component in polar coordinate

* traction free BCs automatically satisfied



on surface of cylinder

$$f \tau_{r\theta} \cap dA = M$$

(Recall the nullifying function of Σ)

$$\epsilon_{11} = 0, \epsilon_{22} = 0, \epsilon_{33} = 0, \epsilon_{44} = 0,$$

$$\epsilon_{13} = \frac{1}{2} \left[-\alpha x_2 + \frac{\partial w}{\partial x_1} \right]$$

$$\epsilon_{23} = \frac{1}{2} \left[\alpha x_1 + \frac{\partial w}{\partial x_2} \right]$$

$$\Rightarrow \left\{ T_{\alpha\beta} = 0, \alpha = 1, 2 \right.$$

$$T_{33} = \alpha$$

$$T_{13} = G \left[-\alpha x_2 + w_{,1} \right] \quad T_{23} = G \left[\alpha x_1 + w_{,2} \right]$$

Enforce equilibrium,

Equilibrium in 1, 2 directions are satisfied
and vertically. \rightarrow No Body Force.

in 3 direction.

w is harmonic.

Equilibrium is satisfied.

$$\frac{\partial T_{13}}{\partial x_1} + \frac{\partial T_{23}}{\partial x_2} = 0 \Rightarrow \text{Traction free BCs on the side of the Bar}$$

$$\frac{\partial^2 w}{\partial x_1^2} + \frac{\partial^2 w}{\partial x_2^2} = 0$$

in some sense, anti-plane shear.

$$\nabla^2 w = 0.$$

$T_{ij} n_j = 0$ (traction free).

$$\underline{t} = \frac{dx_1}{ds} \underline{e}_1 + \frac{dx_2}{ds} \underline{e}_2$$

$$\underline{n} = -\frac{dx_2}{ds} \underline{e}_1 - \frac{dx_1}{ds} \underline{e}_2$$

$$T_{ij} n_j = 0$$

$$\boxed{T_{31} n_1 + T_{32} n_2 = 0} \quad (\text{BCs})$$

$$\boxed{T_{31} \cdot \frac{dx_2}{ds} + T_{32} \frac{dx_1}{ds} = 0}$$

$$G \left[-\alpha x_2 + w_{,1} \right] \frac{dx_2}{ds} - G \left[\alpha x_1 + w_{,2} \right] \frac{dx_1}{ds} = 0.$$

(we can cancel the G).

$$w_{,1} \frac{dx_2}{ds} - w_{,2} \frac{dx_1}{ds} = \alpha \left(x_1 \frac{dx_1}{ds} + x_2 \frac{dx_2}{ds} \right)$$

$$\text{grad: } \underline{\nabla w} \cdot \underline{n} = \frac{\alpha}{2} \left[\frac{d(x_1^2 + x_2^2)}{ds} \right]$$

traction free BCs

$$\frac{dw}{dn} = \frac{\alpha}{2} \frac{d(x_1^2 + x_2^2)}{ds} \rightarrow \text{BCs for Laplace}$$

guarantees this * $\nabla^2 w = 0$. Nielsen BCs.

$$\int_C \frac{dw}{dn} ds \Rightarrow \left(\begin{array}{l} \text{existence of} \\ \text{solution} \end{array} \right) \text{ condition to be satisfied}$$

automatically satisfied. $\rightarrow \frac{dw}{dn}$

$$M = \alpha G \iint_A [x_1 x_2 + x_1 w_{,2} - x_2 w_{,1}] dx_1 dx_2$$

K : torsional stiffness

$$M = k\alpha$$

w is harmonic

$\frac{d}{dt}$

w is the real / Im part of an analytical function.

$$f(z) = w + i\phi \quad : \quad i = \sqrt{-1}.$$

$$z = x_1 + ix_2$$

w, ϕ are related by CR eqns.

$$\{ w_{,1} = \phi_{,2} \}$$

$$w_{,2} = -\phi_{,1}$$

$$\sigma_{13} = G[-\alpha x_2 + w_{,1}] = G[-\alpha x_2 + \phi_{,2}]$$

$$\sigma_{23} = G[\alpha x_1 + w_{,2}] = G[\alpha x_1 - \phi_{,1}]$$

Note: w, ϕ , is harmonic, so ϕ also

satisfy $\nabla^2 \phi = 0$.

Check: Equilibrium eqn is automatically satisfied

$$\sigma_{13} n_1 + \sigma_{23} n_2 = 0 \Rightarrow BCs$$

$$\sigma_{13} \frac{dx_2}{ds} = \sigma_{23} \frac{dx_1}{ds} = 0.$$

Wed, Nov. 3rd, Week 12

REVIEW: Displacement. $\rightarrow \nabla^2 w = 0$

TRACTION FREE BCs: $\frac{dw}{dn} = x_2 n_1 - x_1 n_2$

$$= x_2 \frac{dx_2}{ds} + x_1 \frac{dx_1}{ds} = \frac{1}{2} \frac{d(x_1^2 + x_2^2)}{ds}$$

$$\tau = \frac{dx_1}{ds} e_1 + \frac{dx_2}{ds} e_2$$

$$\eta = \frac{dx_2}{ds} e_1 - \frac{dx_1}{ds} e_2$$

$$\left\{ \begin{array}{l} \sigma_{13} = \frac{G}{2} \alpha [-x_2 + w_{,1}] \\ \sigma_{23} = \frac{G}{2} \alpha [x_1 + w_{,2}] \end{array} \right.$$

$$\left\{ \begin{array}{l} u_1 = -\alpha x_2 x_3 \\ u_2 = \alpha x_1 x_3 \\ u_3 = \alpha w(x_1, x_2) \end{array} \right.$$

A different approach.

$f(z) = w + i\phi$ \leftarrow conjugate harmonic function to w .

$$w_{,1} = \phi_{,2} \quad \& \quad w_{,2} = -\phi_{,1} \quad CR$$

$$\nabla^2 \phi = 0$$

$$\sigma_{13} = \frac{G}{2} \alpha [-x_2 + \phi_{,2}], \quad \sigma_{23} = \frac{G}{2} \alpha [x_1 - \phi_{,1}]$$

$$\text{T.F. BCs} \quad \sigma_{13} n_1 + \sigma_{23} n_2 = 0 \Rightarrow [-x_2 + \phi_{,2}] n_1 + [x_1 - \phi_{,1}] n_2 = 0$$

$$\underbrace{-x_2 \frac{dx_2}{ds} + x_1 (-\frac{dx_1}{ds})}_{\frac{d(x_1^2 - x_2^2)}{ds}} = \phi_{,1} n_2 + \phi_{,2} n_1 = 0.$$


$$\underbrace{\phi_{,1} t_1 + \phi_{,2} t_2}_{\nabla \phi \cdot \underline{t}} = \frac{\partial \phi}{\partial s}$$

$$\Rightarrow \frac{d\phi}{ds} = \frac{d(x_i^L + x_r^L)}{ds} \Rightarrow \phi = \frac{x_i^L + x_r^L}{2} + \text{const} \Rightarrow \text{Curve } C$$

Set const = 0.

$$\underline{\text{BC}}: \left[\begin{array}{l} \phi = \frac{x_i^L + x_r^L}{2} \quad \text{on } C \\ \nabla^2 \phi = 0 \end{array} \right]$$

Example



$$f(z) = w + i\phi.$$

$$f(z) = i(C^r)z^r \rightarrow z^r = x + iy$$

const. $\rightarrow z^r = x - iy + 2ixy$.

$3c^r + ik^r \rightarrow$ some other const.

C & k are real numbers.

hopefully satisfy the boundary conditions.

$$\begin{aligned} w &= ic^r(x^r - y^r) + ik^r - 2c^rxy \\ &\quad \underbrace{\text{imaginary part.}}_{\text{real part}} \quad \rightarrow \frac{1}{a^2} \quad \rightarrow \frac{1}{b^2}. \\ \underline{\text{BC on } C}: c^r(x^r - y^r) - k^r &= \frac{x^r + y^r}{2} \\ k^r &= x^r \left[\frac{1}{2} - c^r \right] + y^r \left[\frac{1}{2} + c^r \right] \end{aligned}$$

$$C^r = \frac{1}{2} \frac{a^r - b^r}{a^r + b^r} \quad k^r = \frac{ab^r}{a^r + b^r}$$

$$\text{that means } \rightarrow \phi \quad \underline{\sigma}_3 = \frac{G\alpha}{4} [-x_r + \phi_2]$$

$$\underline{\sigma}_3 = \frac{G\alpha}{4} [x_i - \phi_1]$$

$$\left\{ \begin{array}{l} \underline{\sigma}_3 = \frac{-2G\alpha a^ry}{a^r + b^r} \\ \underline{\sigma}_3 = \frac{2G\alpha b^rx}{a^r + b^r} \end{array} \right.$$


$w = -2C^r xy$ Also know warping function.

Note $c=0$, $a=b$, ... circle



$$M = \iint_y (\underline{\sigma}_{3x} x - \underline{\sigma}_{2y} y) dA =$$

$$= \frac{GT\alpha b^3 a^3}{a^r + b^r} = k\alpha. \quad A = \pi ab$$



how to calculate warping function / stresses in torsion.

Poisson's stress function approach:

$$\nabla^2 \phi = 0$$

$$\phi = \frac{1}{2} (x^r + y^r)^2, \text{ on } C$$

Define a function: $\Phi = \phi - \frac{1}{2} (x^r + y^r)$
on the BC, $\Phi = 0$. on C

$\nabla^2 \Phi = -2$ Poisson's equation

$$\phi = \Phi + \frac{1}{2} (x^r + y^r) \quad \rightarrow \quad \left\{ \begin{array}{l} \underline{\sigma}_3 = \frac{G\alpha}{4} \Phi_{1r} \\ \underline{\sigma}_3 = \frac{G\alpha}{4} \Phi_{2r} \end{array} \right.$$

Calculate the moment:

$$M = \alpha 2G \int \Phi dA$$

constant Φ curve

$$\Phi = C$$

the gradient of Φ , normal \rightarrow surface.

$$\underline{\sigma} = G \underline{\epsilon} \quad \nabla \Phi = \Phi_{,1} \underline{e}_1 + \Phi_{,2} \underline{e}_2$$


$$[\Phi_{,2} \underline{e}_1 - \Phi_{,1} \underline{e}_2] \Rightarrow \underline{\sigma} \cdot \nabla \Phi = 0$$

The constant lines are the direction of shear vector.

► lines of shear stresses

$$\nabla \cdot \underline{\sigma} = \Phi_{,1}^2 + \Phi_{,2}^2 \propto (1 - \Phi |_{G_0})$$

Prandtl soap film analogy



$$\nabla^2 D = -\frac{P}{T} \leftarrow \text{pressure}$$

$\frac{\text{Force}}{\text{length}}$

define new const.

$$\frac{1}{2}d = \frac{DT}{P}$$

$$D = \frac{dP}{2T}$$

$$\nabla^2 d = -2 \Rightarrow d=0 \text{ on } C$$

$$\nabla^2 \Phi \approx -2 \leftarrow \text{Similar II.}$$

Small membrane deflection formula

$$\text{also } D=0 \text{ on } C$$

Solid Mechanics



Nov. 8, Mon, Week 12.

Linear Viscoelasticity ideal model:

Cartoon Models

• Uniaxial tension test.

$$\uparrow \sigma(t)$$



real material:

Deformation \Rightarrow (history).

MAXWELL model

Spring & dashpot
in series

Viscosity: η

$$\sim \frac{D_s}{E_s}$$

$$E_s$$

$$D_s = E_s \epsilon_s$$

$$\sim \frac{D_{vis}}{E_{vis}}$$

$$E_{vis} \sim \eta$$

$$\dot{\epsilon}_{vis} = \frac{D_{vis}}{\eta}$$

$$\dot{\epsilon}_{vis} = \frac{D_{vis}}{\eta}$$

long run: simple fluid.
(suddenly apply a stress)

$$\epsilon = \frac{D}{E}$$

$$\dot{\epsilon}_{vis} = \frac{D}{\eta}$$


Same since they are
in series.

$$\boxed{\dot{\epsilon} = \frac{D}{E} + \frac{D}{\eta}}$$

$$\dot{\epsilon}_s + \dot{\epsilon}_{vis}$$




\Rightarrow ODE in time

Voigt model




$$\sigma = \sigma_s + \sigma_{vis}$$

$$\sigma_k = E \epsilon + \eta \dot{\epsilon} \Rightarrow \text{Voigt model}$$



$$t > 0, \Rightarrow \eta \dot{\epsilon} + E \epsilon = 0$$



Short time: fluid; \$ long time solid

Standard model


$$\sigma(t)$$

1

$$\epsilon(t)$$

$\frac{1}{E_1}$

t



Voigt element

Slid like behavior

$$\frac{E_1 + E_2}{E_1 E_2} = \frac{1}{E_1} + \frac{1}{E_2}$$

Slid behavior for both long & short time

$$\sigma + \frac{E_1 + E_2}{2} \sigma = \frac{1}{E_1} \dot{\epsilon} + \frac{1}{E_2} \dot{\epsilon} \quad \text{Linear ODE}$$

3 parameters to determine

Concept of Creep function

Creep function $C(t)$ strain history due to

$$\text{a unit stress } \sigma = H(t) = \begin{cases} 1, & t > 0 \\ 0, & t < 0 \end{cases}$$

$$C(t) = \left(\frac{1}{E} + \frac{t}{2} \right) H(t) \Rightarrow \text{Maxwell}$$

$$C(t) = \frac{1}{E} \left(1 - e^{-\frac{t}{\tau}} \right) H(t) \Rightarrow \text{Voigt}$$

$$C(t) = \frac{E_1 + E_2}{E_1 E_2} - \frac{1}{E_2} e^{-\frac{E_2 t}{\eta}}$$

$\frac{E_2}{\eta}$ units: $\frac{1}{t_c}$



$t_c \rightarrow$ Creep relaxation time

$$C(t=0) = \frac{1}{E_1} \quad \text{short time modulus.}$$


$$C(t=\infty) = \frac{1}{E_r} + \frac{1}{E_1} = \frac{1}{E_\infty}$$

long time modulus.

$$\frac{E_\infty}{E_1} = 10^{-3}.$$



für standard Solid:



$$t_0 = \frac{E_1 + E_2}{E_1 - E_2}, \quad \bar{E}_0 = E_1.$$

$$\left(\rightarrow \frac{n}{E_1 + E_2} \quad (\text{typo}) \right)$$

Boltzmann superposition principle

(1) Assume system is linear.

(2) Assume Causality.


(3) Non-Aging.

Creep
f

Given $C(t)$

Response of system

due to a unit stress
step function



$$\sigma(t) = \sigma(0^+) H(t) + \sigma(\Delta t)$$

$$H(t-\Delta t) \quad | \quad \downarrow \quad \sigma'(\Delta t) \Delta t H(t+\Delta t) \quad | \quad \downarrow \quad C(t).$$

$$\sigma(t) = \sigma(0^+) C(t) + \sigma'(\Delta t) \Delta t$$

$$C(t-\Delta t) + \sigma'(\Delta t) \Delta t C(t-2\Delta t) \quad | \quad \downarrow \quad H(t-2\Delta t) + \dots$$

$$\sigma(t) = \sigma(0^+) C(t) + \int_{0^+}^t \sigma'(\tau) C(t-\tau) d\tau.$$

Nov. 10, Wed, Week 12.





Review: Boltzmann superposition

Any stress history can be broken down into sum of step functions.

↓ Each step fun. $f(t-\tau)$
 $C(t-\tau)$.

Real linear viscoelastic $\Rightarrow \epsilon(t) = \sigma(0^+) C(t) + \int_{0^+}^t C(t-\tau) \frac{d\sigma}{dt} d\tau$
 model for uniaxial tension

Do a simple example



[Convolution product $f(t), g(t)$ define for $t \in [0, \infty)$]

$$f * g = \int_0^t f(t-\tau) g(\tau) d\tau = \int_0^t g(t-\tau) f(\tau) d\tau$$

① $\boxed{\epsilon = \sigma(0^+) C(t) + C * \sigma'}$ $\sigma' = \frac{d\sigma}{dt}$
 The Laplace transform of a function f defined in zero to infinity.

$$\mathcal{L}[f] = \int_0^\infty e^{-st} f(t) dt$$

$\mathcal{L}[f]$ is a function of s .
 s is the transform variable.

s is in general a complex variable

Properties

$$\mathcal{L}[f(t)] = sf(s) - f(0^+)$$

$$\mathcal{L}[f * g] = \int_0^\infty f(s) \tilde{g}(s) \rightarrow \text{convolution Theorem}$$

Laplace transform ① :

$$\tilde{\epsilon}(s) = \sigma(0^+) \tilde{Y}(s) + \mathcal{L}[\dot{Y}] = \tilde{\sigma}(s) \tilde{Y}(s)$$

$$\tilde{\sigma}(s) = \mathcal{L}[\sigma(t)]$$

$$[s\tilde{\sigma}(s) - \sigma(0^+)]$$

$$\tilde{\epsilon}(s) = s\tilde{\sigma}(s)\tilde{Y}(s) \quad \text{②}$$

clear & linear.

transform domain

$$\text{Messy} \Rightarrow \epsilon(t) = \sigma(0^+) C(t) + \int_{0^+}^t C(t-\tau) \frac{d\sigma}{dt} d\tau$$

Do the same thing with Relaxation fraction $\tilde{Y}(s)$.

Apply a strain history $\epsilon(t)$ given.

$$\sigma(t) = \epsilon(0^+) \tilde{Y}(t) + \int_{0^+}^t \tilde{Y}(t-\tau) \frac{d\epsilon}{d\tau} d\tau$$

$$\tilde{\sigma}(s) = s\tilde{Y}(s)\tilde{\epsilon}(s) \quad \text{③}$$

on the transform plane,
it's trivial.

Combine ② & ③

$$\tilde{\sigma}(s) = s\tilde{Y}(s) \cdot s\tilde{\epsilon}(s)\tilde{C}(s)\tilde{\sigma}(s)$$

$$\Rightarrow s\tilde{Y}(s) \cdot \tilde{C}(s) = 1 \quad \text{related}$$

$$\tilde{Y}(s) = \frac{1}{s^2 \tilde{C}(s)}$$

$$Y(t) = \mathcal{L}^{-1}\left[\frac{1}{s^2 \tilde{C}(s)}\right]$$

$$\tilde{Y}(s) \cdot \tilde{C}(s) = \frac{1}{s^2}$$

$$\mathcal{L}^{-1}\left[\frac{1}{s^2}\right] = t$$

$$\int_0^t Y(t-\tau) C(\tau) d\tau = t \quad t \geq 0$$

(Bromwich Integral)

$$\frac{1}{2\pi i} \int_{\gamma-i\infty}^{\gamma+i\infty} \tilde{Y}(s) e^{st} ds = Y(t), \quad t > 0$$

$$s = s_1 + i s_2$$

$Y(s)$ is Analytic on $\operatorname{Re}s > 0$

Isotropic Linear Viscoelastic Solid.

$$\sigma_{ij} = 2G \epsilon_{ij} + \lambda \epsilon_{kk} \delta_{ij}$$

MEMORIZE THIS!!

$$\epsilon_{ij} = \frac{\sigma_{ij}}{2G} + \frac{\nu}{E} \sigma_{kk} \delta_{ij} \quad E = \frac{G}{2(1+\nu)}$$

deviatoric stress tensor

$$S_{ij} = \sigma_{ij} - \frac{1}{3} \delta_{kk} \sigma_{ij}$$

$$\epsilon_{ij} = e_{ij} - \frac{1}{3} \epsilon_{kk} \delta_{ij}$$

Strain deviator tensor

in literature, $\frac{1}{3} \delta_{kk} = G$; $\epsilon_{kk} = \epsilon$

$$e_{ij}$$

Shear Modulus.

(relaxation modulus)

$$S_{ij} = 2G e_{ij}$$

$$G_{kk} = 3K \epsilon_{kk}$$

(relaxation)

Bulk Modulus.

change of volume

linear

elasticity

constitutive model.


$\sigma_{ij,j} = 0$ - no body force

$e_{ij} = \frac{u_{i,j} + u_{j,i}}{2}$ - kinematics

$$S_{ij} = e_{ij}(0^+) Y_1(t) + Y_1^* e_{ij}$$

$$G_{kk} = e_{ij} \epsilon_{kk}(0^+) Y_2(t) + Y_2^* \epsilon_{kk}$$

General Problem



$$u(x, t) = f(x, t)$$

$$\sigma_{ij,j} = T_{ij}(x, t)$$

involve time
3K

linear

elasticity

$$e_{ij} = \frac{u_{i,j} + u_{j,i}}{2}$$

correspondence principle

$$S_{ij} = S Y_1(s) \tilde{e}_{ij}(s)$$

$$G_{kk} = S Y_2(s) \tilde{\epsilon}_{kk}(s)$$

$$U_{ij,j} = T_{ij}(x, s)$$

Consider

$$\tilde{S}_{ij} = S \tilde{Y}_1(s) \tilde{e}_{ij}$$

$$\tilde{G}_{kk} = S \tilde{Y}_2(s) \tilde{\epsilon}_{kk}$$

$$\epsilon_{ij} = \frac{\sigma_{ij}}{2G} - \frac{1}{E} G_{kk} \delta_{ij}$$

$$S_{ij} = e_{ij}(0^+) Y_1(t) + \int_{0^+}^t Y_1(t-\tau) \frac{\partial e_{ij}}{\partial \tau} d\tau$$

$$Y_1(t) \leftrightarrow 2G, \quad G_{kk} = \epsilon_{kk}(0^+) Y_2(t) + \int_{0^+}^t Y_2(t-\tau) \frac{\partial \epsilon_{kk}}{\partial \tau} d\tau$$

$$Y_2 \leftrightarrow 3K$$


$$\tilde{G}_{kk} = S \tilde{Y}_2(s) \tilde{\epsilon}_{kk}(s)$$

$$\tilde{B}(\tilde{u}(x, s)) = f(x, s)$$

$$\tilde{U}_{ij,j} = T_{ij}(x, s)$$

$$2G$$

SIMPLE Example




$$\text{BCs} \quad \begin{cases} \sigma_{rr}(r=a, t>0) = P_0 \\ \sigma_{rr}(r=b, t>0) = 0 \end{cases}$$

$\mathcal{S}\mathcal{Y}(s) \mathcal{C}_1(s) s = f$

$$\tilde{\epsilon}_{ij}(s) = s C_1(s) \tilde{s}_{ij}$$

$$e_{ij} = C_1(t) \tilde{s}_{ij}(0^+) + \int_{0^+}^t C_1(t-\tau) \frac{\partial \tilde{s}_{ij}}{\partial \tau} d\tau$$



$$u_3(x_1, x_2, x_3=0) = -\Delta$$

$$(x_1^2 + x_2^2) < 1$$

$$\sigma_{ij} = \frac{G\Delta}{a} + f\left(\frac{r}{a}, \theta\right)$$

Office Hour

$$y \rightarrow \phi$$

$$\nabla^2 \phi = 0 \quad \phi = \frac{x^2 + y^2}{2}$$

formulate

$f \rightarrow \text{BCs}$ to simple

$$f|_{\text{BCs}} = 0$$


$f \rightarrow$ harmonic

separation of variables


Differential Eqs.

$$\frac{\partial^2 \phi}{\partial x^2} + \frac{\partial^2 \phi}{\partial y^2} = 0 \Rightarrow \frac{\partial^2 \phi}{\partial x^2} = -\frac{\partial^2 \phi}{\partial y^2}$$

$$f = \frac{\partial^2 \phi}{\partial x^2} + 1$$



Example:




PRANDTL: Stress function

Three common formulations for S-Wirey torsion:
 w , ϕ , Φ_p .

Solution for Laplacian

Harmonic Analysis:



November 15, 201. Week 13. Mon.


REVIEW = Correspondence principle.

$$Y(t) = Y_\infty + (Y_0 - Y_\infty) \sum_{j=1}^n a_j e^{-t/t_j}$$

$Y_\infty = Y(t = \infty)$ long time Modulus.


$Y_0 = Y(t = 0)$. Instantaneous Modulus.

$$\sum_{j=1}^n a_j = 1$$





Power law model.

$$Y(t) = Y_\infty + (Y_0 - Y_\infty) \frac{Y_0}{1 + (t/t_0)^\alpha}$$



Corresponds to




Pneology.

Shear strain: $\epsilon = \epsilon_0 e^{i\omega t}$.

* What is the response?

(long time / Steady state res)



$$\text{Shear Stress } \sigma(t) = \varepsilon(0^+) Y_1(t) + \int_0^t (Y_1(\tau) - \tau) \frac{d\varepsilon}{d\tau} d\tau$$

$$= \varepsilon_0 Y_1(t) + i\omega \int_0^t Y_1(t-\tau) e^{i\omega\tau} d\tau$$

$$\varepsilon_0 Y_1(t) + i\omega \varepsilon_0 \int_{0^+}^t [Y_1(t-\tau) - Y_1(\tau)] e^{i\omega\tau} d\tau$$

$$+ i\omega \varepsilon_0 Y_1(t) \int_{0^+}^t e^{i\omega\tau} d\tau$$

$$i\omega \varepsilon_0 Y_1(t) \cdot \frac{e^{i\omega t}}{i\omega} \Big|_{0^+}^t$$

$$= \varepsilon_0 Y_1(0) e^{i\omega t} - \varepsilon_0 Y_1(0)$$

$$= \varepsilon_0 Y_1(t) e^{i\omega t} + i\omega \varepsilon_0 \int_0^t [Y_1(t-\tau) - Y_1(\tau)] e^{i\omega\tau} d\tau$$

$$\int_0^t Y_1(t-\tau) e^{i\omega\tau} d\tau. \quad \eta = t-\tau.$$

$$\tau = t-\eta$$

$$= \int_t^\infty Y_1(\eta) e^{i\omega(t-\eta)} (-d\eta)$$

$$= \int_0^t Y_1(\eta) e^{i\omega(t-\eta)} d\eta = e^{i\omega t} \int_0^t Y_1(\eta) e^{i\omega\eta} d\eta$$

$$\int_0^t Y_1(\tau) e^{i\omega\tau} d\tau$$

$$= Y_1(t) \cdot e^{i\omega t} \int_0^t e^{i\omega\eta} d\eta$$

$$T(t) = \varepsilon_0 Y_1(t) \cdot e^{i\omega t} + i\omega \int_0^t [Y_1(\eta) - Y_1(t)] e^{i\omega\eta} d\eta$$

$$= e^{i\omega t} \left[\varepsilon_0 Y_1(t) + i\omega \int_0^t [Y_1(\eta) - Y_1(t)] e^{-i\omega\eta} d\eta \right]$$

$\xrightarrow{t \rightarrow \infty}$

Converge to $\varepsilon_0 Y_1(\infty) + i\omega \int_0^\infty [Y_1(\eta) - Y_1(\infty)] e^{-i\omega\eta} d\eta$.


$\hat{Y}_1(\omega)$

Complex Modulus

$$\sigma(t \rightarrow \infty) = \varepsilon_0 e^{i\omega t} \hat{Y}_1(\omega)$$

$$\hat{Y}_1 = \hat{Y}_1(\omega) + i \hat{E}_1(\omega)$$

Storage modulus loss modulus



$$\hat{Y}'(\omega) = Y_1(\omega) + \omega \int_0^\infty [Y_1(\eta) - Y_1(\omega)] \sin(\omega\eta) d\eta.$$

$$\hat{Y}''(\omega) = \omega \int_0^\infty [Y_1(\eta) - Y_1(\omega)] \cos(\omega\eta) d\eta.$$

$$\hat{Y}'(\omega) = \hat{Y}_1(-\omega) \rightarrow \text{even fct. of } \omega$$

$$\hat{Y}''(\omega) = \text{odd fct. of } \omega$$

Change of energy in a cycle.

$$W = \int_{\text{cycle}} \sigma d\epsilon$$

$$\text{We apply } \epsilon = \epsilon_0 \left[\frac{e^{i\omega t} + e^{-i\omega t}}{2} \right]$$

$$= \epsilon_0 \cos(\omega t).$$

$$\epsilon_0 \frac{e^{i\omega t}}{2} \rightarrow \epsilon_0 \hat{Y}_1(\omega) e^{i\omega t} = \sigma(t)$$

$$\epsilon_0 \frac{e^{-i\omega t}}{2} \rightarrow \frac{\epsilon_0 \hat{Y}_1(-\omega)}{2} e^{-i\omega t} = \sigma(t).$$

$$\hat{Y}_1(-\omega) = \hat{Y}_1(\omega)$$

$$\begin{aligned} \sigma &= \frac{\epsilon_0}{2} [\hat{Y}_1(\omega) e^{i\omega t} + \hat{Y}_1(\omega) e^{-i\omega t}] \\ &= \epsilon_0 [\hat{Y}'(\omega) \cos(\omega t) - \hat{Y}''(\omega) \sin(\omega t)]. \end{aligned}$$

$$\hat{Q}^{\text{rot}} Y_1(\omega) = [\hat{Y}'(\omega) + i\hat{Y}''(\omega)] [\omega s \omega t + i s \omega t].$$

$$\text{Re}(\quad) = \hat{Y}'(\omega) \omega s \omega t - \hat{Y}''(\omega) \cdot s \omega t$$

$$d\epsilon = \omega \epsilon_0 \sin(\omega t) dt$$

$$-\omega \epsilon_0^2 \int ([\hat{Y}'(\omega) \cos(\omega t) - \hat{Y}''(\omega) \sin(\omega t)] \sin(\omega t) dt)$$

(cycle)
Work = \bar{W} in a cycle.
we already show: $\epsilon_0 e^{i\omega t} \rightarrow \epsilon_0 \hat{Y}_1(\omega) e^{i\omega t}$

1st integral


$$-\omega \epsilon_0^2 \hat{Y}''(\omega) \int \sin^2(\omega t) dt \text{ (cycle)}$$

$$\hat{Y}_1(\omega) \cos(\omega t) \sin(\omega t) \text{ (cycle)}$$


some number

$$\frac{d \sin^2 \omega t}{2 \omega}$$

if you plot the lost modulus @ this freq.



Nov. 17, 2021. Wed., Week 13.



Long time stress.

$$\sigma = \sigma_0 \hat{Y}_1(\omega) e^{i\omega t}$$

$$\hat{Y}_1(\omega) = \hat{Y}'_1(\omega) + i \hat{Y}''_1(\omega)$$

complex modulus

$\sqrt{\frac{1}{1}}$ loss modulus \rightarrow odd function.


Storage modulus

$$\text{Energy loss per cycle} = \pi \sigma_0^2 |\hat{Y}''_1(\omega)|$$

\rightarrow even function.

loss tangent.

$$\hat{Y}_1 = |\hat{Y}_1| e^{i\delta}$$



$$\tan \delta = \frac{\hat{Y}''_1}{\hat{Y}'_1}$$

loss tangent.

$$\hat{Y}_1(\omega) = \hat{Y}_1(\infty) + i\omega \int_0^\infty [\hat{Y}_1(\eta) - \hat{Y}_1(\infty)] e^{-i\omega\eta} d\eta$$

complex modulus.

relaxation function


in time domain



long time shear strain.

$$\varepsilon = \varepsilon_0 \hat{C}_1(\omega) e^{i\omega t}$$

$$\hat{C}_1(\omega) = C_1(\infty) + \int_0^\infty [C_1(\eta) - C_1(\infty)] e^{-i\omega\eta} d\eta$$



$$\sigma = \sigma_0 e^{i\omega t}$$

$$\sigma_0 = \varepsilon_0 \hat{Y}_1(\omega)$$

$$\hat{G}_1(\omega) e^{i\omega t} = 1$$

$$\hat{Y}_1(\omega) = \frac{L}{\varepsilon(\omega)}$$


$$\int_0^t C_1(t-\tau) Y_1(\tau) d\tau = t$$

$$S^2 \hat{C}_1 \hat{Y}_1 = 1$$

\hookrightarrow Laplace transform

$$\int_0^\infty e^{-st} C_1(t) dt = \tilde{C}_1(s)$$

Standard model




$$Y_1(t) = Y_\infty + (Y_0 - Y_\infty) e^{-t/t_p}$$

$Y_\infty \equiv Y_1(t \rightarrow \infty) \rightarrow$ long time shear modulus

$Y_0 \equiv Y_1(t \rightarrow 0) \rightarrow$ short time

$$\begin{aligned} Y_1(\omega) &= Y_\infty + \frac{i\omega(Y_0 - Y_\infty)}{\tau_R^2 + \omega^2} \\ Y_1'(\omega) &= Y_\infty + \frac{\omega^2 \tau_R^2 (Y_0 - Y_\infty)}{1 + \omega^2 \tau_R^2} \\ Y_1''(\omega) &= \frac{\omega \tau_R (Y_0 - Y_\infty)}{1 + \omega^2 \tau_R^2} \end{aligned}$$



Time Temp. Superposition

$$\omega = 10^{-2} \text{ Radians/s} + 0 \text{ } 10^2 \text{ rad/s.}$$


$$Y_1'(\omega, T) = b(T, T_0) \phi(a(T, T_0) \omega)$$

↑ Ref. Temp.


$$Y_1'(\omega, T) = b(T, T_0) \phi(a(T, T_0) \omega)$$

Shift Factors.

$$\frac{Y_1'}{b(T, T_0)} = \phi(a(T, T_0) \omega)$$



$$\log \frac{Y_1'}{b(T, T_0)} = \log \frac{1}{b(T, T_0)} - \log a(T, T_0) \omega$$



$$\log [a(T, T_0) \omega]$$

$$= \log a(T, T_0) + \log (\omega)$$

WLF - shift factor.

$$a(T, T_0) = \frac{C_1(T) T_0}{C_1(T_0) (T - T_0)}$$

Normally, $T_0 \rightarrow$ glass transition temp. of polymer

complex modulus.


time domain (relaxation fct.)

Gruen

Y_1' & Y_1'' are not independent to each other

If u know one, you know the other

$$\frac{1}{\pi} PV \int_{-\infty}^{\infty} \frac{Y_1'(r) - Y_1'(\infty)}{r \omega} dr$$



$$2G\varepsilon = \tau$$

$$\tau = G\gamma$$

$$e_j^i = S Y_i^*$$

$$S_{ij}^k = S Y_i^* e_j^i$$

$$T_{kk} = S \sum_i Y_{ik}$$

$$E = 2G(1 + v)$$

linear Elasticity.

G, v .

linear Viscoelasticity.

G, v, E, k .

\uparrow
bulk (relaxation).

OF: Superposition principle.

want to stress in tension test.

$$\sigma(t) = \epsilon(0^+) Y(t) + \int_{0^+}^t Y(t-\tau) \frac{d\epsilon}{d\tau} d\tau$$

$$= \epsilon(0^+) Y(t) + Y \star \frac{d\epsilon}{dt}$$

strain history



stress history




asked to evaluate the stress history.


load fast \rightarrow strain rate \rightarrow high \rightarrow

End: should not have stress in
Spring 1 & Spring 2.

After 2b, you should be able to see



Q:



You have:

creep function $C(t) \cdot Y(t)$

find one equation of how

only one disp. field (η)

Strain $\mapsto 3$ $\epsilon_{xx}, \epsilon_{yy}, \epsilon_{zz}$
 η_x, η_y, η_z

$$u_r \rightarrow \varepsilon_{rr}, \varepsilon_{\theta\theta} = \varepsilon_{\phi\phi}$$


∇ const. model

$$\sigma_{rr}, \sigma_{\theta\theta}, \sigma_{\phi\phi}, \phi,$$

Equilibrium Eq.

Incompressible

$$\varepsilon_{rr} + \varepsilon_{\theta\theta} + \varepsilon_{\phi\phi} = 0$$




pressure = const.

$$\tau = \sigma_0, \sigma_{rr} = -P$$

integrate incompressibility

$$\sigma_{ij} = 2G\varepsilon_{ij} + P\delta_{ij} \quad \begin{matrix} \text{hydrostatic} \\ \downarrow \\ \text{incompressibility} \end{matrix}$$

$$\varepsilon_{kk} = 0$$



$$\sigma_r = P_0 \sin \omega t$$



$$\sigma = \frac{(\cos \omega t) e^t}{(1+t^3)}$$


only difference:

strain

$$\varepsilon = \sigma_0 \cos \omega t$$

$$\varepsilon = \frac{\sigma_0 \cos \omega t}{E}$$

∇ elastic



$$\varepsilon = \sigma(0^+) \frac{C}{E}(t)$$

$$+ \int_0^t C(t-\tau) \frac{\partial \sigma}{\partial \tau} d\tau$$

$$\epsilon = \sigma_1 / E_1$$



$$\sigma = \sigma_1 + \sigma_2$$

$$\sigma_2 = \sigma - \sigma_1$$

$$\ddot{y} = \frac{\sigma_2}{E_2} + \frac{\sigma_1}{\eta}$$

$$\int_0^\infty \frac{e^{-i\omega y}}{1 + n/\omega y} dy$$

$$G_0 - G_\infty$$

$$n$$


$$\tau_R = u$$

Exponential

$$\text{Integral} = \int_0^\infty \frac{e^{-i\omega y}}{1+u} du$$

$$dy = u \tau_R$$

$$\omega = \omega \tau_R$$




basic idea \rightarrow integrate this term.

Compute integral by picking ~~value~~


$$\int_0^\infty \frac{\omega \tau_R u du}{(1+u)} = i \int_0^\infty \frac{\sin \omega u du}{(1+u)}$$

infinite value

Riemann-Hamilton theory



$$\int_0^\infty \frac{\cos \omega x dx}{1+x}$$



Nov. 22, Mon., 2021. Wk 14.

Linear visco-isotropic material.

$$\tilde{\epsilon}_{ij} = \tilde{\epsilon}_{ij} - \frac{1}{3} \tilde{\epsilon}_{kk} \delta_{ij} = \frac{1}{2G} S_{ij} \text{ elasticity.}$$

$$\tilde{\epsilon}_{kk} = \frac{1}{K} \cdot \frac{\tilde{\sigma}_{kk}}{3}$$

bulk deformation

shear deformation

Visco. $\tilde{\epsilon}_{ij} = C_1(t) S_{ij}(t=0^+) + \int_{0^+}^t C_1(t-\tau) \frac{\partial S_{ij}}{\partial \tau} d\tau$

~~del~~

$$\tilde{\epsilon}_{kk} = C_2(t) \tilde{\sigma}_{kk}(t=0^+) + \int_{0^+}^t C_2(t-\tau) \frac{\partial \tilde{\sigma}_{kk}}{\partial \tau} d\tau$$

transform variable.

$C_2^* \tilde{\sigma}_{kk}$

$$\tilde{\epsilon}_{ij} = S \tilde{C}_1(s) \tilde{S}_{ij} = \frac{s^3 \tilde{C}_2(\tilde{C}_1/2)}{\tilde{C}_2 + (\tilde{C}_1/2)}$$


$$\tilde{\epsilon}_{kk} = S \tilde{C}_2(s) \tilde{\sigma}_{kk}$$

$$\frac{1}{2G} \longleftrightarrow S \tilde{C}_1(s)$$

$$\frac{1}{3K} \longleftrightarrow S \tilde{C}_2(s)$$

$$E = \frac{9KG}{3(K+G)}$$

$$= \frac{s^3 \tilde{C}_1 \tilde{C}_2}{2\tilde{C}_2 + \tilde{C}_1} = S E(s)$$




Plane strain problem

$$t_0 = \frac{F}{A} \rightarrow 0 \quad > \text{fundamental sol. for clas.}$$

line force F

(force per unit length).

in direction of blade:




assume infinitely long

$$F, G, T, \theta \quad (go away)$$

$$T = \frac{F}{L} \sin \theta$$

$$G = \frac{F}{L} f(F/G, \theta)$$

force per unit length.



solution has to be

plane strain

$$\sigma = \frac{F}{r} f(\theta) = 0$$

$$\epsilon_{11} = \frac{\sigma_{11}}{E} = \frac{1}{2E} (\sigma_{rr} + \sigma_{\theta\theta}) \quad \epsilon_{12}, \epsilon_{21}, \epsilon_{11}$$

$$\frac{\sigma_{rr}}{E} = \frac{1}{2E} (\sigma_{rr} + \sigma_{\theta\theta})$$

$$= \frac{\sigma_{rr}}{E} = \frac{1}{2} (\sigma_{rr} + \sigma_{\theta\theta}) \quad \tan(\epsilon) = \epsilon_{11} + \epsilon_{21} = 0$$

if

\Leftrightarrow (incompressibility)

$$\sigma_{11} = \left[1 - \frac{1}{4} \right] - \frac{1}{2E} \left[\frac{1}{2} (3 \sigma_{rr}) \right]$$



$$\frac{3}{4E} > \frac{1}{4G} = \frac{3 \sigma_{rr}}{4E} = \frac{3 \sigma_{rr}}{4E}$$

$$= \frac{1}{4G} [\sigma_{11} - \sigma_{rr}]$$

$$\sigma = \frac{F}{r} f(\theta)$$

$$\epsilon = \frac{F}{Gr} g(\theta)$$

displacement u



$$dF(x') = t_{22}(x') \quad dF(x') = t_{11}(x') dx'$$

$$\sigma_{ij}(x, y) = \frac{F}{\sqrt{x^2 + y^2}} f_{ij}\left(\frac{y}{x}\right)$$


$$t(x') dx'$$

$$d\sigma_{ij}(x, y, x') = \frac{F}{\sqrt{(x-x')^2 + y^2}} f_{ij}\left(\frac{y}{x-x'}\right)$$

$$\sigma_{ij}(x, y) = \int_{-\infty}^{\infty} t(x') f_{ij}\left(\frac{y}{x-x'}\right) dx'$$

\rightarrow general solution \rightarrow you need to find

Δ, F



traction free

$2a$

a_0 friction


$$\sigma_{12} = \sigma_{22}$$

$$(|x| > a, y=0) = 0$$

$$W(|x| < a, y=0) = 0$$



traction = 0



$$\frac{1}{2\pi G} \int_{-a}^a \frac{t(x') dx'}{x - x'} = 0$$

principal value
integrate

$$\nabla_x = -\frac{1}{2\pi G} \int_{-a}^a \frac{t(x') dx'}{x - x'} = 0$$

gradient of disp.

SOLUTION: $t(x) = \frac{-A}{\sqrt{a^2 - x^2}} = \frac{F}{\pi \sqrt{a^2 - x^2}}$

HW 11. Q3.

given.

First, substitute the BCs:

$$\sigma_{rr}(r=b) = -P$$

Compatibility eq.

$$\frac{\partial^2 \epsilon_{xx}}{\partial y^2} + \frac{\partial^2 \epsilon_{yy}}{\partial x^2} = \frac{\partial^2 \epsilon_{xy}}{\partial x \partial y} \quad (1)$$

Constitutive Eq.

$$\sigma_{ij} = 2G \epsilon_{ij} + P \delta_{ij} \quad (2)$$

Equilibrium Eq.

$$\sigma_{jj,j} = 0 \quad (3)$$

Substitute the BCs into Eqs. (1), (2), (3). We can hence compute the stress (radial).

► Taking BC's advice, we take \sim

from Eq. (2): $\epsilon_{ij} = (\sigma_{ij} - P \delta_{ij}) / 2G$.

From compatibility Eq. (1):

$$\sigma_{rr,rr} - P \delta_{rr,rr} + \sigma_{\theta\theta,\theta\theta} - P \delta_{\theta\theta,\theta\theta} = \sigma_{rr,rr} - P \delta_{rr,rr}$$

▷ Equilibrium:

$$\sigma_{rr,0} + \sigma_{\theta\theta,r} + \sigma_{r\theta,r} + \sigma_{\theta\theta,0} = 0 \dots (4)$$

▷ Modified compatibility

$$\sigma_{rr,00} + \sigma_{\theta\theta,rr} - \sigma_{rr,rr} = P \dots (5)$$

→ Now, substitute BCs \Rightarrow Nah

Equilibrium: $\int (\sigma_{rr} + \sigma_{\theta\theta}) d\theta = \int (\sigma_{\theta\theta} + \sigma_{rr}) d\theta$

laplace + trans.

$$\{\sigma_{ij,i} = 0$$

$$\tilde{\varepsilon}_{ij} = (\tilde{u}_{i,j} + \tilde{u}_{j,i})/2$$

$$\tilde{\varepsilon}_{kk} = S \tilde{C}_2 \tilde{\sigma}_{kk}, \tilde{\varepsilon}_{ij} = S \tilde{C}_1 \tilde{\sigma}_{ij}$$

$$\tilde{\sigma}_{rr}(r=b) = -\frac{P}{S}$$

$$\frac{d\sigma_{rr}}{dr} + \frac{2}{r}(\sigma_{rr} - \sigma) = 0$$

Same in laplace space:

$$\frac{d\tilde{\sigma}_{rr}}{dr} + \frac{2}{r}(\tilde{\sigma}_{rr} - \tilde{\sigma}) = 0$$

$$\frac{\partial^2 \tilde{\sigma}_{xx}}{\partial r^2} + \frac{\partial^2 \tilde{\sigma}_{yy}}{\partial r^2} = \frac{\partial^2 \tilde{\sigma}_{xy}}{\partial r \partial s}$$



$$\tilde{\sigma}_{ij} = 2G \tilde{\varepsilon}_{ij} + P \delta_{ij}$$

$$\frac{\partial^2 \tilde{\sigma}_{ii}}{\partial r^2} + \frac{\partial^2 \tilde{\sigma}_{jj}}{\partial r^2} = 2 \frac{\partial^2 \tilde{\sigma}_{ij}}{\partial r \partial s}$$

$$\tilde{\sigma}_{ii} = 2G \tilde{\varepsilon}_{ii} + P \delta_{ii}$$

$$\tilde{\sigma}_{jj} = 2G \tilde{\varepsilon}_{jj} + P \delta_{jj}$$

$$\tilde{\sigma}_{ij} = 2G \tilde{\varepsilon}_{ij} + P \delta_{ij}$$

$$\tilde{\varepsilon}_{ii} = \frac{\tilde{\sigma}_{ii} - P \delta_{ii}}{2G}$$

$$\tilde{\varepsilon}_{jj} = \frac{\tilde{\sigma}_{jj} - P \delta_{jj}}{2G}$$

$$\tilde{\varepsilon}_{ij} = \frac{\tilde{\sigma}_{ij} - P \delta_{ij}}{2G}$$

spherical:

$$\frac{\partial^2 \tilde{\sigma}_{xx}}{\partial r^2} + \frac{\partial^2 \tilde{\sigma}_{yy}}{\partial r^2} = \frac{\partial^2 \tilde{\sigma}_{xy}}{\partial r \partial s}$$


$$\frac{\partial^2 \tilde{\sigma}_{ii}}{\partial r^2} + \frac{\partial^2 \tilde{\sigma}_{jj}}{\partial r^2} = \frac{\partial^2 \tilde{\sigma}_{ij}}{\partial r \partial s}$$

in Laplace domain: $\frac{\partial^2 \tilde{\sigma}_{ii}}{\partial r^2} + \frac{\partial^2 \tilde{\sigma}_{jj}}{\partial r^2} = \frac{\partial^2 \tilde{\sigma}_{ij}}{\partial r \partial s}$

Nov. 29, Mon. Wk 15

* Exam: Dec. 11. 9am - 9pm.

HW Review



* Setup the traction free BCs

traction free $\Rightarrow \sigma_{\perp} = 0$

$\rightarrow 1 \quad \sigma_n = \sigma_{zz} = 0$


remember how the setup

the traction free BCs

$$n = \cos \theta e_1 + \sin \theta e_2$$

~~PSD~~ n should always normal to the surface

BECAUSE it identifies the surface



$$\sigma_z(r < a, z=0) = -\Delta \quad \text{traction free}$$

~~PSD~~ Defined in reference configuration.


$$\sigma_{yy} = \sigma_{zz} = 0$$

$$\sigma_{yy} = \sigma_{zz} = 0$$

$$\rho = \sqrt{r^2 + z^2}$$


$$\sigma_z(\rho \rightarrow \infty) \rightarrow 0$$

frictionless BCs: Cannot take any load



~~PSD~~ there are no shear

Next page





What is the displacement

What is the contact condition

$$BC \quad \sigma_{rz} = \sigma_{\theta z} = \tau_{rz} = 0, \quad r > a, \quad z = 0.$$

traction free

$$\text{Inside the contact region: } \sigma_{rz} = \sigma_{\theta z} = 0, \quad r < a, \quad z = 0$$



$$(R-\Delta)^2 + a^2 = R^2$$

$$R^2 - 2R\Delta + \Delta^2 + a^2 = R^2$$

$$a^2 \approx 2R\Delta$$

$$\Delta = \frac{a^2}{2R}$$

wrong

like a fluid.

$$\text{Actual Hertz soln. } \Delta = \frac{a^2}{R}$$

$$\Delta = \frac{P}{G \pi a} \quad \text{numerical const.}$$


measure the load F

$$\Delta = \left[\frac{9}{16R(4G)^2} \right] F^{2/3}$$

incompressible solid

$$4G \rightarrow E^* = \frac{E}{1-2\nu^2}$$

shear modulus




$$4\pi r^2 G_f \approx \frac{P}{r}$$

$$u_r \approx \frac{P}{G r} \hat{u}_r(\theta)$$

Standard Bushiness soln.

$$u_3 = \frac{P}{4\pi G} \cdot \frac{2(1-\nu)}{r} \int_{x+y^2}^b$$



Nov. 24, Wed., 2011. Wk 13.

Introduction to anisotropic Elasticity

Isotropic Elasticity: 2 materials const

anisotropic:

▷ worst: 21 materials const.

$$\text{linear elasticity: } \underline{\sigma} = K \underline{\epsilon} \quad (1)$$

fourth order tensor

(stiffness tensor)

$$K = k_{ijkl} \epsilon_i \epsilon_j \epsilon_k \epsilon_l$$

$$k_{jkl} = k_{jik} = k_{jik}$$

(due to the symmetry of
stress & strain tensors).

36 characteristics.

existence of strain energy density W .

$$\sigma_{ij} = \frac{\partial W}{\partial \epsilon_{ij}} \quad K \text{ has 21 independent consts.}$$

$$\sigma_{ij} \rightarrow \underline{\sigma} = \begin{pmatrix} \sigma_{11} \\ \sigma_{22} \\ \sigma_{33} \\ \sigma_{33} \\ \sigma_{13} \\ \sigma_{12} \end{pmatrix} = \begin{pmatrix} \sigma_1 \\ \sigma_2 \\ \sigma_3 \\ \sigma_3 \\ \sigma_5 \\ \sigma_6 \end{pmatrix}$$

$$\underline{\sigma} = \sigma_{ij} \epsilon_i \epsilon_j$$

$$\epsilon_{ij} \rightarrow \underline{\epsilon} = \begin{pmatrix} \epsilon_{11} = \epsilon_1 \\ \epsilon_{22} = \epsilon_2 \\ \epsilon_{33} = \epsilon_3 \\ \epsilon_{33} = \epsilon_4 \\ \epsilon_{13} = \epsilon_5 \\ \epsilon_{12} = \epsilon_6 \end{pmatrix}$$

$$\text{Eq. (1) } \Rightarrow \underline{\sigma} = K \underline{\epsilon}$$

$$K = \begin{pmatrix} k_{11} & k_{12} & k_{13} & k_{14} & k_{15} & k_{16} \\ k_{21} & k_{22} & k_{23} & k_{24} & k_{25} & k_{26} \\ k_{31} & k_{32} & k_{33} & k_{34} & k_{35} & k_{36} \\ k_{41} & k_{42} & k_{43} & k_{44} & k_{45} & k_{46} \\ k_{51} & k_{52} & k_{53} & k_{54} & k_{55} & k_{56} \\ k_{61} & k_{62} & k_{63} & k_{64} & k_{65} & k_{66} \end{pmatrix}$$

$$\sigma_{ii} = k_{111} \varepsilon_{11} + k_{112} \varepsilon_{12} + k_{113} \varepsilon_{13} + k_{114} \varepsilon_{14} \\ + k_{115} \varepsilon_{15} + k_{116} \varepsilon_{16} + k_{117} \varepsilon_{17} + k_{118} \varepsilon_{18} \\ + k_{119} \varepsilon_{19} + k_{1110} \varepsilon_{10}$$

$$\sigma_i = k_{11} \varepsilon_1 + k_{16} \varepsilon_6 + k_{15} \varepsilon_5 + k_{14} \varepsilon_4 + k_{12} \varepsilon_2 \\ + k_{13} \varepsilon_3 \Rightarrow \underline{\sigma} = K \underline{\varepsilon}$$

Plane of symmetry: (material).

Anisotropic


$$2 \text{ bases: } \{e_1, e_2, e_3\} = B_1$$

$$\{e'_1, e'_2, e'_3\} = B_2$$

$$e'_1 \rightarrow e_1$$

$$e'_2 = e_2$$

$$e'_3 = -e_3$$



(Reflection).

K is the same for both bases: (B_0, B'_0) .

transform into B' basis

$$K'_{ijkl} = K_{ijkl}$$

$$K'_{rstu} = K_{ijkl} (e_i \cdot e'_r) (e_j \cdot e'_s) (e_k \cdot e'_t) (e_l \cdot e'_u) \\ P_{ri} P_{sj} P_{tk} P_{lu}$$

general transformation formula

P matrix is simple

$$P = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & -1 \end{pmatrix}$$

$$K'_{111} = K_{111} = k_{ijkl} P_{1i} P_{1j} P_{1k} P_{1l} \\ (\text{Hypothesis}) \quad \checkmark \quad \checkmark \quad \checkmark \quad \checkmark \\ \delta_{1i} \quad \delta_{1j} \quad \delta_{1k} \quad \delta_{1l}$$

$$= K_{111}$$

$$K'_{222} = K_{222} = k_{ijkl} P_{2i} P_{2j} P_{2k} P_{2l} = K_{222} \\ \checkmark \quad \checkmark \quad \checkmark \quad \checkmark$$

$$K'_{112} = k_{ijkl} P_{1i} P_{1j} P_{2k} P_{2l} = K_{112} \\ \delta_{1i} \quad \delta_{1j} \quad \delta_{2k} \quad \delta_{2l}$$

In the same way you can show for all.

I already have material plane of symmetry

$$K'_{1123} = K_{ijkl} P_{1i} P_{2j} P_{3k} P_{4l} = -K_{1123}$$

~~$\delta_{11} \delta_{2j}$~~

$\delta_{1i} \delta_{ij} \quad \delta_{2k} (-\delta_{2j})$

we know in prior: $K'_{1123} = K_{1123}$

Hence: $K_{1123} = -K_{1123}$.

i. $K_{1123} = 0$.

$K_{14} = 0$

$K_{24} = K_{25} = K_{34} = K_{35} = K_{46} = K_{56} = 0$

reduce the num. of consts. to 8.

$$K = \begin{bmatrix} K_{11} & K_{12} & K_{13} & 0 & 0 & K_{16} \\ K_{21} & K_{22} & K_{23} & 0 & 0 & K_{26} \\ K_{31} & K_{32} & K_{33} & 0 & 0 & K_{36} \\ K_{41} & K_{42} & K_{43} & K_{44} & K_{45} & 0 \\ K_{51} & K_{52} & K_{53} & K_{54} & K_{55} & 0 \\ K_{61} & K_{62} & K_{63} & 0 & 0 & K_{66} \end{bmatrix}$$

13 Material constants.

$$\sigma_1 = K_{11} \epsilon_{11} + K_{12} \epsilon_{21} + K_{13} \epsilon_{31} + K_{16} \epsilon_{61} \quad (3)$$

$$\sigma_2 = K_{12} \epsilon_{12} + K_{22} \epsilon_{22} + K_{23} \epsilon_{32} + K_{26} \epsilon_{62}$$

$$\sigma_3 = K_{13} \epsilon_{13} + K_{23} \epsilon_{23} + K_{33} \epsilon_{33} + K_{36} \epsilon_{63}$$

$$\sigma_4 = K_{44} \epsilon_{44} + K_{45} \epsilon_{54}$$

$$\sigma_5 = K_{54} \epsilon_{45} + K_{55} \epsilon_{55}$$

$$\sigma_6 = K_{61} \epsilon_{16} + K_{62} \epsilon_{26} + K_{63} \epsilon_{36} + K_{66} \epsilon_{66}$$



define a new basis:

$$e'_1 = e_1$$

$$e'_2 = e_2$$

$$e'_3 = e_3$$

put an additional plane of symmetry.

$$\sigma_{ij} \rightarrow \sigma'_{ij}$$

$$\epsilon_{ij} \rightarrow \epsilon'_{ij}$$

$$\sigma'_4 = \sigma_4 = K_{44} \epsilon'_{44}$$

$$[\sigma'_{ij}] = \begin{bmatrix} \sigma_{11} & -\sigma_{12} & -\sigma_{13} \\ -\sigma_{12} & \sigma_{22} & \sigma_{23} \\ -\sigma_{13} & \sigma_{23} & \sigma_{33} \end{bmatrix} \quad \sigma_{46} = K_{46} \epsilon_{64} - K_{45} \epsilon_{54}$$

$$K_{46} = 0 \quad K_{36} = 0$$

$$K_{16} = 0 \quad K_{26} = 0$$

$$K = \begin{bmatrix} k_{11} & k_{12} & k_{13} & 0 & 0 & 0 \\ k_{21} & k_{22} & k_{23} & 0 & 0 & 0 \\ k_{31} & k_{32} & k_{33} & 0 & 0 & 0 \\ k_{41} & k_{42} & k_{43} & 0 & 0 & 0 \\ k_{51} & k_{52} & k_{53} & 0 & 0 & 0 \\ k_{61} & k_{62} & k_{63} & 0 & 0 & 0 \end{bmatrix}$$

Hw 11

In torsion rheology test, circular cylinder

$$R, h \quad \gamma(t) = \gamma_0 e^{i\omega t}$$

use cylinder coordinate,

only stress exist: $\sigma_{\theta z}$.

Initial condition: $\epsilon_{ij} = \sigma_{ij} = 0, \quad t=0$

boundary condition:

$$\{ u_i (r, \theta, z=0, t>0) = 0,$$

$$\{ u_r (r, \theta, z=h, t>0) = 0, \quad u_\theta (r, \theta, z=h, t>0) = 0, \\ u_\theta (r \leq R, \theta, z=h, t>0) = rh\gamma = rh\gamma_0 e^{i\omega t},$$

$$\sigma_{rr} (r=R, \theta, 0 < z < h, t>0) = 0, \quad \dots$$

$$= \sigma_{zz} (r=R, \theta, 0 < z < h, t>0) = 0.$$

(traction free on side walls)

governing eqs. for torsion:

$$u_r = u_z = 0, \quad u_\theta = \gamma r/2$$

the only non-vanishing strain: $\epsilon_{z\theta} = \frac{\gamma r}{2}$

In cylindrical coor., all equilibrium satisfied!

* constitutive model: here linear viscoelasticity comes in

$$\sigma_{z\theta} (r, t) = 2G(t)\epsilon_{z\theta}(r, t=0^+) + 2 \int_{0^+}^t G(t-\tau) \frac{d\epsilon_{z\theta}(r, \tau)}{d\tau} d\tau$$

$$\rightarrow \sigma_{z\theta} (r, t) = G(t) r \delta(t=0^+) + r \int_{0^+}^t G(t-\tau) \frac{d\delta(\tau)}{d\tau} d\tau$$

$$= G(t) \tau_0 + i\omega \int_{0^+}^t G(t-\tau) \frac{d\tau_0 e^{i\omega\tau}}{d\tau} d\tau$$

$$= \left[G(t) + i\omega \int_{0^+}^t G(t-\tau) e^{i\omega\tau} d\tau \right] \tau_0 \equiv \varphi(\omega, t) \tau_0$$

the torque $M(t)$:

$$M(t) = 2\pi \int_0^R \bar{\sigma}_{03} r^3 dr = \pi \tau_0 \varphi(\omega, t) \int_0^R r^3 dr$$

$$= \frac{\pi \varphi(\omega, t) R^4 \tau_0}{2}$$

$$1b. \varphi(\omega, t) = G(t) + i\omega \int_{0^+}^t G(t-\tau) e^{i\omega\tau} d\tau.$$

integral term:

$$\int_{0^+}^t G(t-\tau) e^{i\omega\tau} d\tau = e^{i\omega t} \int_0^t G(t-\tau) e^{-i\omega(t-\tau)} d\tau$$

$$= e^{i\omega t} \int_0^t G(\eta) e^{-i\omega\eta} d\eta = e^{i\omega t} \left[\int_0^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta \right]$$

$$e^{-i\omega\eta} d\eta + \int_0^t G_\infty e^{-i\omega\eta} d\eta \right]$$

$$= e^{i\omega t} \left[\int_0^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta \right]$$

$$+ \frac{G_\infty}{-i\omega} e^{-i\omega t} \Big|_0^t$$

$$= e^{i\omega t} \int_0^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta + \frac{G_\infty}{i\omega} (e^{i\omega t} - 1)$$

then we have φ :

$$\varphi(\omega, t) = G(t) + i\omega \int_{0^+}^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta$$

$$+ \frac{G_\infty}{i\omega} (e^{i\omega t} - 1)$$

$$= (G(t) - G_\infty) + G_\infty e^{i\omega t} + i\omega e^{i\omega t} \int_{0^+}^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta$$

We already know:

$$\int_0^t [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta$$

$$= \int_0^\infty [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta - \int_t^\infty [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta$$

$$\varphi(\omega, t) = [(G(t) - G_\infty) - i\omega e^{i\omega t} \int_t^\infty [G(\eta) - G_\infty]$$

$$e^{-i\omega\eta} d\eta] + \{G_\infty + i\omega \int_t^\infty [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta\} e^{i\omega t}$$

Since $G(\eta \rightarrow \infty) - G_\infty = 0$.

$$\varphi(\omega, t \rightarrow \infty) = \{G_\infty + i\omega \int_t^\infty [G(\eta) - G_\infty] e^{-i\omega\eta} d\eta\} e^{i\omega t}$$

$$= M(\omega) e^{i\omega t}$$

$$M_s(\omega) = \frac{\pi R^4 \tau_0}{2} \omega e^{i\omega t}$$

Assuming $G(t) = G_{\infty} + \frac{G_0 - G_{\infty}}{(1 + \frac{t}{t_p})^n}$, find storage & loss modulus.

• Storage modulus:

$$n'(w) = \operatorname{Re}[\mu(w)] = \operatorname{Re}\left[G_{\infty} + i w \int_0^{\infty} \frac{G_0 - G_{\infty}}{(1 + \eta/t_p)^n} e^{-i w \eta} d\eta\right]$$

$$= G_{\infty} + (G_0 - G_{\infty}) w \operatorname{Re}\left[i \int_0^{\infty} (1 + \eta/t_p)^{-n} e^{-i w \eta} d\eta\right]$$

• Loss modulus:

$$n''(w) = \operatorname{Im}[\mu(w)]$$

$$= (G_0 - G_{\infty}) w \operatorname{Im}\left[i \int_0^{\infty} (1 + \eta/t_p)^{-n} e^{-i w \eta} d\eta\right]$$

to evaluate the integrals, let $\eta/t_p = p$,

$$\text{so that } \int_0^{\infty} (1 + \eta/t_p)^{-n} e^{-i w \eta} d\eta$$

$$= t_p \int_0^{\infty} (1 + p)^{-n} e^{-i w p} dp$$

For our case, $n = 1$.

$$\int_0^{\infty} (1 + p)^{-1} e^{-i w p} dp = \int_0^{\infty} (1 + p)^{-1} \cos(i w p) dp$$

$$= i \int_0^{\infty} (1 + p)^{-1} \sin(i w p) dp$$

$$= \int_0^{\infty} (w + p)^{-1} \cos q dq - i \int_0^{\infty} (w + q)^{-1} \sin q dp$$

$$= \{-C_i(\omega) \cos \omega - S_i(\omega) \sin \omega\} - i \{C_i(\omega) \sin \omega - S_i(\omega) \cos \omega\}$$

C_i & S_i : sine and cosine integrals.

normalize the storage & loss modulus:

$$\bar{n}'(w) = 1 + \left(\frac{G_0}{G_{\infty}} - 1\right) \omega \operatorname{Re}\left[i \int_0^{\infty} (1 + p)^{-1} e^{-i w p} dp\right]$$

$$= 1 + \left(\frac{G_0}{G_{\infty}} - 1\right) \omega \{C_i(\omega) \sin \omega - S_i(\omega) \cos \omega\}$$

$$\bar{n}''(w) = \left(\frac{G_0}{G_{\infty}} - 1\right) \omega \operatorname{Im}\left[i \int_0^{\infty} (1 + p)^{-1} e^{-i w p} dp\right]$$

$$= -\left(\frac{G_0}{G_{\infty}} - 1\right) \omega \{C_i(\omega) \cos \omega + S_i(\omega) \sin \omega\}$$


$$\tan \delta = \frac{-\left(\frac{G_0}{G_{\infty}} - 1\right) \omega \{C_i(\omega) \cos \omega + S_i(\omega) \sin \omega\}}{1 + \left(\frac{G_0}{G_{\infty}} - 1\right) \omega \{C_i(\omega) \sin \omega - S_i(\omega) \cos \omega\}}$$

Dec. 6., Mon., 2021. Wk 16.

Orthotropic material. 9 constants.

$$K = \begin{bmatrix} k_{11} & k_{12} & k_{13} & 0 & 0 & 0 \\ k_{21} & k_{22} & k_{23} & 0 & 0 & 0 \\ k_{31} & k_{32} & k_{33} & 0 & 0 & 0 \\ 0 & 0 & 0 & k_{44} & 0 & 0 \\ 0 & 0 & 0 & 0 & k_{55} & 0 \\ 0 & 0 & 0 & 0 & 0 & k_{66} \end{bmatrix}$$

Transversely Isotropic



$$[\underline{R}] = \begin{bmatrix} \cos\theta & -\sin\theta & 0 \\ \sin\theta & \cos\theta & 0 \\ 0 & 0 & 1 \end{bmatrix}$$

$$\left\{ \begin{array}{l} \underline{\epsilon}'_1 = \cos\theta \underline{\epsilon}_1 + \sin\theta \underline{\epsilon}_2 \\ \underline{\epsilon}'_2 = -\sin\theta \underline{\epsilon}_1 + \cos\theta \underline{\epsilon}_2 \\ \underline{\epsilon}'_3 = -\underline{\epsilon}_3 \end{array} \right.$$

$\underline{\epsilon}_3$

$[\underline{P}] = \begin{bmatrix} \cos\theta & \sin\theta & 0 \\ -\sin\theta & \cos\theta & 0 \\ 0 & 0 & 1 \end{bmatrix}$

$\underline{\epsilon}_1 \leftarrow \theta$

$\sigma_1 = k_{11}\epsilon_1 + k_{12}\epsilon_2 + k_{13}\epsilon_3$
 $\sigma_2 = k_{21}\epsilon_1 + k_{22}\epsilon_2 + k_{23}\epsilon_3$
 $\sigma_3 = k_{31}\epsilon_1 + k_{32}\epsilon_2 + k_{33}\epsilon_3$
 $\sigma_4 = k_{44}\epsilon_4$
 $\sigma_5 = k_{55}\epsilon_5$
 $\sigma_6 = k_{66}\epsilon_6$

$$\underline{\sigma}' = \underline{\underline{P}} \underline{\sigma} \underline{P}^T$$

$$\underline{\epsilon}' = \underline{\underline{P}} \underline{\epsilon} \underline{P}^T$$

$$\sigma'_1 = \sigma_2 \quad \sigma'_2 = 0, \quad \sigma'_3 = \sigma_3$$

$$\sigma'_4 = \sigma_6 - \sigma_5 \quad \sigma'_5 = \sigma_4$$

$$\sigma'_6 = -\sigma_6$$

Same thing for strain.

$$\sigma'_1 = k_{11}\epsilon'_1 + k_{12}\epsilon'_2 + k_{13}\epsilon'_3$$

$$\rightarrow \sigma'_2 = k_{11}\epsilon'^0_2 + k_{12}\epsilon'_1 + k_{13}\epsilon'_3$$

$$\sigma'_2 = k_{21}\epsilon'^0_1 + k_{22}\epsilon'^0_2 + k_{23}\epsilon'_3$$

$$\sigma'_1 = k_{44}\epsilon'_1 + k_{55}\epsilon'_2 + k_{66}\epsilon'_3$$

$$\sigma'_1 = k_{11}\epsilon'_2 + k_{22}\epsilon'_1 + k_{33}\epsilon'_3$$

$$\sigma_1 = k_{11}\varepsilon_1 + k_{12}\varepsilon_2 + k_{13}\varepsilon_3$$

$$k_{12}\varepsilon_2 + k_{21}\varepsilon_1 = k_{11}\varepsilon_1 + k_{12}\varepsilon_2$$

$$k_{11}\varepsilon_1 = k_{12}\varepsilon_2$$

$$k_{11}\varepsilon_1 + k_{13}\varepsilon_3 = k_{11}\varepsilon_1 + k_{23}\varepsilon_3$$

$$(k_{11} - k_{11})\varepsilon_1 + (k_{13} - k_{23})\varepsilon_3 = 0$$

$$k_{11} = k_{11}$$

$$k_{13} = k_{13}$$

$$\sigma_4' = k_{44} \varepsilon_4'$$

$$\sigma_5' = k_{55} \varepsilon_5'$$

$$\sigma_4 = k_{44} \varepsilon_4$$

$$\sigma_4' = -\sigma_5 = -k_{44} \varepsilon_5'$$

$$\sigma_5 = k_{44} \varepsilon_5$$

$$k_{44} = k_{55}$$

$$k_{44} = k_{55} \Rightarrow k_{11} = k_{11} \quad \{$$

$$k_{13} = k_{23} \quad \}$$

$$\begin{bmatrix} k_{11} & k_{12} & k_{13} & 0 & 0 & 0 \\ k_{11} & k_{13} & 0 & 0 & 0 & 0 \\ k_{13} & k_{23} & k_{44} & 0 & 0 & 0 \\ 0 & 0 & 0 & k_{55} & 0 & 0 \\ 0 & 0 & 0 & 0 & k_{66} & 0 \\ 0 & 0 & 0 & 0 & 0 & k_{66} \end{bmatrix}$$

$$\theta = 45^\circ \rightarrow \pi/4$$

$$[P] = \begin{pmatrix} \frac{1}{\sqrt{2}} & \frac{1}{\sqrt{2}} & 0 \\ -\frac{1}{\sqrt{2}} & \frac{1}{\sqrt{2}} & 0 \\ 0 & 0 & 1 \end{pmatrix}$$

$$\varepsilon_{12}', \varepsilon_{12}$$

calculated.
this has to be
true.

$$k_{66} = \frac{1}{2}(k_{11} - k_{11})$$

$$\frac{1}{2}[k_{11} - k_{11}]$$

$$K^{-1} \cdot Q = \Sigma$$

S matrix compliance index

Poisson's ratio for anisotropic elastic material.
Can leave no bounds. Tzg, TCT.


Linear Viscoelasticity

Correspondence principle

↪ stress dependent of underlying

$$\sigma_{ij} = S_{ij}(0^+) C_1(t) + \int_{0^+}^t C_1(t-\tau) \frac{\partial S_{ij}}{\partial \tau} d\tau$$

$$\epsilon_{kk} = \Omega_{kk}(0^+) C_2(t) + \int_{0^+}^t C_2(t-\tau) \frac{\partial \Omega_{kk}}{\partial \tau} d\tau$$




Creep modulus.

(\rightarrow) remote hydrostatic tension

$$P_{out}(t=0) = 0$$

Elastic problem:



$$\left\{ \begin{array}{l} \sigma_{rr} = \frac{A}{r^2} + P_\infty \\ \sigma_{\theta\theta} = -\frac{A}{r^2} + P_\infty \\ \sigma_{r\theta} = 0 \end{array} \right. \quad r > A$$

$$\sigma_{rr} = \sigma_{\theta\theta} = \sigma_{in}$$



$r < A$

Continuity of traction.

$$\frac{A}{r^2} + P_\infty = \sigma_{in}$$

$A, P_\infty \rightarrow \text{unknown}$

$$2G_{out} \epsilon_{\theta\theta} = \sigma_{\theta\theta} - \frac{1}{2} \sigma_{rr} \quad r > a$$

$$(r > a) \quad \epsilon_{\theta\theta} = \frac{1}{3G_{out}} \left[-\frac{3A}{2r^2} + \frac{P_\infty}{r} \right]$$

$$\epsilon_{\theta\theta} = \frac{u}{r}$$

$$r < a, \quad \epsilon_{in} = \epsilon_{\theta\theta} = \epsilon_m = \frac{u}{r}$$

$$u = \epsilon_m r$$

$$3G_{in} \epsilon_{in} = \sigma_{\theta\theta} - \frac{1}{2} \sigma_{rr} \\ = \sigma_{in}/2$$

$$\therefore \dot{\epsilon}_{in} = \frac{\dot{O}_{in}}{6G_{in}} = \frac{u}{r}$$

Continuity of Hookes strain.

$$2G_{out} \left[\frac{-3A}{2a^2} + \frac{P_\infty}{r} \right] = \frac{\dot{O}_{in}}{6G_{in}}$$

$$\frac{A}{a^2} = \frac{(p-1)P_\infty}{(1+3p)}, \quad p = \frac{G_{in}}{G_{out}}$$

$$\dot{O}_{in} = \frac{4p}{1+3p} P_\infty$$

$$\frac{G_{in}}{G_\infty} \rightarrow \infty \Rightarrow \frac{A}{a^2} = \frac{1}{3} P_\infty$$

$$\dot{O}_{\infty} (r = a) = -\frac{2}{3} P_\infty$$

$$G_{in} = \frac{1}{r} s \tilde{Y}_{in}(s)$$

$$G_{out} = \frac{1}{r} s \tilde{Y}_{out}(s)$$

$$\tilde{O}_{in} = \frac{4 \frac{\tilde{Y}_{in}(s)}{\tilde{Y}_{out}(s)}}{1 + 3 \frac{\tilde{Y}_{in}(s)}{\tilde{Y}_{out}(s)}} \tilde{P}_\infty(s)$$

$$Y_{in}(t) = Y_{in0} + (Y_{out0} - Y_{in0}) e^{-t/t_{in}}$$

$$L(Y_{in}(t)) = \tilde{Y}_{in}(s) = \int_0^\infty e^{-st} Y_{in}(t) dt$$

$$\tilde{Y}_{in}(s) = \frac{Y_{in0}}{s} + \frac{(Y_{out0} - Y_{in0})}{s + t/t_{in}}$$

$$\tilde{Y}_{out}(s) = \frac{Y_{out0}}{s} + \frac{Y_{out0} - Y_{out\infty}}{s + t/t_{out}}$$

$$\tilde{O}_{in}(t) = \frac{1}{2\pi i} \int_{\delta-\infty}^{\delta+\infty} e^{st} \tilde{O}_\infty(t) ds$$

* Solve ODE with MATLAB.

HW 10. Review:

a. Problem formulation

$$\nabla^2 \phi = 0, \text{ in } |x| < a \text{ and } |y| < b$$

BCs:

$$\phi(x = \pm a/2, |y| < b) = \frac{1}{2} \left(\frac{a^2}{4} + y^2 \right)$$

$$\phi(|x| < \frac{a}{2}, y = \pm \frac{b}{2}) = \frac{1}{2} \left(\frac{b^2}{4} + x^2 \right)$$

b. $f = \nabla_m \phi + 1$.

on the boundary $y = \pm \frac{b}{2}$,

$$\Rightarrow f(x < a/2, y = \pm \frac{b}{2}) = 2$$

on the boundary $x = \pm \frac{a}{2}$.

we know $\partial_x \phi = -\partial_y \phi$.

$$\Rightarrow f(x = \pm \frac{a}{2}, |y| < b/2) = 0$$

c. find f :

$$f(x, y) = X(x) Y(y)$$

Substitute into $\nabla^2 f = 0$:

$$X''(x)Y(y) + X(x)Y''(y) = 0$$

$$\Rightarrow \frac{X''(x)}{X(x)} = -\frac{Y''(y)}{Y(y)} = C = -k^2$$

we look for solution satisfy $x = \pm \frac{a}{2}$:

$$\{ X''(x) + k^2 X(x) = 0$$

$$\{ Y''(y) - k^2 Y(y) = 0$$

$$\{ X(x) = B \sin kx + A \cos kx \xrightarrow{x = \pm \frac{a}{2}, Y=0}$$

$$\{ Y(y) = C \cosh ky + D \sinh ky$$

$$f(x, y) = \sum a_n \cos(k_n x) \cosh(k_n y)$$

BCs: $f(x < \frac{a}{2}, y = \pm \frac{b}{2}) = 2$

$$\sum a_n \cos(k_n x) \cosh(k_n b/2) = 2$$

Method of Fourier series:

$$a_n = \frac{2}{a \cosh(k_n b/2)} \int_{-a/2}^{a/2} 2 \cos(k_n x) dx$$

$$= \frac{8(-1)^n}{\pi(2n+1) \cosh(kab/\nu)}$$

Thus:

$$f(x,y) = \frac{8}{\pi} \sum_{n=0}^{\infty} \frac{(-1)^n}{2n+1} \frac{\cosh(kay)}{\cosh(kab/\nu)} \cos((kn\pi)x)$$

$$k_n = \frac{2n+1}{a}\pi$$

d: find max stress:

Shear stresses:

$$\left\{ \begin{array}{l} \sigma_{13} = G\gamma(-y + \phi_{12}) \\ \tau_{13} = G\tau(x - \phi_{12}) \\ \frac{\sigma_{13}}{G\gamma} - y = \phi_{12} \\ -\frac{\sigma_{23}}{G\tau} + x = \phi_{12} \end{array} \right.$$

on the boundary $x = \pm \frac{a}{2}$, $\phi_{12} \Big|_{x=\pm \frac{a}{2}} = y$.

$$\sigma_{13} = 0 \text{ on } x = \pm \frac{a}{2}$$

$$\tau_{13} = 0 \text{ on } y = \pm \frac{b}{2}$$

$$\phi_{12} \Big|_{y=\pm \frac{b}{2}} = \pi$$