CHAPTER 4

USING THE COMPILER

This chapter explains how to use the C cross compiler to compile programs on your host system. It explains how to invoke the compiler, and describes the command line options the compiler accepts. It also describes the functions which constitute the C library.

Invoking the Compiler

To invoke the cross compiler, type the command name c, followed by the name(s) of the file or files you want to compile and any compiler options you choose. All the valid compiler options are described in this chapter. Commands to compile source files must have the form:

c [-<options>] <file>.[c|s|o]

c is the name of the "compiler driver" program that runs the compiler and other programs. The compiler driver and the compilation process are discussed in Chapter 1 and in Appendix C. The option list is optional. You must include the name of at least one source file <file>. <file> must be a C source file with the suffix '.c', an assembly language source file with the suffix '.s', or an object file with the suffix '.o'. You may specify multiple source files with any combination of these suffixes in any order. You can change the default suffixes that c expects as described in Appendix C, "Modifying Compiler Operation." For information on default file names, see the section "File Naming Conventions" below.

If you do not specify any command line options, c will compile and link your <files> by default. It will also write the name of each file to STDOUT as it is processed. It writes any error messages to STDERR.

The following example compiles the C source file acia.c:

c acia.c

This command compiles, assembles, and links the acia.c C program, creating the executable program xeq.80.

If the compiler finds an error in your program, it halts compilation. When an error occurs, the compiler sends a error message to your terminal screen, or to your listing if you request one. Appendix A, "Compiler Error Messages," lists the error messages the compiler generates. If one or more command line arguments are invalid, c processes the next file name on the command line and begins the compilation process again. The only error that c tests for is invalid command line length.

The example command above does not request any compiler options. In this case, the compiler driver will use only default information to compile, assemble, and link your program. You can change the operation of the compiler driver by specifying the options you want when you run the compiler driver. You can also change the operation of the compiler driver by modifying the "prototype file" that specifies options directly to the passes of the compiler. Appendix C, "Modifying Compiler Operation," tells you how to modify the prototype file and create your own compiler driver options.

To specify options to the compiler driver, type the appropriate option or options on the command as shown in the first example above. Options should be separated with spaces. You must include the '-' or '+' that is part of the option name.

Compiler Command Line Options

The $\, c \,$ compiler driver accepts the following command line options:

c -[delim* d*^ o* prefix* proto* sep* s v x +*^] <files>

The options are described below.

- -delim* change delimiter characters between the file name and suffix on host systems where the period '.' is not an acceptable symbol.
- -d** specify * as the name of a user-defined "programmable" compiler command line option. You may specify up to 20 such options. See Appendix B for information on creating user-defined compiler options.

- -d64180 use the HD64180 extensions. By default code is produced for a Z80.
- -ddl1 produce line number information (type 1). Type 1 line number information includes the function name and line number.
- -dd12 produce line number information (type 2). Type 2 line number information includes the file name and line number.
- -dfloat Link your C program with C library functions from the floating point library. This option directs the linker to load the floating point library before the integer library. Therefore, modules common to both libraries are loaded from the floating point library. By default, the linker links your program with C library functions from the integer library only. See the section "C Library Support" in this chapter for more information.
- -dlincl force a listing of all #include files to be included with the source listing, and cause diagnostics (when produced) to indicate the actual #include file name and line number. This option is meaningful only in combination with -dlistcs.
- -dlistc Create a C source listing interspersed with error messages; the listing output defaults to <file>.lst.
- -dlistcs merge C source listing with assembly language code; listing output defaults to <file>.ls.
- -dnobss Generate an object image without a bss section. By default, the compiler automatically places all initialized static data objects in the bss section.
- -dnostrict Direct the compiler to enforce weaker type checking. When you specify -dnostrict, the compiler will not generate an error message if:
 - you assign a pointer value to an integer,
 - you assign an integer value other than zero (NULL) to a pointer,
 - 3. you check two different data objects of type pointer to ... for assignment compatibility, or 4. the type of the operand of a conditional expression that the compiler evaluates is not compatible with the type of the result. For information on how the compiler evaluates conditional expressions, see the section "Expressions" in

- Chapter 2 of the <u>C</u> <u>Language</u> <u>Specification</u> <u>for Microcontroller</u> <u>Environments</u>. By <u>default</u>, any of the above actions causes the compiler to generate an error message.
- -dprom enable automatic data initialization, and select the corresponding startup object file.
- -dproto enable prototype checking.
- -drev Reorder bits in bitfields, from most significant to least significant. By default, bits are numbered from least significant to most significant.
- schar Take "plain" char as signed char. By default char is taken to bu unsigned char.
- -dsp Enable single precision floating point support. By default, the compiler provides double precision floating point support.
- -dsprec Force all floating point arithmetic to single precision. If this option is enabled, all floats, doubles, and long doubles are treated as floats, and calculations are made in single precision.
- -dstd Force your C source input to conform to the April 1985 ANSI Draft Proposed Standard for C. By default, your C source need not conform to the ANSI Draft Proposed Standard to compile successfully.
- -dstrict Direct the compiler to enforce stronger type
 checking. When you specify -dstrict, the compiler
 will generate an error message if:
 - 1. an argument to a function definition does not have an explicit type associated with it at the time that the compiler encounters the opening '{' of the function body. By default, the compiler will assign the type int to a function argument that does not have an explicit type.
 - 2. an assignment operation narrows the type of the result. By default, the compiler will truncate the result of a narrowing assignment without generating an error message. For more information on type conversion, see the section "Expressions" in Chapter 2 of the C Language Specification for Microcontroller Environments.
 - you use the return value of a function and do not declare the return type of the func-

tion. By default, the compiler will assign the type int to to the return value of a function.

- -dverbose Display to STDOUT the name of the function currently being processed by the code generator, and the number of optimizations performed by the optimizer. By default, the compiler does not provide this specific information.
- -dxdebug generate a Version 3.3 object module containing debugging information. This information can be interpreted by cxdb or by the lines or prdbg utilities. Only modules compiled with this option will contain debugging information. See Chapter 7 for more information.
- -prefix* prefix names of all permanent output files with the pathname *.
- -proto* take prototype input from the file *.
- -s be "silent". Do not write filenames or arguments to STDOUT during compilation.
- -v be "verbose". Before executing a command, print the command, along with its arguments, to STDOUT. The default is to output only the names of each file processed, and the root name when (and if) the grouping line is run. Each name is followed by a colon and newline. The root name consists of the source line without its suffix. If you specify both the -v and -s options, -v is performed.
- -x do not execute the commands in the prototype file. Instead, write the commands which otherwise would have been performed to STDOUT.
- +* save permanent copies of (otherwise temporary) intermediate files with suffix * Compilation halts at the
 end of the pass producing files with that suffix.
 For example, to save the intermediate output of the
 cp180 compiler pass (the suffix for which is 2),
 specify the +2 option.

The compiler accepts up to ten instances of +*. Valid values for * are any or all of the suffixes that the com-

piler appends to the output of each pass. The default suffixes generated are described in the section "File Naming Conventions" below. See Appendix D for information on compiler passes.

The compiler appends suffixes to output files produced by each pass by reading the prototype file and copying the labels preceding each step. You can change the default suffix that the compiler appends to its output files by modifying the labels in your prototype file. See Appendix B for more information.

File Naming Conventions

The programs making up the C cross compiler generate the following output file names by default when passed as input a file whose name (minus any suffix) is <file>. See the documentation on a specific program for information about how to change the default file names that it accepts as input or generates as output.

program	input file name	output file name
C Compiler Passes		
cpp80 cp180 cp280 opt80 assembler list C source and c	errors	<pre><file>.1 <file>.2 <file>.3 <file>.s <file>.c c s <file>.ls <file>.c <file>.ls</file></file></file></file></file></file></file></file></pre>
Assembler		
x80 source listing symbol table	<pre> ⟨file⟩.s ⟨file⟩.s ⟨file⟩.s</pre>	<file>.o <file>.ls <file>.sm</file></file></file>
Linker		
lnk80	<file>.o</file>	xeq.80
Programming Support Utilities		
hex80 lby lm lord80 pr rel80 toprom unhex	<file> <file></file></file></file></file></file></file></file></file></file></file></file></file>	STDOUT user must specify name STDOUT dir STDOUT STDOUT <file> <file></file></file>

Generating Listings

You can generate listings of the output of any (or all) the compiler passes by specifying one or both of the command line options -dlincl and -dlistcs to the c compiler driver. These and other command line options are

described in the preceding section.

When any command line options are specified, the compiler driver specifies the +list option to the appropriate compiler passes, forcing invocation of lm, the listing merger utility, which merges the listings output by the compiler, and pr, which paginates the listing and places a header at the top of each page.

All passes of the compiler accept the same line references and error message flags, which are generated by each pass along with the source code translation. When the compiler driver exits, all files created will have embedded in them relevant error listings from the compiler pass that generated them, as well as listings from all previous passes where diagnostics were output. For example, assembly language files will contain diagnostics generated by the compiler and/or the assembler, depending on if either or both programs found errors. However, any error message points to the line in the original source code where the error occurred. The listing will hold line number references from the originating language.

It is also possible to generate error listings that point to lines in the intermediate language file. One does so by stopping the compiler at the desired intermediate step using the +* compiler option, removing the original source line references, and re-compiling with the intermediate code as the source. For example, to generate a listing of assembly language code with error messages that refer to the assembly language code itself instead of the original C or Pascal source,

- o stop compilation after the code generator pass, thus automatically saving the resulting assembly language code in a permanent file.
- Strip out the original #line sequences, instead of the original C or Pascal source, and begin compilation again from there. Error messages will now point to assembly language statements.

The example on the following pages shows the listing produced by compiling the C source file acia.c with the -dlistcs command line option:

c -dlistcs acia.c

```
1
                       .psect _text
 2
                        1
                  ;
 3
                        2
                           /*
                  ;
 4
                        3
                            *
                   ;
 5
                   ;
                        4
                            * Each received character is copied in a buffer
 6
                            * by the interrupt routine. main() reads
                   ;
 7
                        6
                            * characters from the buffer and echoes them.
                   ;
 8
                        7
                   ;
 9
                        8
                            */
                   ;
                                                     /* size of the buffer */
10
                       9
                          #define SIZE
                                            512
                  ;
11
                      10
12
                      11
                          /* the input port is a char at port 2
13
                      12
                           * the output port is a char at port 5
14
                      13
15
                      14
                          @port char input @0x02;
16
                      15
                          @port char output @0x05;
17
                      16
18
                          /* Some variables
                      17
19
                      18
                           */
20
                      19
                          char buffer[SIZE];
                                                     /* reception buffer */
21
                      20
                          char *ptlec;
                                                     /* read pointer */
22
                      21
                          char *ptecr;
                                                     /* write pointer */
23
                      22
24
                          /* "builtin" function for enabling interrupts
                      23
25
                      24
                           */
26
                      25
                          @builtin ei() @0xfb;
                  ;
27
                      26
                  ;
28
                      27
                          /* character reception. loops until a character
                  ;
29
                      28
                           is received */
                  ;
30
                      29
                          char getch()
                  ;
31
                      30
                               {
32
                  getch:
33
    0000
           CD0000
                      call
                               c.savs0
                      ld hl,-7
34
    0003
           21F9FF
35
    0006
           39
                      add hl,sp
36
    0007
          F9
                      ld sp,hl
37
                 L1:
38
                  ;
                      31
                               char c:
                                         /* character to be returned */
39
                      32
                 ;
40
                      33
                              while (ptlec == ptecr)
41
    8000
           210000
                      ld
                          hl, ptecr
                          a,(_ptlec)
(hl)
42
    000B
           3A0200
                      ld
43
    000E
          BE
                      ср
44
    000F
           2005
                          nz,L4
                      jr
45
    0011
           3A0300
                      ld
                          a,(_ptlec+1)
46
    0014
           23
                      inc hl
47
    0015
          BE
                      ср
                          (hl)
48
                 L4:
49
    0016
           28F0
                      jr
                          z, L1
50
                      34
51
                      35
                              c = *ptlec++;
                                                /* get the received char */
                      ld hl,(_ptlec)
push hl
52
    0018
           2A0200
53
    001B
                      push
          E5
54
    001C
          23
                      inc hl
```

```
55
     001D
           220200
                      ld (_ptlec),hl
56
     0020
           E1
                      pop hI
57
     0021
           7E
                      ld
                          a,(hl)
58
     0022
           DD77F9
                      1d
                           (ix-7),a
59
                      36
                               if (ptlec > &buffer[SIZE]) /* put in in buffer */
60
    0025
           210402
                      ld
                           hl,_buffer+512
61
    0028
           ED4B0200
                      ld
                           bc,(_ptlec)
62
    002C
           7D
                      ld
                           a,l
63
    002D
           91
                      sub c
64
    002E
           7C
                      ld
                          a,h
65
    002F
           98
                      sbc a,b
66
    0030
           3006
                      jr
                          nc,L12
67
                      37
                                        ptlec = buffer;
68
    0032
           210400
                      ld
                           hl, buffer
69
    0035
           220200
                      ld
                           (ptlec),hl
70
                  L12:
71
                      38
                               return (c);
72
    0038
           DD6EF9
                      ld
                          1,(ix-7)
73
    003B
           97
                      sub a
    003C
74
           67
                      ld
                          h,a
75
    003D
           4D
                      ld
                          c,l
76
    003E
           44
                      ld
                          b,h
77
    003F
           C30000
                      jр
                          c.rets0
78
                      39
                               }
79
                      40
80
                          /* Send a char to the output port
                      41
                  ÷
81
                      42
                           */
                  ;
82
                      43
                          outch(c)
                  ;
83
                      44
                               char c;
                  ;
84
                      45
85
                   outch:
86
    0042
           CD0000
                      call
                              c.savs
87
                      46
                              output = c;
                                                  /* send it */
88
    0045
           DD7E04
                      ld
                         a,(ix+4)
89
    0048
           D305
                      out (5), a
90
                      47
                              }
    004A
91
           C30000
                      jр
                          c.rets
92
                      48
93
                          /* character reception routine.
                      49
                 ;
94
                           * This routine is called on interrupt
                      50
                 ;
95
                      51
                 ;
                           * It puts the received char in the buffer
96
                      52
                           */
97
                      53
                          @port recept()
98
                      54
                              {
99
                  recept:
100 004D
          F5
                      push
                              af
101 004E
           C5
                      push
                              bc
102 004F
          D5
                      push
                              de
103 0050
          E5
                              hl
                      push
104 0051
           CD5A00
                              L21
                      call
105 0054
          E1
                      pop hl
106 0055
          D1
                     pop de
107 0056
          C1
                     pop bc
108 0057
          F1
                     pop af
```

```
109 0058
          ED4D
                     reti
                 L21:
110
111
                     55
                             *ptecr++ = input; /* get the char */
112 005A
          2A0000
                     ld hl,(_ptecr)
113 005D
                     push
          E5
114 005E
          23
                     inc hl
115 005F
          220000
                     ld (ptecr), hl
116 0062
          E1
                     pop hl
117 0063
          DB02
                     in a, (2)
118 0065
          77
                     ld
                        (hl),a
119
                     56
                             if (ptecr >= &buffer[SIZE]) /* put in buffer*/
120 0066
          210402
                     ld hl,_buffer+512
121 0069
          3A0000
                     ld a,(_ptecr)
122 006C
          95
                     sub 1
123 006D
          3A0100
                     ld a,(_ptecr+1)
124 0070
          9C
                     sbc a,h
125 0071
          3806
                     jr c,L13
126
                     57
                                     ptecr = buffer;
127 0073
          210400
                     ld hl,_buffer
128 0076
          220000
                     ld (ptecr),hl
129
                 L13:
130
                     58
                             }
131 0079
          C9
                     ret
132
                     59
                 ;
133
                     60
                         /* Main program : an infinite loop
                 ;
134
                         * of receive transmit
                     61
                 ;
135
                          */
                     62
                 ;
136
                     63
                         main()
137
                     64
                             {
138
                 main:
139 007A
          CD0000
                             c.savs0
                     call
                     ld hl,-7
140 007D
          21F9FF
141 0080
          39
                     add hl,sp
142 0081
                     ld sp,hl
143
                     65
                                              /* received char */
                             char c;
144
                     66
145
                     67
                             ptecr = ptlec = buffer; /* init pointers */
146 0082
          210400
                        hl, buffer
                     ld
147 0085
          220200
                     ld
                         (ptlec),hl
148 0088
          220000
                     ld
                         ( ptecr), hl
149
                     68
                             ei();
                                                  /*enable interrupts */
150 008B
                             251
                     .byte
151
                L14:
152
                     69
                             for (;;)
                                                  /* loop */
                ;
153
                     70
                                  {
154
                     71
                                  c = getch();
                                                  /* get a char */
155 008C
          CD0000
                     call
                              getch
156 008F
          DD71F9
                     ld (ix-7), c
157
                     72
                                  outch(c);
                                                  /* send it */
158 0092
          DD6EF9
                    1d 1,(ix-7)
159 0095
          97
                     sub a
160 0096
          67
                    ld h,a
161 0097
          CD4200
                             _outch
                     call
162
                     73
```

```
163 009A 18F0
                           jr L14
164
                           74
165
                           .psect
                                      bss
166
                      _ptecr:
167
                          .byte
                                     [2]
168
                      ptlec:
169
                           .byte
                                      [2]
170
                      _buffer:
171
                           byte
                                      [512]
172
                           .external
                                            c.rets0
173
                           .external
                                            c.savs0
                           .public _ptecr
.public _ptlec
.public _getch
.public _recept
.public _buffer
174
175
176
177
178
179
                           .external
                                           c.rets
180
                           .external
                                           c.savs
181
                           .public _main
.public _outch
182
183
                           .end
```

Return Status

c returns success if it can open all files successfully. It prints a message to STDERR and returns failure if there are errors in the prototype file, or if any files cannot be opened.

Examples

To echo the names of each program that the compiler driver runs to your terminal screen:

c -v file.c

To generate information for use by the cxdb, the C source debugger:

c -dxdebug file.c

To save the intermediate files created by the code generator and the assembler, and to halt compilation after creating an object file:

c +s +o file.c

To give the name myprog to the executable file that the compiler generates:

c -o myprog file.c

C Library Support

This section describes the facilities provided by the C library. The C cross compiler for Z80/HD64180 includes all the standard C library functions, including those useful to programmers writing applications for ROM-based systems.

How C Library Functions are Packaged

The functions in the C library are packaged in three separate sub-libraries; one for machine-dependent routines (the machine library), one for functions that do not require floating point support (the integer library) and one for functions that do require floating point support (the floating point library). If your application does not perform floating point calculations, you can decrease its size and increase its runtime efficiency by including only functions from the integer library.

Inserting Assembler Code Directly

Assembler instructions can be quoted directly into C source files, and entered unchanged into the output assembly stream, by use of the _asm() function. This function is not part of either library; it is recognized by the compiler itself.

Linking Libraries with Your Program

By default, the compiler links its input programs with appropriate modules from the integer library only. If your application requires floating point support, specify the defloat option when invoking the compiler, or at link time, if compilation and linking occur separately. This option directs the linker to load the floating point library before the integer library. Modules common to both libraries will therefore be loaded from the floating point library, followed by the appropriate modules from the floating point and integer libraries, in that order.

Integer Library Functions

The following table lists the C library functions in the integer library.

Integer Library Functions

Floating Point Library Functions

Floating Point Library Functions

acos	cos	log10	sprintf
asin	cosh	pow	sqrt
atan	exp	printf	sscanf
atan2	fabs	scanf	tan
atof	floor	sin	tanh
ceil	log	sinh	

Common Input/Output Functions

Four of the functions that perform stream input/output are included in both the integer and floating point libraries. The functionalities of the versions in the integer library are a subset of the functionalities of their floating point counterparts. The versions in the integer library cannot print or manipulate floating point numbers. These functions are: printf, scanf, sprintf and sscanf.

Functions Implemented as Macros

Five of the functions in the C library are actually implemented as "macros." Unlike other functions, which (if they do not return int) are declared in header files and defined in a separate object module that is linked in with your program later, functions implemented as macros are defined using #define preprocessor directives in the header file that declares them. Macros can therefore be used independently of any library by including the header file that defines and declares them with your program, as explained below. The functions in the C library that are implemented as macros are: max, min, va_arg, va_end, and va_start.

Including Header Files

If your application calls a C library function that can return a value of a type other than int, you must include the header file that declares the function at compile time. You do this by writing a preprocessor directive of the form:

#include <header name>

in your program, where header_name is the name of the appropriate header file enclosed in angle brackets. Include a required header file before you refer to any function that it declares.

C library functions returning <u>int</u> are not declared in header files, since <u>int</u> is the function return type that the compiler assumes by default. You can therefore call these functions without including any header file.

The names of the header files packaged with the C library and the functions declared in each header are listed below.

<math.h> Header file for mathematical functions: abs,
 acos, asin, atan, atan2, ceil, cos, cosh, exp, fabs,
 floor, log, log10, pow, sin, sinh, sqrt, tan and tanh

<setjmp.h> Header file for nonlocal jumps: setjmp and
longjmp

<stdarg.h> Header file for walking argument lists:
 va_arg, va_end and va_start. Use these macros with
 any function you write that must accept a variable
 number of arguments.

- <stdio.h> Header file for stream input/output: getchar,
 gets, printf, putchar, puts, scanf, sprintf and
 sscanf
- <stdlib.h> Header file for general utilities: atof, atoi,
 atol, calloc, free, malloc, max, min, rand, realloc
 and srand
- <string.h> Header file for string functions: memchr,
 memcmp, memcpy, memset, strcat, strchr, strcmp,
 strcpy, strcspn, strlen, strncat, strncmp, strncpy,
 strpbrk, strrchr and strspn
- <wslxa.h> This header file provides definitions for
 Whitesmiths' defined types and special storage
 classes, and for various system parameters. There
 are no C library functions defined in <wslxa.h>.
- Functions returning int C library functions that return int, and can therefore be called without including any header file, are: isalnum, isalpha, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, sbreak, tolower and toupper

Descriptions of C Library Functions

The following pages describe each of the functions in the C library in quick reference format. The descriptions are in alphabetical order by function name.

asm() - generate inline assembly code

SYNOPSIS

/* no header file need be included */
asm(<string constant>);

FUNCTION

_asm() generates inline assembly code by copying <string constant> and quoting it into the output assembly code stream.

RETURNS

Nothing, unless <u>asm()</u> is used in an expression. In that case, normal return conventions must be followed. See chapter 3, "Register Usage."

EXAMPLE

The sequence ld hl, 1; call _func, may be generated by the following call:

_asm("\tld hl, 1\n\tcall func\n");

Note that the string-quoting syntax matches the familiar $\mathbf{printf}(\mathbf{)}$ function.

NOTES

<u>asm()</u> is not packaged in any library. It is recognized (and its argument passed unchanged) by the compiler itself.

abs - find absolute value

SYNOPSIS

/* no header file need be included */
int abs(i)
 int i;

FUNCTION

abs obtains the absolute value of $\underline{\mathbf{i}}$. No check is made to see that the result can be properly represented.

RETURNS

abs returns the absolute value of i, expressed as an int.

EXAMPLE

SEE ALSO

fabs

NOTES

abs is packaged in the integer library.

acos - arccosine

SYNOPSIS

FUNCTION

acos computes the angle in radians the cosine of which is x, to full double precision.

RETURNS

acos returns the closest internal representation to acos(x), expressed as a double floating value in the range [0, pi]. If x is outside the range [-1, 1], acos returns zero.

EXAMPLE

To find the arccosine of x: theta = acos(x);

SEE ALSO

asin, atan, atan2

NOTES

acos is packaged in the floating point library.

	asin - arcsine
SYNOPSIS	
	<pre>#include <math.h> double asin(x) double x;</math.h></pre>
FUNCTION	asin computes the angle in radians the sine of which is \underline{x} , to full double precision.
RETURNS	asin returns the nearest internal representation to asin(x), expressed as a double floating value in the range [-pi/2, pi/2]. If x is outside the range [-1, 1], asin returns zero.

EXAMPLE

To compute the arcsine of y: theta = asin(y);

SEE ALSO

acos, atan, atan2

NOTES

asin is packaged in the floating point library.

atan

NAME

atan - arctangent

SYNOPSIS

FUNCTION

atan computes the angle in radians; the tangent of which is \underline{x} , to full double precision.

RETURNS

atan returns the nearest internal representation to atan(x), expressed as a double floating value in the range [-pi/2, pi/2].

EXAMPLE

To find the phase angle of a vector in degrees: theta = atan(y/x) * 180.0 / pi;

SEE ALSO

acos, asin, atan2

NOTES

atan is packaged in the floating point library.

atan2 - arctangent of y/x

SYNOPSIS

FUNCTION

atan2 computes the angle in radians the tangent of which is y/x to full double precision. If y is negative, the result is negative. If x is negative, the magnitude of the result is greater than pi/2.

RETURNS

atan2 returns the closest internal representation to atan(y/x), expressed as a double floating value in the range [-pi, pi]. If both input arguments are zero, atan2 returns zero.

EXAMPLE

To find the phase angle of a vector in degrees: theta = atan2(y/x) * 180.0/pi;

SEE ALSO

acos, asin, atan

NOTES

atan2 is packaged in the floating point library.

atof - convert buffer to double

SYNOPSIS

#include <stdlib.h>
double atof(nptr)
 const char *nptr;

FUNCTION

atof converts the string at nptr into a double. The string is taken as the text representation of a decimal number, with an optional fraction and exponent. Leading whitespace is skipped and an optional sign is permitted; conversion stops on the first unrecognizable character. Acceptable inputs match the pattern

[+|-]d*[.d*][e[+|-]dd*]

where \underline{d} is any decimal digit and \underline{e} is the character 'e' or 'E'. No checks are made against overflow, underflow, or invalid character strings.

RETURNS

atof returns the converted double value. If the string has no recognizable characters, it returns zero.

EXAMPLE

To read a string from STDIN and convert it to a double at d:
 gets(buf);
 d = atof(buf);

SEE ALSO

atoi, atol

NOTES

atof is packaged in the floating point library.

atoi - convert buffer to integer

SYNOPSIS

#include <stdlib.h>
int atoi(nptr)
 const char *nptr;

FUNCTION

atoi converts the string at npt" into an integer. The string is taken as the text representation of a decimal number. Leading whitespace is skipped and an optional sign is permitted; conversion stops on the first unrecognizable character. Acceptable characters are the decimal digits. If the stop character is 1 or L, it is skipped over.

No checks are made against overflow or invalid character strings.

RETURNS

atoi returns the converted integer value. If the string has no recognizable characters, zero is returned.

EXAMPLE

To read a string from STDIN and convert it to an int at i: gets(buf);
 i = atoi(buf);

SEE ALSO

atof, atol

NOTES

atoi is packaged in the integer library.

atol - convert buffer to long

SYNOPSIS

#include <stdlib.h>
long atol(nptr)
 const char *nptr;

FUNCTION

atol converts the string at \underline{nptr} into a long integer. The string is taken as the text representation of a decimal number. Leading whitespace is skipped and an optional sign is permitted; conversion stops on the first unrecognizable character. Acceptable characters are the decimal digits. If the stop character is l or L it is skipped over.

No checks are made against overflow or invalid character strings.

RETURNS

atol returns the converted long integer. If the string has no recognizable characters, zero is returned.

EXAMPLE

To read a string from STDIN and convert it to a long 1:
 gets(buf);
 l = atol(buf);

SEE ALSO

atof, atoi

NOTES

atol is packaged in the integer library.

calloc - allocate and clear space on the heap

SYNOPSIS

#include <stdlib.h>
void *calloc(nelem, elsize)
 unsigned int nelem;
 unsigned int elsize;

FUNCTION

calloc allocates space on the heap for an item of size nbytes, where nbytes = nelem * elsize. The space allocated is guaranteed to be at least nbytes long, starting from the pointer returned, which is guaranteed to be on a proper storage boundary for an object of any type. The heap is grown as necessary. If space is exhausted, calloc returns a null pointer. The pointer returned may be assigned to an object of any type without casting. The allocated space is initialized to zero.

RETURNS

calloc returns a pointer to the start of the allocated cell if successful; otherwise it returns NULL.

EXAMPLE

To allocate an array of ten <u>doubles</u>: double *pd; pd = calloc(10, sizeof (double));

SEE ALSO

free, malloc, realloc

NOTES

calloc is packaged in the integer library.

ceil

NAME	ceil - round to next higher integer
SYNOPSIS	<pre>#include <math.h> double ceil(x) double x;</math.h></pre>
FUNCTION	ceil computes the smallest integer greater than or equal to \underline{x} .
RETURNS	ceil returns the smallest integer greater than or equal to x , expressed as a double floating value.
EXAMPLE	x ceil(x)
	5.1 6.0 5.0 5.0 0.0 0.0 -5.0 -5.0 -5.1 -5.0
SEE ALSO	floor
NOTES	

ceil is packaged in the floating point library.

cos - cosine

SYNOPSIS

FUNCTION

cos computes the cosine of \underline{x} ; expressed in radians, to full double precision. If the magnitude of \underline{x} is too large to contain a fractional quadrant part, the value of \cos is 1.

RETURNS

 \cos returns the nearest internal representation to $\cos(x)$ in the range [0, pi], expressed as a double floating value. A large argument may return a meaningless value.

EXAMPLE

To rotate a vector through the angle theta:

xnew = xold * cos(theta) - yold * sin(theta);
ynew = xold * sin(theta) + yold * cos(theta);

SEE ALSO

sin, tan

NOTES

cos is packaged in the floating point library.

cosh

NAME

cosh - hyperbolic cosine

SYNOPSIS

FUNCTION

 \boldsymbol{cosh} computes the hyperbolic cosine of $\underline{\boldsymbol{x}}$ to full double precision.

RETURNS

 \cosh returns the nearest internal representation to $\cosh(x)$ expressed as a double floating value. If the result is too large to be properly represented, \cosh returns zero.

EXAMPLE

To use de Moivre's theorem to compute (cosh x + sinh x) to the nth power:

demoivre = cosh(n * x) + sinh(n * x);

SEE ALSO

exp, sinh, tanh

NOTES

cosh is packaged in the floating point library.

WANT.	
NAME	exp - exponential
SYNOPSIS	<pre>#include <math.h> double exp(x) double x;</math.h></pre>
FUNCTION	exp computes the exponential of \underline{x} to full double precision.
RETURNS	exp returns the nearest internal representation to exp x , expressed as a double floating value. If the result is too large to be properly represented, exp returns zero.
EXAMPLE	To compute the hyperbolic sine of x : $sinh = (exp(x) - exp(-x)) / 2.\overline{0}$;
SEE ALSO	log

 $\ensuremath{\mathbf{exp}}$ is packaged in the floating point library.

NOTES

NAME	
NAME	fabs - find double absolute value
SYNOPSIS	<pre>#include <math.h> double fabs(x) double x;</math.h></pre>
FUNCTION	fabs obtains the absolute value of x .
RETURNS	fabs returns the absolute value of \underline{x} , expressed as a double floating value.
EXAMPLE	x fabs(x) 5.0 5.0 0.0 0.0 -3.7 3.7
SEE ALSO	abs
NOTES	fabs is packaged in the floating point library.

floor - round to next lower integer

SYNOPSIS

FUNCTION

floor computes the largest integer less than or equal to x.

RETURNS

floor returns the largest integer less than or equal to \underline{x} , expressed as a double floating value.

EXAMPLE

x floor(x)
5.1 5.0
5.0 5.0
0.0 0.0
-5.0 -5.0
-5.1 -6.0

SEE ALSO

ceil

NOTES

floor is packaged in the floating point library.

free - free space on the heap

SYNOPSIS

#include <stdlib.h>
void free(ptr)
 void *ptr;

FUNCTION

free returns an allocated cell to the heap for subsequent reuse. The cell pointer ptr must have been obtained by an earlier calloc, malloc, or realloc call; otherwise the heap will become corrupted. free does its best to check for invalid values of ptr. A NULL value for ptr is explicitly allowed, however, and is ignored.

RETURNS

Nothing.

EXAMPLE

To give back an allocated area: free(pd);

SEE ALSO

calloc, malloc, realloc

NOTES

No effort is made to lower the system break when storage is freed, so it is quite possible that earlier activity on the heap may cause problems later on the stack.

free is packaged in the integer library.

getchar - get character from input stream

SYNOPSIS

#include <stdio.h>
int getchar()

FUNCTION

getchar obtains the next input character, if any, from the user supplied input stream. This user must rewrite this function in C or in assembly language to provide an interface to the input mechanism of the C library.

RETURNS

getchar returns the next character from the input stream. If end of file (break) is encountered, or a read error occurs, getchar returns EOF.

EXAMPLE

To copy characters from the input stream to the output stream: while ((c = getchar()) != EOF)
putchar(c);

SEE ALSO

getc, putchar

NOTES

getchar is packaged in the integer library.

gets - get a text line from input stream

SYNOPSIS

FUNCTION

gets copies characters from the input stream to the buffer starting at \underline{s} . Characters are copied until a newline is reached or end of file is reached. If a newline is reached, it is discarded and a NUL is written immediately following the last character read into s.

gets uses getchar to read each character.

RETURNS

gets returns s if successful. If end of file is reached, gets
returns NULL. If a read error occurs, the array contents are
indeterminate and gets returns NULL.

EXAMPLE

To copy input to output, line by line:
 while (puts(gets(buf)))
;

SEE ALSO

puts

NOTES

There is no assured limit on the size of the line read by gets. gets is packaged in the integer library.

isalnum - test for alphabetic or numeric character

SYNOPSIS

/* no header file need be included */
int isalnum(c)
 int c;

FUNCTION

isalnum tests whether \underline{c} is an alphabetic character (either upper or lower case), or \overline{a} decimal digit.

RETURNS

isalnum returns nonzero if the argument is an alphabetic or numeric character; otherwise the value returned is zero.

EXAMPLE

To test for a valid C identifier:
if (isalpha(*s) || *s == ' ')
for (++s; isalnum(*s) || *s == '_'; ++s)
;

SEE ALSO

isalpha, isdigit, islower, isupper, isxdigit, tolower, toupper

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

isalnum is packaged in the integer library.

NAME	isalpha - test for alphabetic character			
SYNOPSIS	<pre>/* no header file need be included */ int isalpha(c) int c;</pre>			
FUNCTION	isalpha tests whether <u>c</u> is an alphabetic character, either upper or lower case.			
RETURNS	isalpha returns nonzero if the argument is an alphabetic character. Otherwise the value returned is zero.			
EXAMPLE	To find the end points of an alphabetic string: while (*first && !isalpha(*first)) ++first; for (last = first; isalpha(*last); ++last) ;			
SEE ALSO	isalnum, isdigit, islower, isupper, isxdigit, tolower, toupper			
NOTES	If the argument is outside the range [-1, 255], the result is undefined.			
	isalpha is packaged in the integer library.			

iscntrl - test for control character

SYNOPSIS

/* no header file need be included */
int iscntrl(c)
 int c;

FUNCTION

iscntrl tests whether \underline{c} is a delete character (0177 in ASCII), or an ordinary control character (less than 040 in ASCII).

RETURNS

iscntrl returns nonzero if \underline{c} is a control character; otherwise the value is zero.

EXAMPLE

To map control characters to percent signs:
 for (; *s; ++s)
 if (iscntrl(*s))
 *s = '%';

SEE ALSO

isgraph, isprint, ispunct, isspace

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

iscntrl is packaged in the integer library.

1741/77	
NAME	isdigit - test for digit
SYNOPSIS	<pre>/* no header file need be included */ int isdigit(c) int c;</pre>
FUNCTION	isdigit tests whether <u>c</u> is a decimal digit.
RETURNS	isdigit returns nonzero if c is a decimal digit; otherwise the value returned is zero.
EXAMPLE	To convert a decimal digit string to a number: for (sum = 0; isdigit(*s); ++s) sum = sum * 10 + *s - '0';
SEE ALSO	isalnum, isalpha, islower, isupper, isxdigit, tolower, toupper
NOTES	If the argument is outside the range [-1, 255], the result is undefined.
	isdigit is packaged in the integer library.

isgraph - test for graphic character

SYNOPSIS

/* no header file need be included */
int isgraph(c)
 int c;

FUNCTION

isgraph tests whether \underline{c} is a graphic character; i.e. any printing character except \overline{a} space (040 in ASCII).

RETURNS

isgraph returns nonzero if \underline{c} is a graphic character. Otherwise the value returned is zero.

EXAMPLE

To output only graphic characters:
for (; *s; ++s)
if (isgraph(*s))
putchar(*s);

SEE ALSO

iscntrl, isprint, ispunct, isspace

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

isgraph is packaged in the integer library.

NAME	
NAME	islower - test for lowercase character
SYNOPSIS	<pre>/* no header file need be included */ int islower(c) int c;</pre>
FUNCTION	islower tests whether \underline{c} is a lowercase alphabetic character.
RETURNS	islower returns nonzero if \underline{c} is a lowercase character; otherwise the value returned is zero.
EXAMPLE	To convert to uppercase: if (islower(c)) C += 'A' - 'a'; /* also see toupper() */
SEE ALSO	isalnum, isalpha, isdigit, isupper, isxdigit, tolower, toupper
NOTES	If the argument is outside the range [-1, 255], the result is undefined.
	islower is packaged in the integer library.

isprint - test for printing character

SYNOPSIS

/* no header file need be included */
int isprint(c)
 int c;

FUNCTION

isprint tests whether \underline{c} is any printing character. Printing characters are all characters between a space (040 in ASCII) and a tilde '~' character (0176 in ASCII).

RETURNS

isprint returns nonzero if \underline{c} is a printing character; otherwise the value returned is zero.

EXAMPLE

To output only printable characters:
 for (; *s; ++s)
 if (isprint(*s))
 putchar(*s);

SEE ALSO

iscntrl, isgraph, ispunct, isspace

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

isprint is packaged in the integer library.

ispunct - test for punctuation character

SYNOPSIS

/* no header file need be included */
int ispunct(c)
 int c;

FUNCTION

ispunct tests whether \underline{c} is a punctuation character. Punctuation characters include any printing character except space, a digit, or a letter.

RETURNS

ispunct returns nonzero if \underline{c} is a punctuation character; otherwise the value returned is zero.

EXAMPLE

To collect all punctuation characters in a string into a buffer:
for (i = 0; *s; ++s)
if (ispunct(*s))
buf[i++] = *s;

SEE ALSO

iscntrl, isgraph, isprint, isspace

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

ispunct is packaged in the integer library.

isspace - test for whitespace character

SYNOPSIS

/* no header file need be included */
int isspace(c)
 int c;

FUNCTION

isspace tests whether \underline{c} is a whitespace character. Whitespace characters are horizontal tab ('\t'), newline ('\n'), vertical tab ('\v'), form feed ('\f'), carriage return ('\r'), and space ('').

RETURNS

isspace returns nonzero if \underline{c} is a whitespace character; otherwise the value returned is \overline{z} ero.

EXAMPLE

To skip leading whitespace:
while (isspace(*s))
++s;

SEE ALSO

isentrl, isgraph, isprint, ispunct

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

isspace is packaged in the integer library.

NAME	isupper - test for uppercase character			
SYNOPSIS	<pre>/* no header file need be included */ int isupper(c) int c;</pre>			
FUNCTION	isupper tests whether \underline{c} is an uppercase alphabetic character.			
RETURNS	isupper returns nonzero if \underline{c} is an uppercase character; otherwise the value returned is \overline{z} ero.			
EXAMPLE	To convert to lowercase: if (isupper(c)) c += 'a' - 'A'; /* also see tolower() */			
SEE ALSO	isalnum, isalpha, isdigit, islower, isxdigit, tolower, toupper			
NOTES	If the argument is outside the range [-1, 255], the result is undefined.			
	isupper is packaged in the integer library.			

NAME	isxdigit - test for hexadecimal digit				
SYNOPSIS	<pre>/* no header file need be included */ int isxdigit(c) int c;</pre>				
FUNCTION	isxdigit tests whether c is a hexadecimal digit, i.e. in the set $[0123456789abcdefABCDE\overline{F}]$.				
RETURNS	isxdigit returns nonzero if \underline{c} is a hexadecimal digit; otherwise the value returned is zero.				
EXAMPLE	To accumulate a hexadecimal digit: for (sum = 0; isxdigit(*s); ++s) if (isdigit(*s) sum = sum * 10 + *s - '0'; else sum = sum * 10 + tolower(*s) + (10 - 'a');				

SEE ALSO

isalnum, isalpha, isdigit, islower, isupper, tolower, toupper

NOTES

If the argument is outside the range [-1, 255], the result is undefined.

isxdigit is packaged in the integer library.

log - natural logarithm

SYNOPSIS

FUNCTION

 \log computes the natural logarithm of \underline{x} to full double precision.

RETURNS

 \log returns the closest internal representation to $\log(x)$, expressed as a double floating value. If the input argument is less than zero, or is too large to be represented, \log returns zero.

EXAMPLE

To compute the hyperbolic arccosine of x: arccosh = log(x + sqrt(x * x - 1));

SEE ALSO

exp

NOTES

log is packaged in the floating point library.

log10 - common logarithm

SYNOPSIS

FUNCTION

log10 computes the common log of x to full double precision by computing the natural log of x divided by the natural log of 10. If the input argument is less than zero, a domain error will occur. If the input argument is zero, a range error will occur.

RETURNS

log10 returns the nearest internal representation to $log10 \times ,$ expressed as a double floating value. If the input argument is less than or equal to zero, log10 returns zero.

EXAMPLE

To determine the number of digits in x, where x is a positive integer expressed as a double:
 ndig = log10(x) + 1;

SEE ALSO

log

NOTES

log10 is packaged in the floating point library.

longjmp - restore calling environment

SYNOPSIS

```
#include <setjmp.h>
void longjmp(env, val)
    jmp_buf env;
    int val;
```

FUNCTION

longjmp restores the environment saved in env by setjmp. If env has not been set by a call to setjmp, or if the caller has returned in the meantime, the resulting behavior is unpredictable.

All accessible objects have their values restored when longjmp is called, except for objects of storage class register, the values of which have been changed between the setjmp and longjmp calls.

RETURNS

When longjmp returns, program execution continues as if the corresponding call to setjmp had returned the value val. longjmp cannot force setjmp to return the value zero. If $\frac{\text{val}}{\text{is zero}}$, setjmp returns the value one.

EXAMPLE

```
You can write a generic error handler as:
void handle(err)
   int err;
   {
   extern jmp_buf env;

   longjmp(env, err); /* return from setjmp */
}
```

SEE ALSO

setjmp

NOTES

longjmp is packaged in the integer library.

malloc - allocate space on the heap

SYNOPSIS

#include <stdlib.h>
void *malloc(nybytes)
 unsigned int nbytes;

FUNCTION

malloc allocates space on the heap for an item of size <u>nbytes</u>. The space allocated is guaranteed to be at least <u>nbytes</u> long, starting from the pointer returned, which is guaranteed to be on a proper storage boundary for an object of any type. The heap is grown as necessary. If space is exhausted, malloc returns a null pointer.

RETURNS

malloc returns a pointer to the start of the allocated cell if successful; otherwise it returns NULL. The pointer returned may be assigned to an object of any type without casting.

EXAMPLE

To allocate an array of ten doubles: double *pd;

pd = malloc(10 * sizeof *pd);

SEE ALSO

calloc, free, realloc

NOTES

malloc is packaged in the integer library.

max - test for maximum

SYNOPSIS

#include <stdlib.h>
max(a, b)

FUNCTION

max obtains the maximum of its two arguments, \underline{a} and \underline{b} . Since max is implemented as a C preprocessor macro, \overline{i} ts arguments can be any numerical type, and type coercion occurs automatically.

RETURNS

max is a numerical rvalue of the form ((a < b) ? b : a), suitably parenthesized.

EXAMPLE

To set a new maximum level: hiwater = max(hiwater, level);

SEE ALSO

min

NOTES

max is an extension to the proposed ANSI C standard.

max is a macro declared in the **<stdlib.h>** header file. You can use it by including **<stdlib.h>** with your program. Because it is a macro, max cannot be called from non-C programs, nor can its address be taken. Arguments with side effects may be evaluated other than once.

NAME	
	memchr - scan buffer for character
SYNOPSIS	<pre>#include <string.h> void *memchr(s, c, n) const void *s; int c; unsigned int n;</string.h></pre>
FUNCTION	memchr looks for the first occurrence of a specific character \underline{c} in an \underline{n} character buffer starting at \underline{s} .
RETURNS	memchr returns a pointer to the first character that matches \underline{c} , or NULL if no character matches.
EXAMPLE	To map keybuf[] characters into subst[] characters: if ((t = memchr(keybuf, *s, KEYSIZ)) != NULL) *s = subst[t - keybuf];
SEE ALSO	strchr, strcspn, strpbrk, strrchr, strspn
NOTES	memchr is packaged in the integer library.

Using The Compiler

memcmp

NAME

memcmp - compare two buffers for lexical order

SYNOPSIS

#include <string.h>
int memcmp(s1, s2, n)
 const void *s1, *s2;
 unsigned int n;

FUNCTION

memcmp compares two text buffers, character by character, for lexical order in the character collating sequence. The first buffer starts at $\underline{s1}$, the second at $\underline{s2}$; both buffers are \underline{n} characters long.

RETURNS

memcmp returns a short integer greater than, equal to, or less than zero, according to whether $\underline{s1}$ is lexicographically greater than, equal to, or less than $\underline{s2}$.

EXAMPLE

To look for the string "include" in name:
if (memcmp(name, "include", 7) == 0)
doinclude();

SEE ALSO

strcmp, strncmp

NOTES

memcmp is packaged in the integer library.

NAME	memcpy - copy one buffer to another
SYNOPSIS	
	<pre>#include <string.h> void *memcpy(s1, s2, n) void *s1; const void *s2; unsigned int n;</string.h></pre>
FUNCTION	
	memcpy copies the first <u>n</u> characters starting at location $\underline{s2}$ into the buffer beginning at $\underline{s1}$.
RETURNS	moments we think a safe
	memcpy returns s1.
EXAMPLE	
	To place "first string, second string" in buf[]:
	<pre>memcpy(buf, "first string", 12); memcpy(buf + 13, ", second string", 15);</pre>
SEE ALSO	
	strepy, strnepy

memcpy is packaged in the integer library.

NOTES

NAME	memset - propagate fill character throughout buffer
SYNOPSIS	<pre>#include <string.h> void *memset(s, c, n) void *s; int c; unsigned int n;</string.h></pre>
FUNCTION	memset floods the <u>n</u> character buffer starting at \underline{s} with fill character \underline{c} .
RETURNS	memset returns s.
EXAMPLE	To flood a 512-byte buffer with NULs: memset(buf,'\0', BUFSIZ);
NOTES	memset is packaged in the integer library.

min - test for minimum

SYNOPSIS

#include <stdlib.h>
min(a, b)

FUNCTION

min obtains the minimum of its two arguments, \underline{a} and \underline{b} . Since **min** is implemented as a C preprocessor macro, its arguments can be any numerical type, and type coercion occurs automatically.

RETURNS

min is a numerical rvalue of the form ((a < \underline{b}) ? \underline{a} : \underline{b}), suitably parenthesized.

EXAMPLE

To set a new minimum level: nmove = min(space, size);

SEE ALSO

max

NOTES

min is an extension to the proposed ANSI C standard.

min is a macro declared in the <stdlib.h> header file. You can use it by including <stdlib.h> with your program. Because it is a macro, min cannot be called from non-C programs, nor can its address be taken. Arguments with side effects may be evaluated more than once.

pow - raise x to the y power

SYNOPSIS

FUNCTION

pow computes the value of \underline{x} raised to the power of y.

RETURNS

pow returns the value of \underline{x} raised to the power of \underline{y} , expressed as a double floating value. If \underline{x} is zero and \underline{y} is less than or equal to zero, or if \underline{x} is negative and \underline{y} is not an integer, pow returns zero.

EXAMPLE				
	х	У	pow(x, y)	
	2.0	2.0	4.0	
	2.0	1.0	2.0	
	2.0	0.0	1.0	
	1.0	any	1.0	
	0.0	-2.0	0	
	-1.0	2.0	1.0	

2.1

SEE ALSO

exp

-1.0

NOTES

pow is packaged in the floating point library.

0

printf - output formatted arguments to stdout

SYNOPSIS

#include <stdio.h>
int printf(fmt, ...)
 const char *fmt;

FUNCTION

printf writes formatted output to the output stream using the format string at $\underline{\text{fmt}}$ and the arguments specified by $\underline{\dots}$, as described below.

printf uses putchar to output each character.

Format Specifiers

The format string at fmt consists of literal text to be output, interspersed with conversion specifications that determine how the arguments are to be interpreted and how they are to be converted for output. If there are insufficient arguments for the format, the results are undefined. If the format is exhausted while arguments remain, the excess arguments are evaluated but otherwise ignored. printf returns when the end of the format string is encountered.

Each <conversion specification> is started by the character '%'. After the '%', the following appear in sequence:

<flags> - zero or more which modify the meaning of the
 conversion specification.

<field width> - a decimal number which optionally
 specifies a minimum field width. If the converted
 value has fewer characters than the field width, it
 is padded on the left (or right, if the left adjust ment flag has been given) to the field width. The
 padding is with spaces unless the field width digit
 string starts with zero, in which case the padding is
 with zeros.

precision takes the form of a period followed by a decimal digit string. A null digit string is treated as zero.

- h optionally specifies that the following d, i, o, u, x, or X conversion character applies to a short int or unsigned short int argument (the argument will have been widened according to the integral widening conversions, and its value must be cast to short or unsigned short before printing). It specifies a short pointer argument if associated with the p conversion character. If an h appears with any other conversion character, it is ignored.
- optionally specifies that the d, i, o, u, x, and X conversion character applies to a long int or unsigned long int argument. It specifies a long or far pointer argument if used with the p conversion character. If the l appears with any other conversion character, it is ignored.
- L optionally specifies that the following e, E, f, g, and G conversion character applies to a long double argument. If the L appears with any other conversion character, it is ignored.

<conversion character> - character that indicates the type
 of conversion to be applied.

A field width or precision, or both, may be indicated by an asterisk '*' instead of a digit string. In this case, an int argument supplies the field width or precision. The arguments supplying field width must appear before the optional argument to be converted. A negative field width argument is taken as a - flag followed by a positive field width. A negative precision argument is taken as if it were missing.

The <flags> field is zero or more of the following:

- space a space will be prepended if the first character
 of a signed conversion is not a sign. This flag will
 be ignored if space and + flags are both specified.
- # result is to be converted to an "alternate form".

 For c, d, i, s, and u conversions, the flag has no effect. For o conversion, it increases the precision to force the first digit of the result to be zero. For p, x and X conversion, a non-zero result will have 0x or 0X prepended to it. For e, E, f, g, and G conversions, the result will contain a decimal point, even if no digits follow the point. For g and G conversions, trailing zeros will not be removed from the result, as they normally are. For p conversion, it

designates hexadecimal output.

- result of signed conversion will begin with a plus or minus sign.
- result of conversion will be left justified within the field.

The <conversion character> is one of the following:

- % a '%' is printed. No argument is converted.
- c the least significant byte of the <u>int</u> argument is converted to a character and printed.
- d, i, o, u, x, X the int argument is converted to signed decimal (d or i), unsigned octal (o), unsigned decimal (u), or unsigned hexadecimal notation (x or X); the letters abcdef are used for x conversion and the letters ABCDEF are used for X conversion. The precision specifies the minimum number of digits to appear; if the value being converted can be represented in fewer digits, it will be expanded with leading zeros. The default precision is 1. The result of converting a zero value with precision of zero is no characters.
- e, E the double argument is converted in the style [-]d.ddde+dd, where there is one digit before the decimal point and the number of digits after it is equal to the precision. If the precision is missing, six digits are produced; if the precision is zero, no decimal point appears. The E format code will produce a number with E instead of e introducing the exponent. The exponent always contains at least two digits. However, if the magnitude to be printed is greater than or equal to 1E+100, additional exponent digits will be printed as necessary.
- f the <u>double</u> argument is converted to decimal notation in the style [-]ddd.ddd, where the number of digits following the decimal point is equal to the precision specification. If the precision is missing, it is taken as 6. If the precision is explicitly zero, no decimal point appears. If a decimal point appears, at least one digit appears before it.
- g, G the <u>double</u> argument is printed in style f or e (or in style E in the case of a G format code), with the precision specifying the number of significant digits. The style used depends on the value converted; style e will be used only if the exponent resulting from the conversion is less than -4 or

greater than the precision. Trailing zeros are removed from the result; a decimal point appears only if it is followed by a digit.

- n the argument is taken to be an <u>int</u> * pointer to an integer into which is written the <u>number</u> of characters written to the output stream so far by this call to printf. No argument is converted.
- p the argument is taken to be a void * pointer to an object. The value of the pointer is converted to a sequence of printable characters, and printed as a hexadecimal number with the number of digits printed being determined by the field width.
- s the argument is taken to be a char * pointer to a string. Characters from the string are written up to, but not including, the terminating NUL, or until the number of characters indicated by the precision are written. If the precision is missing, it is taken to be arbitrarily large, so all characters before the first NUL are printed.

If the character after '%' is not a valid conversion character, the behavior is undefined.

If any argument is or points to an aggregate (except for an array of characters using %s conversion or any pointer using %p conversion), unpredictable results will occur.

A nonexistent or small field width does not cause truncation of a field; if the result is wider than the field width, the field is expanded to contain the conversion result.

RETURNS

printf returns the number of characters transmitted, or a negative number if a write error occurs.

NOTES

A call with more conversion specifiers than argument variables will cause unpredictable results.

EXAMPLE

To print arg, which is a double with the value 5100.53:

printf("%08.2f\n", arg);
printf("%*.*f\n", 08, 2, arg);

both forms will output:

05100.53

SEE ALSO

sprintf

NOTES

printf is packaged in both the integer library and the floating point library. The functionality of the integer only version of printf is a subset of the functionality of the floating point version. The integer only version cannot print or manipulate floating point numbers. If your programs call the integer only version of printf, the following conversion specifiers are invalid: e, E, f, g and G. The L modifier is also invalid.

If printf encounters an invalid conversion specifier, the invalid specifier is ignored and no special message is generated.

Using The Compiler putchar

NAME	putchar - put a character to output stream
SYNOPSIS	<pre>#include <stdio.h> int putchar(c) char c;</stdio.h></pre>
FUNCTION	putchar copies c to the user specified output stream.
	You must rewrite putchar in either C or assembly language to provide an interface to the output mechanism to the C library.
RETURNS	<pre>putchar returns c. If a write error occurs, putchar returns EOF.</pre>
EXAMPLE	To copy input to output: while ((c = getchar()) != EOF) putchar(c);
SEE ALSO	pute
NOTES	mutchen is nealessed in the internal library

putchar is packaged in the integer library.

Using The Compiler

puts

NAME	<pre>puts - put a text line to output stream</pre>
SYNOPSIS	<pre>#include <stdio.h> int puts(s) const char *s;</stdio.h></pre>
FUNCTION	<pre>puts copies characters from the buffer starting at s to the output stream and appends a newline character to the output stream.</pre>
	<pre>puts uses putchar to output each character. The terminating NUL is not copied.</pre>
RETURNS	<pre>puts returns zero if successful, or else nonzero if a write er- ror occurs.</pre>
EXAMPLE	To copy input to output, line by line: while (puts(gets(buf)));
SEE ALSO	gets
NOTES	puts is packaged in the integer library.

Using The Compiler

rand

NAME

rand - generate pseudo-random number

SYNOPSIS

#include <stdlib.h>
int rand()

FUNCTION

rand computes successive pseudo-random integers in the range [0, 32767], using a linear multiplicative algorithm which has a period of 2 raised to the power of 32.

EXAMPLE

```
int dice()
    {
    return (rand() % 6 + 1);
}
```

RETURNS

rand returns a pseudo-random integer.

SEE ALSO

srand

NOTES

rand is packaged in the integer library.

realloc - reallocate space on the heap

SYNOPSIS

#include <stdlib.h>
void *realloc(ptr, nbytes)
 void *ptr;
 unsigned int nbytes;

FUNCTION

realloc grows or shrinks the size of the cell pointed to by ptr to the size specified by nbytes. The contents of the cell will be unchanged up to the lesser of the new and old sizes. The cell pointer ptr must have been obtained by an earlier calloc, malloc, or realloc call; otherwise the heap will become corrupted.

RETURNS

realloc returns a pointer to the start of the possibly moved cell if successful. Otherwise realloc returns NULL and the cell and ptr are unchanged. The pointer returned may be assigned to an object of any type without casting.

EXAMPLE

To adjust p to be n doubles in size: p = realloc(p, n * sizeof(double));

SEE ALSO

calloc, free, malloc

NOTES

realloc is packaged in the integer library.

sbreak - allocate new memory

SYNOPSIS

/* no header file need be included */
void *sbreak(size)
 unsigned int size;

FUNCTION

sbreak modifies the program memory allocation as necessary, to make available at least <u>size</u> contiguous bytes of new memory, on a storage boundary adequate for representing any type of data. There is no guarantee that successive calls to **sbreak** will deliver contiguous areas of memory.

RETURNS

sbreak returns a pointer to the start of the new memory if successful; otherwise the value returned is NULL.

EXAMPLE

To buy space for an array of symbols:
if (!(p = sbreak(nsyms * sizeof (symbol))))
 remark("not enough memory!", NULL);

NOTES

sbreak is packaged in the integer library.

sbreak is an extension to the proposed ANSI C standard.

scanf - read formatted input

SYNOPSIS

#include <stdio.h>
int scanf(fmt, ...)
 const char *fmt;

FUNCTION

scanf reads formatted input from the output stream using the format string at $\underline{\text{fmt}}$ and the arguments specified by $\underline{\dots}$, as described below.

scanf uses getchar to read each character.

The behavior is unpredictable if there are insufficient argument pointers for the format. If the format string is exhausted while arguments remain, the excess arguments are evaluated but otherwise ignored.

Format Specifiers

The format string may contain:

- Any number of spaces, horizontal tabs, and newline characters which cause input to be read up to the next non-whitespace character, and
- o Ordinary characters other than '%' which must match the next character of the input stream.

Each <a href="mailto:conversio

A conversion specification directs the conversion of the next input field. The result is placed in the object pointed to by the subsequent argument, unless assignment suppression was indicated by a '*'. An input field is a string of non-space characters; it extends to the next conflicting character or until the field width, if specified, is exhausted.

The conversion specification indicates the interpretation of the input field; the corresponding pointer argument must be a restricted type. The <conversion character> is

one of the following:

% - a single % is expected in the input at this point; no assignment occurs.

If the character after '%' is not a valid conversion character, the behavior is undefined.

- c a character is expected; the subsequent argument must be of type pointer to char. The normal behavior (skip over space characters) is suppressed in this case; to read the next non-space character, use %1s. If a field width is specified, the corresponding argument must refer to a character array; the indicated number of characters is read.
- d a decimal integer is expected; the subsequent argument must be a pointer to integer.
- e, f, g a float is expected; the subsequent argument must be a pointer to float. The input format for floating point numbers is an optionally signed sequence of digits, possibly containing a decimal point, followed by an optional exponent field consisting of an E or e, followed by an optionally signed integer.
- i an integer is expected; the subsequent argument must be a pointer to integer. If the input field begins with the characters Ox or OX, the field is taken as a hexadecimal integer. If the input field begins with the character O, the field is taken as an octal integer. Otherwise, the input field is taken as a decimal integer.
- n no input is consumed; the subsequent argument must be an int * pointer to an integer into which is written the number of characters read from the input stream so far by this call to scanf.
- an octal integer is expected; the subsequent argument must be a pointer to integer.
- p a pointer is expected; the subsequent argument must be a void * pointer. The format of the input field should be the same as that produced by the %p conversion of printf. On any input other than a value printed earlier during the same program execution, the behavior of the %p conversion is undefined.
- s a character string is expected; the subsequent argument must be a char *pointer to an array large enough to hold the string and a terminating NUL, which will be added automatically. The input field

is terminated by a space, a horizontal tab, or a newline, which is not part of the field.

- an unsigned decimal integer is expected; the subsequent argument must be a pointer to integer.
- x a hexadecimal integer is expected; a subsequent argument must be a pointer to integer.
 - a string that is not to be delimited by spaces is expected; the subsequent argument must be a char * just as for %s. The left bracket is followed by a set of characters and a right bracket; the characters between the brackets define a set of characters making up the string. If the first character is not a circumflex ''', the input field consists of all characters up to the first character that is not in the set between the brackets; if the first character after the left bracket is a circumflex, the input field consists of all characters up to the first character that is in the set of the remaining characters between the brackets. A NUL character will be appended to the input.

The conversion characters d, i, o, u and x may be preceded by l to indicate that the subsequent argument is a pointer to long int rather than a pointer to int, or by h to indicate that it is a pointer to short int. Similarly, the conversion characters e and f may be preceded by l to indicate that the subsequent argument is a pointer to double rather than a pointer to float, or by L to indicate a pointer to long double.

The conversion characters **e**, **g** or **x** may be capitalized. However, the use of upper case has no effect on the conversion process and both upper and lower case input is accepted.

If conversion terminates on a conflicting input character, that character is left unread in the input stream. Trailing white space (including a newline) is left unread unless matched in the control string. The success of literal matches and suppressed assignments is not directly determinable other than via the %n conversion.

RETURNS

scanf returns the number of assigned input items, which can be zero if there is an early conflict between an input character and the format, or EOF if end of file is encountered before the first conflict or conversion.

EXAMPLE

To be certain of a dubious request:

SEE ALSO

sscanf

NOTES

scanf is packaged in both the integer library and the floating point library. The functionality of the integer only version of scanf is a subset of the functionality of the floating point version. The integer only version cannot read or manipulate floating point numbers. If your programs call the integer only version of scanf, the following conversion specifiers are invalid: e, f, g and p. The L flag is also invalid.

If an invalid conversion specifier is encountered, it is ignored.

setjmp - save calling environment

SYNOPSIS

#include <setjmp.h>
int setjmp(env)
 jmp_buf env;

FUNCTION

setjmp saves the calling environment in <u>env</u> for later use by the longjmp function.

Since **setjmp** manipulates the stack, it should never be used except as the single operand in a switch statement.

RETURNS

setjmp returns zero on its initial call, or the argument to a longjmp call that uses the same env.

EXAMPLE

To call anyevent until it returns 0 or 1 and calls longjmp, which will then start execution at the function event0 or event1:

```
static jmp_buf ev[2];
switch (setjmp(ev[0]))
case 0:
                 /* registered */
        break;
default:
                 /* event 0 occurred */
        event0();
        next();
switch (setjmp(ev[1])
    {
    case 0:
                     /* registered */
        break;
    default:
                     /* event 1 occurred */
        event1();
        next();
next();
next()
    int i;
    for (; ;)
        i = anyevent();
```

setjmp

SEE ALSO

longjmp

NOTES

setjmp is packaged in the integer library.

sin - sine

SYNOPSIS

#include <math.h>
double sin(x)
 double x;

FUNCTION

 \sin computes the sine of x, expressed in radians, to full double precision. If the magnitude of x is too large to contain a fractional quadrant part, the value of \sin is 0.

RETURNS

 \sin returns the closest internal representation to $\sin(x)$ in the range [-pi/2, pi/2], expressed as a double floating value. A large argument may return a meaningless result.

EXAMPLE

To rotate a vector through the angle theta: xnew = xold * cos(theta) - yold * sin(theta); ynew = xold * sin(theta) + yold * cos(theta);

SEE ALSO

cos, tan

NOTES

sin is packaged in the floating point library.

sinh

Using The Compiler

NAME

sinh - hyperbolic sine

SYNOPSIS

FUNCTION

sinh computes the hyperbolic sine of \underline{x} to full double precision.

RETURNS

sinh returns the closest internal representation to sinh(x), expressed as a double floating value. If the result is too large to be properly represented, sinh returns zero.

EXAMPLE

SEE ALSO

cosh, exp, tanh

NOTES

sinh is packaged in the floating point library.

sprintf

NAME

sprintf - output arguments formatted to buffer

SYNOPSIS

#include <stdio.h>
int sprintf(s, fmt, ...)
 char *s;
 const char *fmt;

FUNCTION

sprintf writes formatted to the buffer pointed at by <u>s</u> using the format string at <u>fmt</u> and the arguments specified by ..., in exactly the same way as printf. See the description of the printf function for information on the format conversion specifiers. A NUL character is written after the last character in the buffer.

RETURNS

sprintf returns the numbers of characters written, not including the terminating NUL character.

EXAMPLE

To format a double at d into buf: sprintf(buf, "%10f\n", d);

SEE ALSO

printf

NOTES

sprintf is packaged in both the integer library and the floating point library. The functionality of the integer only version of sprintf is a subset of the functionality of the floating point version. The integer only version cannot print or manipulate floating point numbers. If your programs call the integer only version of sprintf, the following conversion specifiers are invalid: e, E, f, g and G. The L flag is also invalid.

sqrt - real square root

SYNOPSIS

FUNCTION

sqrt computes the square root of \underline{x} to full double precision.

RETURNS

sqrt returns the nearest internal representation to sqrt(x), expressed as a double floating value. If \underline{x} is negative, sqrt returns zero.

EXAMPLE

```
To use sqrt to check whether n > 2 is a prime number:
if (!(n & 01))
    return (NOTPRIME);
sq = sqrt((double)n);
for (div = 3; div <= sq; div += 2)
    if (!(n % div))
        return (NOTPRIME);
return (PRIME);</pre>
```

NOTES

sqrt is packaged in the floating point library.

srand - seed pseudo-random number generator

SYNOPSIS

#include <stdlib.h>
void srand(nseed)
 unsigned char nseed;

FUNCTION

srand uses nseed as a seed for a new sequence of pseudo-random
numbers to be returned by subsequent calls to rand. If srand
is called with the same seed value, the sequence of pseudo-random numbers will be repeated. The initial seed value used by
rand and srand is 0.

RETURNS

Nothing.

EXAMPLE

To set up a new sequence of random numbers: srand(103);

SEE ALSO

rand

NOTES

srand is packaged in the integer library.

sscanf - read formatted input from a string

SYNOPSIS

#include <stdio.h>
int sscanf(s, fmt, ...)
 char *s;
 const char *fmt;

FUNCTION

sscanf reads formatted input from the NUL-terminated string pointed at by \underline{s} using the format string at \underline{fmt} and the arguments specified by \ldots , in exactly the same way as scanf. See the description of the scanf function for information on the format conversion specifiers.

RETURNS

sscanf returns the number of assigned input items, which can be zero if there is an early conflict between an input character and the format, or EOF if the end of the string is encountered before the first conflict or conversion.

SEE ALSO

scanf

NOTES

sscanf is packaged in both the integer library and the floating point library. The functionality of the integer only version of sscanf is a subset of the functionality of the floating point version. The integer only version cannot print or manipulate floating point numbers. If your programs call the integer only version of sscanf, the following conversion specifiers are invalid: e, f, g and p. The L flag is also invalid.

strcat

NAME

strcat - concatenate strings

SYNOPSIS

FUNCTION

strcat appends a copy of the NUL terminated string at $\underline{s2}$ to the end of the NUL terminated string at $\underline{s1}$. The first character of $\underline{s2}$ overlaps the NUL at the end of $\underline{s1}$. A terminating NUL is always appended to $\underline{s1}$.

RETURNS

strcat returns s1.

EXAMPLE

To place the strings "first string, second string" in buf[]:
 buf[0] = '\0';
 strcpy(buf, "first string");
 strcat(buf, ", second string");

SEE ALSO

strncat

NOTES

There is no way to specify the size of the destination area to prevent storage overwrites.

strcat is packaged in the integer library.

strchr

Using The Compiler

NOTES

NAME	strchr - scan string for first occurrence of character
SYNOPSIS	<pre>#include <string.h> char *strchr(s, c) const char *s; int c;</string.h></pre>
FUNCTION	strchr looks for the first occurrence of a specific character \underline{c} in a NUL terminated target string \underline{s} .
RETURNS	strchr returns a pointer to the first character that matches c, or NULL if none does.
EXAMPLE	To map keystr[] characters into subst[] characters: if (t = strchr(keystr, *s)) *s = subst[t - keystr];
SEE ALSO	memchr, strcspn, strpbrk, strrchr, strspn

strchr is packaged in the integer library.

strcmp

374367
NAME

strcmp - compare two strings for lexical order

SYNOPSIS

#include <string.h>
int strcmp(s1, s2)
 const char *s1, *s2;

FUNCTION

strcmp compares two text strings, character by character, for lexical order in the character collating sequence. The first string starts at $\underline{s1}$, the second at $\underline{s2}$. The strings must match, including their terminating NUL characters, in order for them to be equal.

RETURNS

strcmp returns an integer greater than, equal to, or less than zero, according to whether $\underline{s1}$ is lexicographically greater than, equal to, or less than $\underline{s2}$.

EXAMPLE

To look for the string "include":

if (strcmp(buf, "include") == 0)
 doinclude();

SEE ALSO

memcmp, strncmp

NOTES

strcmp is packaged in the integer library.

strcpy - copy one string to another

SYNOPSIS

FUNCTION

strcpy copies the NUL terminated string at $\underline{s2}$ to the buffer pointed at by $\underline{s1}$. The terminating NUL is also copied.

RETURNS

strcpy returns s1.

EXAMPLE

To make a copy of the string s2 in dest: strcpy(dest, s2);

SEE ALSO

memcpy, strncpy

NOTES

There is no way to specify the size of the destination area, to prevent storage overwrites.

strcpy is packaged in the integer library.

strcspn - find the end of a span of characters in a set

SYNOPSIS

#include <string.h>
unsigned int strcspn(s1, s2)
 const char *s1, *s2;

FUNCTION

strcspn scans the string starting at $\underline{s1}$ for the first occurrence of a character in the string starting at $\underline{s2}$. It computes a subscript i such that

- o s1[i] is a character in the string starting at s1
- o s1[i] compares equal to some character in the string starting at s2, which may be its terminating null character.

RETURNS

strcspn returns the lowest possible value of i. s1[i] designates the terminating null character if none of the characters in $\underline{s1}$ are in $\underline{s2}$.

EXAMPLE

To find the start of a decimal constant in a text string:
if (!str[i = strcspn(str, "0123456789+-")])
 printf("can't find number\n");

SEE ALSO

memchr, strchr, strpbrk, strrchr, strpn

NOTES

strcspn is packaged in the integer library.

strlen - find length of a string

SYNOPSIS

#include <string.h>
unsigned int strlen(s)
 const char *s;

FUNCTION

strlen scans the text string starting at \underline{s} to determine the number of characters before the terminating NUL.

RETURNS

The value returned is the number of characters in the string before the NUL.

NOTES

strlen is packaged in the integer library.

strncat - concatenate strings of length n

SYNOPSIS

#include <string.h>
char *strncat(s1, s2, n)
 char *s1;
 const char *s2;
 unsigned int n;

FUNCTION

strncat appends a copy of the NUL terminated string at $\underline{s2}$ to the end of the NUL terminated string at $\underline{s1}$. The first character of $\underline{s2}$ overlaps the NUL at the end of $\underline{s1}$. \underline{n} specifies the maximum number of characters to be copied, unless the terminating NUL in $\underline{s2}$ is encountered first. A terminating NUL is always appended $\underline{t0}$ s1.

RETURNS

strncat returns s1.

EXAMPLE

To concatenate the strings "day" and "light": strcpy(s, "day"); strncat(s + 3, "light", 5);

SEE ALSO

strcat

NOTES

strncat is packaged in the integer library.

strncmp - compare two n length strings for lexical order

SYNOPSIS

#include <string.h>
int strncmp(s1, s2, n)
 const char *s1, *s2;
 unsigned int n;

FUNCTION

strncmp compares two text strings, character by character, for lexical order in the character collating sequence. The first string starts at $\underline{s1}$, the second at $\underline{s2}$. \underline{n} specifies the maximum number of characters to be compared, unless the terminating NUL in $\underline{s1}$ or $\underline{s2}$ is encountered first. The strings must match, including their terminating NUL character, in order for them to be equal.

RETURNS

strncmp returns an integer greater than, equal to, or less than zero, according to whether $\underline{s1}$ is lexicographically greater than, equal to, or less than $\underline{s2}$.

EXAMPLE

To check for a particular error message:
if (strncmp(errmsg, "can't write output file", 23) == 0)
 cleanup(errmsg);

SEE ALSO

memcmp, strcmp

NOTES

strncmp is packaged in the integer library.

strncpy - copy n length string

SYNOPSIS

#include <string.h>
char *strncpy(s1, s2, n)
 char *s1;
 const char *s2;
 unsigned int n;

FUNCTION

strncpy copies the first \underline{n} characters starting at location $\underline{s2}$ into the buffer beginning at $\underline{s1}$. \underline{n} specifies the maximum number of characters to be copied, unless the terminating NUL in $\underline{s2}$ is encountered first. In that case, additional NUL padding \underline{is} appended to $\underline{s2}$ to copy a total of \underline{n} characters.

RETURNS

strncpy returns s1.

EXAMPLE

To make a copy of the string s2 in dest: strncpy(dest, s2, n);

SEE ALSO

memcpy, strcpy

NOTES

If the string $\underline{s2}$ points at is longer than \underline{n} characters, the result may not be NUL-terminated.

strncpy is packaged in the integer library.

strpbrk

Using The Compiler

strpbrk - find occurrence in string of character in set

SYNOPSIS

#include <string.h>
char *strpbrk(s1, s2)
 const char *s1, *s2;

FUNCTION

strpbrk scans the NUL terminated string starting at $\underline{s1}$ for the first occurrence of a character in the NUL terminated set $\underline{s2}$.

RETURNS

strpbrk returns a pointer to the first character in $\underline{s1}$ that is also contained in the set $\underline{s2}$, or a NULL if none does.

EXAMPLE

To replace unprintable characters (as for a 64 character terminal):
while (string = strpbrk(string, "`{|}~"))
*string = '@';

SEE ALSO

memchr, strchr, strcspn, strrchr, strspn

NOTES

strpbrk is packaged in the integer library.

NAME	strrchr - scan string for last occurrence of character
SYNOPSIS	<pre>#include <string.h> char *strrchr(s, c) const char *s; int c;</string.h></pre>
FUNCTION	strrchr looks for the last occurrence of a specific character \underline{c} in a NUL terminated string starting at \underline{s} .
RETURNS	$strrchr$ returns a pointer to the last character that matches \underline{c} , or NULL if none does.
EXAMPLE	To find a filename within a directory pathname: if (s = strrchr("/usr/lib/libc.user", '/') ++s;
SEE ALSO	memchr, strchr, strpbrk, strcspn, strspn
NOTES	

strrchr is packaged in the integer library.

strspn - find the end of a span of characters not in set

SYNOPSIS

#include <string.h>
unsigned int strspn(s1, s2)
 const char *s1, *s2;

FUNCTION

strspn scans the string starting at $\underline{s1}$ for the first occurrence of a character not in the string starting at $\underline{s2}$. It computes a subscript i such that

- o $\underline{s1[i]}$ is a character in the string starting at $\underline{s1}$
- o $\underline{s1[i]}$ compares equal to no character in the string starting at $\underline{s2}$, except possibly its terminating null character.

RETURNS

strspn returns the lowest possible value of <u>i. s1[i]</u> designates the terminating null character if all of the characters in $\underline{s1}$ are in $\underline{s2}$.

EXAMPLE

To check a string for characters other than decimal digits: if (str[strspn(str, "0123456789")]) printf("invalid number\n");

SEE ALSO

memchr, strcspn, strchr, strpbrk, strrchr

NOTES

strspn is packaged in the integer library.

tan - tangent

SYNOPSIS

FUNCTION

tan computes the tangent of \underline{x} , expressed in radians, to full double precision.

RETURNS

tan returns the nearest internal representation to tan(x), in the range [-pi/2, pi/2], expressed as a double floating value. If the number in \underline{x} is too large to be represented, tan returns zero. An argument with a large size may return a meaningless value, i.e. when x/(2 * pi) has no fraction bits.

EXAMPLE

To compute the tangent of theta: y = tan(theta);

SEE ALSO

cos, sin

NOTES

tan is packaged in the floating point library.

NAME	tanh - hyperbolic tangent
SYNOPSIS	<pre>#include <math.h> double tanh(x) double x;</math.h></pre>
FUNCTION	tanh computes the value of the hyperbolic tangent of \underline{x} to double precision.
RETURNS	tanh returns the nearest internal representation to tanh(x), expressed as a double floating value. If the result is too large to be properly represented, tanh returns zero.
EXAMPLE	To compute the hyperbolic tangent of x: y = tanh(x);
SEE ALSO	cosh, exp, sinh
NOTES	

tanh is packaged in the floating point library.

tolower

NAME

tolower - convert character to lowercase if necessary

SYNOPSIS

/* no header file need be included */
int tolower(c)
 int c;

FUNCTION

tolower converts an uppercase letter to its lowercase equivalent, leaving all other characters unmodified.

RETURNS

tolower returns the corresponding lowercase letter, or the unchanged character.

EXAMPLE

```
To accumulate a hexadecimal digit:
for (sum = 0; isxdigit(*s); ++s)
    if (isdigit(*s)
        sum = sum * 16 + *s - '0';
    else
        sum = sum * 16 + tolower(*s) + (10 - 'a');
```

SEE ALSO

toupper

NOTES

tolower is packaged in the integer library.

NAME		

toupper - convert character to uppercase if necessary

SYNOPSIS

/* no header file need be included */
int toupper(c)
 int c;

FUNCTION

toupper converts a lowercase letter to its uppercase equivalent, leaving all other characters unmodified.

RETURNS

toupper returns the corresponding uppercase letter, or the unchanged character.

EXAMPLE

To convert a character string to uppercase letters:
 for (i = 0; i < size; ++i)
 buf[i] = toupper(buf[i]);</pre>

SEE ALSO

tolower

NOTES

toupper is packaged in the integer library.

va arg - get pointer to next argument in list

SYNOPSIS

#include <stdarg.h>
type va arg(ap, type)
 va_list ap;
 type;

FUNCTION

The macro va arg is an rvalue that computes the value of the next argument in a variable length argument list. Information on the argument list is stored in the array data object ap. You must first initialize ap with the macro va start, and compute all earlier arguments in the list by expanding va arg for each argument.

The type of the next argument is given by the type name type. The type name must be the same as the type of the next argument. Remember that the compiler widens an arithmetic argument to int, and converts an argument of type float to double. You write the type after conversion. Write int instead of char and double instead of float.

Do not write a type name that contains any parentheses. Use a type definition, if necessary, as in

```
typedef int (*Pfi)();
    /* pointer to function returning int */
    ...
fun_ptr = va_arg(ap, Pfi);
    /* get function pointer argument */
```

RETURNS

va_arg expands to an rvalue of type type. Its value is the value of the next argument. It alters the information stored in ap so that the next expansion of va_arg accesses the argument following.

EXAMPLE

To write multiple strings to a file:

```
#include <stdio.h>
#include <stdarg.h>
main()
      {
       void strput();
```

```
strput(pf, "This is one string\n",
        "and this is another...\n", (char *)0);
void strput(FILE *pf, ...);
void strput(char *ptr, ....)
void strput(ptr)
    char *ptr;
    char ptr;
    va_list va;
    if (!ptr)
        return;
    else
        puts(ptr);
        va start(va, ptr);
        while (ptr = va_arg(va, char *);
            puts(ptr);
        va_end(va);
    }
```

SEE ALSO

va end, va_start

NOTES

va_arg is a macro declared in the <stdarg.h> header file. You
can use it with any function that accepts a variable number of
arguments, by including <stdarg.h> with your program.

va end - stop accessing values in an argument list

SYNOPSIS

#include <stdarg.h>
void va end(ap)
 va_list ap;

FUNCTION

va_end is a macro which you must expand if you expand the macro va_start within a function that contains a variable length argument list. Information on the argument list is stored in the data object designated by ap. Designate the same data object in both va_start and va_end.

You expand va_end after you have accessed all argument values with the macro va_arg, before your program returns from the function that contains the variable length argument list. After you expand va_end, do not expand va_arg with the same ap. You need not expand va_arg within the function that contains the variable length argument list.

You must write an expansion of va_end as an expression statement containing a function call. The call must be followed by a semicolon.

RETURNS

Nothing. va end expands to a statement, not an expression.

EXAMPLE

To write multiple strings to a file:

```
if (!ptr)
    return;
else
    {
    puts(ptr);
    va_start(va, ptr);
    while (ptr = va_arg(va, char *);
        puts(ptr);
    va_end(va);
    }
}
```

SEE ALSO

va_arg, va_start

NOTES

va_end is a macro declared in the <stdarg.h> header file. You
can use it with any function that accepts a variable number of
arguments, by including <stdarg.h> with your program.

va start - start accessing values in an argument list

SYNOPSIS

```
#include <stdarg.h>
void va_start(va_list ap, parmN)
    va_list ap;
    parmN;
```

FUNCTION

va_start is a macro which you must expand before you expand the macro va_arg. It initializes the information stored in the data object designated by \underline{ap} . The argument \underline{parmN} must be the identifier you declare as the name of the last specified argument in the variable length argument list for the function. In the function prototype for the function, \underline{parmN} is the argument name you write just before the , ...

The type of $\underline{\text{parmN}}$ must be one of the types assumed by an argument passed in the absence of a prototype. Its type must not be $\underline{\text{float}}$ or $\underline{\text{char.}}$ Also, $\underline{\text{parmN}}$ cannot have storage class $\underline{\text{register.}}$

If you expand va_start, you must expand the macro va_end before your program returns from the function containing the variable length argument list.

You must write an expansion of **va_start** as an <u>expression</u> statement containing a function call. The call must be followed by a semicolon.

RETURNS

Nothing. va start expands to a statement, not an expression.

EXAMPLE

To write multiple strings to a file:

va_start

SEE ALSO

va_arg, va_end

NOTES

va_start is a macro declared in the <stdarg.h> header file.
You can use it with any function that accepts a variable number
of arguments, by including <stdarg.h> with your program.

			$\overline{}$