SECTION FOUR

IDRIS SUPPORT LIBRARY

Conventions - the Idris support library

## SYNOPSIS

/lib/libi\*

#### FUNCTION

The functions documented in this section are kept in a library, separate from the standard C library, with a name whose prefix is /lib/libi (and whose suffix is machine dependent). They are used extensively in the construction of standard Idris utilities, to perform common functions uniformly and to enforce communication protocols among utilities. They are thus quite useful to anyone wishing to add utilities that are to cooperate with the existing community.

Most of the notation used here is the same as in earlier sections of this manual, but there are a few additional types that creep in from various header files:

BLOCK an unsigned short, capable of holding any filesystem block number.

Block 0 is often taken as the absence of a block number. Defined in /lib/ino.h.

FINODE a filesystem inode, possibly as represented on the disk or possibly in native byte order. Defined in /lib/ino.h.

INUM an unsigned short, capable of holding any filesystem inode number. Inode 0 does not exist. Defined in /lib/ino.h.

TVEC a time vector, used to communicate parsed dates among library functions. Defined in /lib/time.h as:

```
typedef struct {
                                    [0, 60) */
                    /* seconds
   BYTES secs;
                                     [0, 60) #/
                    /# minutes
    BYTES mins;
                                     [0, 24) */
                    /* hours
    BYTES hrs;
                                             [1, 31] */
                    /* day of month
    BYTES dmth;
                                             [0, 12) */
                    /# month of year
    BYTES mth;
                                            [70, 131) */
                    /* years since 1900
    BYTES yr;
                    /* day of week, sunday = 0 [0, 7) */
    BYTES dwk;
                                                 [0, 365] */
                    /* day of year
    BYTES dyr;
                    /* non-zero if daylight savings time */
    BOOL dstf;
    } TVEC;
```

Also included in this library is a version of putf (the internal routine putf to be exact) that cannot deal with the floating point conversions %d and %f. This is provided so that utilities can perform formatted output — using decode, errfmt, putf, and putfmt — without dragging in (possibly extensive) floating point runtime support code that will never be needed. Be warned, however, that automatically including the Idris support library with the standard compile and link scripts will lead to puzzling behavior in a program that expects to perform floating output.

\_penable - control function entry counts in profiling

## SYNOPSIS

TBOOL \_penable;

## FUNCTION

\_penable is used by the function entry counting routine of the profiling package, to control whether or not calls to the routine actually will record function entries. If penable is non-zero, function entries will be counted; otherwise, the counting routine returns without doing anything.

\_profil() sets \_penable to 1 just before returning. \_proend() clears \_penable just after being called.

## SEE ALSO

\_proend, \_profil

\_proend

NAME

\_proend - end profiling

SYNOPSIS

VOID (\*proend())()

## FUNCTION

\_proend terminates profiling, by clearing the one-byte flag \_penable to disable function entry counting, calling profil() to end time profiling, and writing out the time profiling and entry count buffers to the file named in the last preceding call to \_profil().

## RETURNS

Since \_proend() is linked into the chain of programs to be called on program exit or interrupt, it returns the address of the next one to call.

## SEE ALSO

\_penable, \_profil

IV - 3

\_profil - start profiling

## SYNOPSIS

```
TEXT *_profil(p)
    struct {
        UCOUNT config, esize;
        BYTES pbuf, psize, offset, scale, tbias, ebias;
        TEXT *fname;
        } *p;
```

## FUNCTION

\_profil performs a number of useful housekeeping functions preparatory to commencing program profiling. Its single argument, p, is a pointer to a standard profile file header, which is immediately followed by the name of the file to be generated by \_proend().

\_profil computes file header parameters psize and scale, allocates space for the time profiling and entry count buffers at pbuf, calls profil() to initiate time profiling, and ensures that \_proend() is called on program interrupt or exit. Finally, it enables function entry counting by setting the one-byte flag \_penable to 1.

## RETURNS

\_profil returns the address of the first byte past the end of the buffer space it allocated at pbuf.

### SEE ALSO

\_penable, \_proend

askpw - ask for a password

## SYNOPSIS

TEXT \*askpw(kbuf, key)
 TINY kbuf[8];
 TEXT \*key;

## FUNCTION

askpw fills kbuf with the NUL terminated password at key, or if (key == NULL) reads a line from STDIN to fill kbuf. Before reading a line from a terminal as STDIN, askpw will drain outstanding input by performing an stty, prompt with the string "\7password:\ ", and accept the subsequent line, echoing only the trailing newline.

In any case, the first eight characters of the password are used; a short string is padded on the right with NULs.

Note that a password may thus be obtained from any of three sources: from an argument to the function, from a terminal with prompting and with printing suppressed, or from a noninteractive STDIN with no prompting.

## RETURNS

askpw returns the address of kbuf, which contains the NUL padded password.

## **EXAMPLE**

bldks(ks, askpw(kbuf, NULL));

## SEE ALSO

codepw

asure - get user response to question

## SYNOPSIS

BOOL asure(p) TEXT \*p;

## FUNCTION

If STDIN looks like a terminal, asure drains its input by performing an stty, writes the NUL terminated string at \*p to STDERR, followed by a space, then reads up to 32 characters from STDIN.

This meticulous sequence of events is useful when a program needs to be assured that a conscious human accomplice is present.

## RETURNS

If the line read begins with a 'y' or 'Y', or if STDIN is not a terminal, asure returns YES; otherwise it returns NO.

## **EXAMPLE**

if (asure("are you sure?"))
 serog();

## NAME

atime - convert time vector to ASCII string

## SYNOPSIS

TEXT \*atime(vt, s) TVEC \*vt; TEXT \*s;

## FUNCTION

atime converts the time vector at vt to a 24 character string at s, having

Thu Aug 12 09:53:12 1980

There is no terminating NUL or newline.

## RETURNS

atime writes the date in ASCII at s[0] through s[23], and returns s.

To print the date:

IMPORT LONG time();
IMPORT TEXT \* est, \* edt;
INTERN TEXT buf[] {"012345678901234567890123"}; TVEC tvec; ltime(&tvec, time(NULL)); putstr(STDOUT, atime(&tvec, buf), tvec.dstf ? \_edt : \_est, "\n", NULL);

## SEE ALSO

ltime, vtime

```
NAME
```

baudcode - return code given speed text

## SYNOPSIS

UCOUNT baudcode(s) TEXT \*s;

## FUNCTION

baudcode compares the text string s with the table baudlist and returns the index of the matching string.

#### RETURNS

The speed code in the range [0, 15], or 16, if the lookup fails.

## EXAMPLE

## SEE ALSO

baudlist, baudtext

baudlist - list of speeds supported by Idris drivers

## SYNOPSIS

```
TEXT baudlist[NBAUD] {
   "0", "50", "75", "110"
   "134.5", "150", "200", "300",
   "600", "1200", "1800", "2400",
   "4800", "9600", "19200", "38400"};
```

## FUNCTION

baudlist is a table of text speeds supported by Idris drivers. The table is indexed by a code in the range [0, 15].

## SEE ALSO

baudcode, baudtext

IV - 9

## baudtext

## NAME

baudtext - return text speed given speed code

## SYNOPSIS

TEXT \*baudtext(c)
UCOUNT c;

## FUNCTION

baudtext returns a pointer to the speed text string corresponding to the baudrate code c. The actual strings live in the table baudlist[].

#### RETURNS

A pointer to the speed text string, or NULL if code was not in the range [0, 15].

## SEE ALSO

baudcode, baudlist

clrbuf

NAME

clrbuf - clear a standard sized buffer

SYNOPSIS

VOID clrbuf(buf)
 TEXT buf[BUFSIZE];

FUNCTION

clrbuf writes zeros throughout a 512-byte buffer beginning at buf.

RETURNS

Nothing, except a clear buffer.

EXAMPLE

clrbuf(p->\_buf);

codepw - encode a password

#### SYNOPSIS

TEXT \*codepw(loginid, kbuf)
 TEXT \*loginid, kbuf[8];

#### **FUNCTION**

codepw encrypts the password in kbuf, then translates it to a printable form, suitable for storing in a textfile. The encrypted form is obtained by using the DES algorithm to encrypt the first eight characters of the file /adm/salt, exclusive-ored character by character with the NUL terminated string at loginid, using the password as a key. If the salt file is not readable, the string "password" is used in its stead.

The resulting eight-character encrypted string is repacked as twelve sixbit characters, using the alphabet [0-9a-zA-Z/.]. For convenience, a NUL is placed at the end of this string.

#### RETURNS

codepw returns a pointer to the NUL terminated, twelve-character encoded password which is stored in an internal buffer.

## **EXAMPLE**

if (!cmpstr(codepw("root", askpw(kbuf, NULL)), getpw("root", 0, 1)))
 error("sorry", NULL);

#### FILES

/adm/salt for the string to be encrypted.

## SEE ALSO

askpw, getpw

cpyi - copy an inode converting between native and filesystem

### SYNOPSIS

FINODE \*cpyi(dest, src) FINODE \*dest, \*src;

## FUNCTION

cpyi copies the entire FINODE structure pointed to by src into the structure at dest, ensuring that all fields are converted if native byte order differs from filesystem byte order. For portability, its use is encouraged even on machines that need no conversion.

It is permissible for src and dest to be the same.

## RETURNS

cpyi returns dest.

## EXAMPLE

To get a pointer to an inode in native order:

```
FINODE *getino(fd, ino)
   FILE fd;
   INUM ino;
   {
   INTERN FINODE buf[BUFSIZE / sizeof (FINODE)], ibuf;
   if (!getblk(fd, buf, inblk(ino)))
      return (NULL);
   else
      return (cpyi(&ibuf, ioff(buf, ino)));
}
```

#### NAME

cwd - get current working directory

#### SYNOPSIS

COUNT cwd(tbuf)
TEXT tbuf[NAMSIZE];

#### FUNCTION

cwd determines the absolute pathname of the current working directory by tracing .. entries from . back to the root. The result is placed in tbuf as a NUL terminated string. If the current directory is on a mounted filesystem the mount history file /adm/mtab is used to determine the prefix of the absoute pathname.

If the path to the root of the filesystem becomes longer than 64 characters, including the terminating NUL, cwd returns the system error code -E2BIG. If cwd cannot find an entry in a directory that it needs it returns the system error code -EMLINK. If an error occurs while trying to open any directories for reading, the partially formed path is left in thuf and cwd returns the appropriate system return code.

#### RETURNS

cwd writes a NUL terminated string at tbuf. If successful, the return value is zero; otherwise, the return value is a negative number indicating cwd's displeasure (as one of the Idris error return codes, negated).

## **EXAMPLE**

To map a pathname to absolute form:

```
if (name[0] == '/')
    cpystr(abuf, name, NULL);
else if (cwd(build) < 0)
    error("broken directory tree", NULL);
else
    cpystr(abuf, build, "/", name, NULL);</pre>
```

## FILES

/adm/mtab for mounted filesystems, . for current directory,  $\...$  for parents.

devname - get device name

## SYNOPSIS

BOOL devname(s, mdev, cspec)
TEXT \*s;
UCOUNT mdev;
BOOL cspec;

## FUNCTION

devname fills the buffer pointed to by s with the NUL terminated device name in the /dev directory matching the major/minor device code contained in mdev. If cspec is nonzero, the device must be a character special device; otherwise, the device must be a block special device.

## RETURNS

devname returns YES if it could find the appropriate device entry. The buffer at s is filled in with the device name, written as a 14-character link right filled with NULs.

#### **EXAMPLE**

The terminal message control function is:

```
BOOL mesg(new)

BOOL new;

{

FAST BOOL old;

STAT node;

TEXT buf[20];

if (fstat(STDERR, &node) < 0)

return (NO);

old = (node.s mode & 022) ? YES : NO;

cpybuf(buf, "/dev/", 5);

buf[19] = '\0';

if (devname(buf + 5, node.s addr[0], YES))

chmod(buf, new ? 0622 : 0600);

return (old);

}
```

### ename

NAME

ename - get pathname of an entry in a directory

#### SYNOPSIS

TEXT \*ename(pname, dname, pdir)
 TEXT \*pname, \*dname;
 DIR \*pdir;

## FUNCTION

ename creates a fully qualified pathname consisting of the directory named dname to which is appended a '/' and the entry name pointed at by pdir. This NUL terminated pathname is returned at pname.

pname should be large enough to hold lenstr(dname) + 16 characters, counting the terminating NUL.

## RETURNS

ename returns a pointer to the entry name.

## **EXAMPLE**

if(!cmpstr(".", pdir->d\_name) && !cmpstr("..", pdir->d\_name))
 remove(ename(entry, dir, pdir));

#### NAME

flushi - flush out any pending inode writes

## SYNOPSIS

VOID flushi(fd) FILE fd;

## FUNCTION

flushi writes the in-core buffer used by geti and puti to the filesystem controlled by fd. If there have been no changes to the buffer, no output is performed. In any case, the buffer is disqualified, and the next geti or puti is guarenteed to read a fresh block from the filesystem.

#### RETHRMS

If there is pending output, and it cannot be written, the writerr condition is raised.

## EXAMPLE

To process the entire inode list of a filesystem:

```
for (i = isize << 4; 1 <= i; --i)
    if (process(pi = geti(fd, &ibuf, i)))
        puti(fd, pi, i);
flushi(fd);</pre>
```

## SEE ALSO

geti, puti

ftime - find modified or accessed time of a file

## SYNOPSIS

LONG ftime(fd, modflag)
FILE fd;
BOOL modflag;

## FUNCTION

ftime finds the time of last access, or the time of last modification if modflag is true, to the file under control of  ${\tt fd.}$ 

## RETURNS

ftime returns the time specified by modflag in seconds since 1 Jan 1970, or zero if the file status is unobtainable.

## **EXAMPLE**

To print the date on which file "xeq" was last modified:

INTERN TEXT buf[] {"012345678901234567890123"};
FILE fd = open("xeq", READ, 0);
TVEC tvec;

putstr(STDOUT, atime(ltime(&tvec, ftime(fd, YES)), buf),
 "\n", NULL);

## SEE ALSO

atime, ltime

getblk - get filesystem block

## SYNOPSIS

BOOL getblk(fd, buf, bno)
FILE fd;
TEXT \*buf;
BLOCK bno;

## FUNCTION

getblk reads the 512-byte block whose number is bno into buf from the file under control of fd.

## RETURNS

getblk returns YES only if exactly 512 characters were read.

## **EXAMPLE**

if (!getblk(fd, superbuf, 1))
 error("can't read filsys", NULL);

## SEE ALSO

mapblk, putblk

## getdn

## NAME

getdn - get device name

## SYNOPSIS

FILE getdn(s, fname, mode)
 TEXT \*s, \*fname;
 BOOL mode;

## FUNCTION

getdn opens a block or character special device using mode as the mode argument to the open call. If the file fname exists and is a block or character special device, it is opened. If the file fname does not exist, to it is prepended "/dev/" for a second try. If fname does exist but is not block or character special, then the block or character special device on which fname exists is opened instead, if that can be determined by calls to devname.

#### RETURNS

getdn returns a file descriptor for the opened file, or a negative number which is the Idris return code, negated. The name of the opened file, or the best guess at one on failure, is copied to s.

## EXAMPLE

if ((fd = getdn(buf, fname, pflag ? UPDATE : READ)) < 0)
 error("invalid pathname: ", buf);</pre>

### SEE ALSO

devname, stat

geti - get inode from filesystem

## SYNOPSIS

FINODE \*geti(fd, buf, ino)
 FILE fd;
 FINODE \*buf;
 INUM bno;

#### FUNCTION

geti reads the inode whose number is ino from the filesystem under control of fd. It then copies the inode into buf, converting from filesystem format to in-core format in the process.

geti shares an in-core buffer of 16 inodes (1 block) with puti, and will use the contents of the buffer when appropriate. Thus, the buffer should be disqualified by calling flushi before switching filesystems.

## RETURNS

If geti cannot read the necessary inode it will raise the readerr condition. If there is pending inode output from puti and the inode cannot be written, the writerr condition will be raised. Otherwise, geti will return buf, the pointer to the in-core inode.

## EXAMPLE

To process the entire inode list of a filesystem:

```
for '(i = isize << 4; 1 <= i; --i)
    if (process(pi = geti(fd, &ibuf, i)))
        puti(fd, pi, i);
flushi(fd);</pre>
```

## SEE ALSO

flushi, puti

#### NAME

getlinks - read and sort a directory

## SYNOPSIS

DIR \*getlinks(dirname, nentries, size)
 TEXT \*dirname;
 BYTES \*nentries;
 LONG size;

## FUNCTION

getlinks allocates an array of size bytes, reads a directory into it, then sorts the entries in lexical order on link names, but with zero inodes at the end. The number of non-null entries in the directory, including . and .. is written at nentries. size is the size in bytes of the directory, dirname.

## RETURNS

getlinks returns a pointer to the first directory entry (usually .), or NULL if the directory cannot be read. The pointer is suitable for later use on a free call.

#### **EXAMPLE**

To print all the entries in a directory, and then free the allocated space:

```
IMPORT LONG lsize();
BYTES nentries;
DIR *pdir, *p;
STAT dstat;
TEXT *dirname;
if (stat(dirname, &dstat) < 0)
    putstr(STDERR, dirname, " does not exist\n", NULL);
else
    {
    pdir = getlinks(dirname, &nentries, lsize(&dstat->s_mode));
    for (p = pdir; nentries--; ++p)
        putstr(STDOUT, p->d_name, "\n", NULL);
    free(pdir, NULL);
}
```

getpw - retrieve a field from the password file

## SYNOPSIS

```
TEXT *getpw(matchstr, matchfld, wantfld)
BYTES matchfld, wantfld;
TEXT *matchstr:
```

## FUNCTION

getpw scans the system password file for a line with a field, specified by matchfld, that matches the NUL terminated string pointed at by matchstr.

Fields in the password file are separated by colons on a text line, as follows:

FIELD	CONTENTS
0	loginid
1	encrypted password
_	user number
3 4	group number
5	long name
6	home directory
U	shell

Lines are assumed to be no longer than 128 bytes.

getpw remembers the last password line obtained in an internal buffer; consequently multiple calls leading to the same line are reasonably efficient. The line should not be corrupted by the calling program, however, nor should its contents be trusted if other getpw calls intervene.

## RETURNS

getpw returns a pointer to the field specified by wantfld, in the matched field. If no match is found, NULL is returned. If the field is found, but the desired field does not exist, the returned pointer will be pointing at newline.

## **EXAMPLE**

To find the loginid of user number 5:

## FILES

/adm/passwd for the password file.

## BUGS

Lines should be up to 512 bytes in the password file.

```
NAME
    inblk - find home block of an inode
SYNOPSIS
    BLOCK inblk(ino)
        INUM ino;
FUNCTION
    inblk locates the block number containing ino for any desired inode.
RETURNS
    inblk returns the correct block number.
EXAMPLE
    To get an inode:
    FINODE *getino(fd, ino)
       FILE fd;
        INUM ino;
        INTERN FINODE buf[BUFSIZE / sizeof (INO)];
       if (!getblk(fd, buf, inblk(ino)))
           return (NULL);
           return (ioff(buf, ino);
```

SEE ALSO ioff

```
IDRIS Support Library
                                                                             ioff
NAME
     ioff - get inode offset within block
SYNOPSIS
    TEXT *ioff(s, ino)
         TEXT *s;
         INUM ino:
FUNCTION
    ioff locates inode number ino within the 512-byte block at s, assuming the
    correct block has already been read into s.
RETURNS
    ioff returns a pointer to the first byte of the inode.
EXAMPLE
    To get an inode:
    FINODE *getino(fd, ino)
FILE fd;
        INUM ino;
        INTERN FINODE buf[BUFSIZE / sizeof (INO)];
        if (!getblk(fd, buf, inblk(ino)))
            return (NULL);
            return (ioff(buf, ino);
SEE ALSO
   inblk
```

lsize - get size of a file

## SYNOPSIS

LONG lsize(pi) FINODE \*pi;

## FUNCTION

lsize obtains the size of a file in bytes from the sizeO and size1 fields in the inode at pi. The inode is assumed to be in native byte order, such as is returned as part of a stat (or fstat) system call.

#### RETURNS

lsize returns the size as a long integer.

# EXAMPLE

IMPORT LONG lsize();

nblocks = lsize(&ps->s\_mode) >> 9;

lslin - convert inode information to readable form

## SYNOPSIS

TEXT \*lslin(buf, pnode, grp, atim)
TEXT \*buf;
FINODE \*pnode;
BOOL grp, atim;

## FUNCTION

Islin fills a 43 character buffer pointed at by buf with a printable representation of information from the file system inode pointed at by pnode. The inode is assumed to be in native byte order, such as is returned as part of a stat (or fstat) system call.

The first character in the returned buffer is the inode type;

'-' for a plain file

'c' for a character special device

'd' for a directory

'b' for a block special device

The next nine characters of this first field specify the read 'r', write 'w' and execute 'x' permissions for the owner, the owner's group and all others, in that order. A '-' in any position indicates that the associated permission is denied. An 's' in place of an 'x' means: set userid if in the owner field, set groupid if in the group field, save text if in the others field. An 'e' in place of an 'x' means much the same, except that the corresponding execute permission is not present.

The next 3 character field specifies the number of links to the inode, right justified.

A space follows.

The loginid occupies the next 8 character field, left justified. If (grp) then the loginid corresponds to the first password file entry whose groupid matches that of the file; otherwise the loginid is for the first entry whose userid matches. If the loginid is not obtainable from the password file, the above key is printed as a decimal number, left justified in the field.

If the inode is not a special device, the next eight character field specifies the size, in bytes, of the file. Otherwise the device's major and minor inode numbers are printed, right justified and separated by a comma.

In either case, a space follows.

The last field is 12 characters long and contains the month, day and time of the date last accessed, if atim is nonzero; otherwise the date of last update. If this time is more than half a year ago, the time subfield is replaced with the year of last update.

lslin

IDRIS Support Library

RETURNS

lslin returns buf, whose contents are replaced.

EXAMPLE

stat(\*av, &fi); lslin(buf, &p->s\_mode, YES); putfmt("%.43p %p\n", buf, \*av);

which might print:

-r-sr-xr-x 1 root

18678 May 06 1980 /bin/rm

SEE ALSO atime

ltime - convert system time to local time

## SYNOPSIS

```
TVEC *ltime(pv, lt)
TVEC *pv;
LONG lt;
```

## FUNCTION

ltime converts lt, the number of seconds elapsed since 00:00 Jan 1 1970, to a structure at pv giving the time components in local time.

The timezone is determined from the timezone file, if it can be read; it will be read at most once. Otherwise, the default internal values are used, which are correct for Secaucus NJ. Timezone information is available in the external variables:

```
BOOL _dst {YES}; /* non-zero enables daylight savings */
BYTES _timezone {5}; /* hours west of Greenwich */
BYTES _tzmins {0}; /* minutes west of standard */
TEXT *_edt {"EDT"};
TEXT *_est {"EST"};
```

The initial values shown are the defaults. Note that fractional timezones, such as for Surinam, are supported.

If (12 <= \_timezone) ltime subtracts 24 for use in its computation. Thus to get the correct time east of Greenwich, the timezone should be set to 24 minus the number of hours east of Greenwich. The timezone for Japan is (24-9).

## RETURNS

ltime returns the pointer pv and fills in the structure at pv.

## **EXAMPLE**

To print the date:

## FILES

/adm/zone for the timezone.

## SEE ALSO

atime, vtime

## BUGS

This will fail after Feb 28, 2100.

## NAME

mapblk - map logical block to physical

## SYNOPSIS

```
BLOCK mapblk(fd, pi, lbn)
FILE fd;
FINODE *pi;
BLOCK lbn;
```

#### FUNCTION

mapblk determines the physical block number corresponding to the logical block number lbn in the file whose inode is at pi. It reads indirect blocks as necessary from the filesystem under control of fd.

## RETURNS

mapblk returns the physical block number, if present. Zero is returned if lbn is off the end or inside a hole in the file.

## EXAMPLE

## SEE ALSO

getblk, putblk

mesg

## NAME

mesg - turn on or off messages to current terminal

## SYNOPSIS

BOOL mesg(new)
BOOL new;

## FUNCTION

mesg allows other users to write to the current terminal when new is non-zero; otherwise it prevents other users from writing to this terminal.

## RETURNS

 ${\tt mesg}$  returns  ${\tt YES}$  if the terminal had write permission when the function was called.

## **EXAMPLE**

old = mesg(NO); print(); mesg(old);

## SEE ALSO

devname

mkdir - make a directory

## SYNOPSIS

ERROR mkdir(dname)
 TEXT \*dname;

## **FUNCTION**

mkdir makes the directory dname, with two entries, ., linking dname to itself, and .., linking dname to its parent. mkdir can only be used by the superuser.

## RETURNS

mkdir returns 0 if successful, else a negative number which is the Idris error code negated.

## EXAMPLE

if (mkdir(name) < 0)
 putstr(STDERR, "can't make directory: ", name, "\n", NULL);</pre>

mv - move a file

## SYNOPSIS

ERROR mv(old, new)
 TEXT \*old, \*new;

## FUNCTION

mv creates the link new to a file and removes the link old. If a file named new already exists, it is removed. If old and new are on different filesystems and old is a plain file mv will copy old to new; otherwise, if old is a character or block special device, mv will make the appropriate device; in either case, old is removed. A directory cannot be moved to another filesystem, or to a subtree of itself.

#### RETURNS

mv returns zero if successful, else a negative number, which is the Idris error return code, negated.

## **EXAMPLE**

Physical Physical Physical Property of the Pro

if (mv("a.out", "xeq") < 0)
 putstr(STDERR, "can't move a.out\n", NULL);</pre>

parent

#### NAME

parent - get parent name of a file

## SYNOPSIS

TEXT \*parent(buf, path) TEXT \*buf, \*path;

## FUNCTION

parent creates a NUL terminated string at buf which is the name of the parent of the file named path. The parent is created by a) stripping off trailing '/' characters; b) stripping off trailing "/." strings; stripping off and remembering trailing "/.." strings; d) repeating a-c until there are no more to be stripped; e) partitioning the remainder into LEFT '/' RIGHT, where LEFT is NULL if there is not at least one slash, and RIGHT contains no slash. f) determining the "base" parent by the following table:

```
SLASH
                 RIGHT
                         PARENT
LEFT
                         .. (or / if path started with a /)
        no
                 none
none
none
        no
none
        no
                 other
        no
none
                 any
none
        ves
                          <LEFT>
        yes
                 any
any
```

g) adding back the trailing "/.." strings that were stripped in c. h) stripping off leading "./" strings;

## For example:

```
PARENT
FILENAME
abc
             X
x/y
/a
              a/..
a/b/..
../c
              • •
```

Note that parent is sufficiently cautious about writing into buf, that parent(name, name) is meaningful, and will work as expected.

## RETURNS

parent returns buf.

```
stat(parent(buf, path), &pstat);
if (!perm(&pstat, 02))
    putstr(STDERR, "can't remove ", path, "\n", NULL);
```

perm - test permissions of a file

#### SYNOPSES

BOOL perm(pst, mask) STAT \*pst; COUNT mask:

## FUNCTION

perm determines if the current process has all of the permissions requested by mask, for the file whose status, as returned by stat, is pointed at by pst. mask is the inclusive or of 04, to check read permission, 02, to check write permission, and 01, to check execute permission. The permissions are checked according to the real userid and groupid of the process. This means that perm may be called by set-userid programs to test whether the invoker of the program has the required permissions. If the userid of the file is the same as the real userid then the "user access" bits are checked; otherwise, if the groupid of the file matches the real groupid, the "group access" bits are checked; otherwise, the "other access" bits are checked.

#### RETURNS

perm returns YES if the file has all of the requested permissions. If the user is the superuser, perm returns YES, unless mask requests execute permission and none of the execute permissions are turned on for the file.

## EXAMPLE

if (!perm(&filestat, 02))
 putstr(STDERR, "can't write\n", NULL);

```
putblk
```

NAME

putblk - put filesystem block

SYNOPSIS

BOOL putblk(fd, buf, bno)
FILE fd;
TEXT \*buf;
BLOCK bno;

FUNCTION

putblk writes the 512-byte block whose number is bno from buf to the file under control of fd. If the write fails, the function returns NO.

RETURNS

putblk returns YES if it can write the whole block else NO.

EXAMPLE

if (!putblk(fd, superbuf, 1))
 error("can't write superblock", NULL);

SEE ALSO

getblk, mapblk

puti - put inode to filesystem

## SYNOPSIS

VOID puti(fd, pi, ino)
 FILE fd;
 FINODE \*pi;
 INUM ino;

## FUNCTION

puti writes the in-core inode pointed at by pi to the filesystem controlled by fd, after converting the inode to filesystem format. puti shares an in-core buffer of 16 inodes (1 block) with geti, and pi is actually just copied and converted into this buffer. Thus, flushi must be called before closing fd, to insure that any pending output is completed.

## RETURNS

If there is pending output for another inode block, and it cannot be written, the writerr condition is raised. If the appropriate inode block is not in the buffer shared between geti and puti and it cannot be read, the readerr condition is raised. In any case, there is no useful return value from puti.

## **EXAMPLE**

To process the entire inode list of a filesystem:

```
for (i = isize << 4; 1 <= i; --i)
    if (process(pi = geti(fd, &ibuf, i)))
        puti(fd, pi, i);
flushi(fd);</pre>
```

## SEE ALSO

flushi, geti

rdir - read directory on unmounted filesystem

## SYNOPSIS

```
DIR *rdir(fd, pi, lno)

FILE fd;

FINODE *pi;

BYTES lno;
```

## FUNCTION

rdir obtains the directory entry whose ordinal position is lno within the directory, counting from zero, by reading the unmounted filesystem at fd. It is assumed that pi points at the directory's inode, in native byte order. If lno is zero, or if the block differs from that remembered on the last call to rdir, a new block is obtained by reading from the file under control of fd.

Note well that this function is designed for sequential processing of  $\$  one directory at a time.

## RETURNS

rdir returns a pointer to the link within its current block in memory. If the list is off the end of the directory, rdir returns NULL.

## EXAMPLE

```
for (i = 0; pd = rdir(fd, &ino, i); ++i)
    process(pd);
```

## SEE ALSO

Wdir

rmdir

## NAME

rmdir - remove a directory

## SYNOPSIS

COUNT rmdir(dname)
TEXT \*dname;

## FUNCTION

rmdir removes an empty directory, (i.e., one with at most one . entry and at most one .. entry). Directories can only be removed by the superuser.

## RETURNS

rmdir returns zero if successful; otherwise: -ENOENT if dname does not exist, -ENOTDIR if dname is not a directory, -EISDIR if directory is not empty, or -EPERM if user does not have write permission for the parent directory.

## **EXAMPLE**

if (rmdir(fname) < 0)
 putstr(STDERR, "can't remove ", fname, "\n", NULL);</pre>

#### NAME

shell - execute a shell command escape

## SYNOPSIS

COUNT shell(cmd, fname, flags)
TEXT \*cmd, \*fname;
COUNT flags;

## FUNCTION

shell invokes the shell command interpreter to parse and execute cmd. It is most often used within programs offering a "! cmd" shell escape or within programs offering a "-c cmd" flag.

Any trailing '\n' before the trailing NUL on cmd is ignored. If fname is not NULL, any occurrence of the sequence "\f" within cmd will be replaced by the string fname.

If the first 3 characters of cmd are "cd\" then a chdir system call is done with the rest of cmd as an argument. This will affect the caller.

If the first 3 characters of cmd are not "cd\" then the shell command interpreter is invoked as "sh -c cmd" under the current execution path. If (!(flags & 3)) cmd is invoked as a new process; shell will wait until the command has completed and will return its status to the calling program. If (flags & 1) cmd is invoked as a new process and shell will not wait, but will return the processid of the child. If (flags & 2) cmd is invoked in place of the current process, whose image is forever gone. In this case, shell will never return to the caller.

To the value of flags may be added a 4 if the processing of interrupt and quit signals for cmd is to revert to system handling. They are normally turned off in both the invoker and any new process for the duration of cmd. The value of flags may also be incremented by 8 if the effective userid is to be made the real userid before cmd is executed.

## RETURNS

If a chdir is requested, shell will return what chdir does. If cmd cannot be invoked, shell will return failure; If (!(flags & 3)) shell returns YES if the command executed successfully, otherwise NO; if (flags & 1) shell returns the id of the child process, if one exists, otherwise zero; if (flags & 2) shell will never return to the caller.

In all cases, if cmd cannot be executed, an appropriate error message is written to STDERR.

## SEE ALSO

xecl, xecv

vtime

NAME

vtime - convert system time to Greenwich Mean Time

SYNOPSIS

TVEC \*vtime(pv, lt)
TVEC \*pv;
LONG lt;

FUNCTION

vtime converts lt, the number of seconds elapsed since 00:00 Jan 1 1970, to a structure at pv giving the time components in GMT.

RETURNS

vtime returns the pointer pv and fills in the structure at pv.

EXAMPLE

To print the date:

IMPORT LONG time();
TVEC tvec;
INTERN TEXT buf[] {"012345678901234567890123 GMT\n"};
putstr(STDOUT, atime(vtime(&tvec, time(NULL)), buf), NULL);

SEE ALSO

atime, ltime

## NAME

wdir - write directory to unmounted filesystem

## SYNOPSIS

```
VOID wdir(fd, pi)

FILE fd;

FINODE *pi;
```

## FUNCTION

wdir writes the last block obtained by rdir to the unmounted filesystem under control of fd. It is presumed that pi points at the inode that rdir has been reading.

Note well that this function is designed for sequential processing of one directory at a time, in conjunction with rdir.

## RETURNS

Nothing.

## EXAMPLE

```
for (i = 0; pd = rdir(fd, &ino, i); ++i)
    if (badlink(pd))
    {
       fixlink(pd);
       wdir(fd, &ino);
    }
}
```

## SEE ALSO

rdir

## NAME

who - read and sort who file

## SYNOPSIS

WHO \*who(n, fname)
COUNT \*n;
TEXT \*fname;

### FUNCTION

who allocates a buffer large enough to hold the specified file, reads the file contents into it, sorts the entries by tty name, then sets the integer at pn to the number of non-null entries found. The file is presumed to have records like the standard who and log files.

#### PETHENS

who returns a pointer to the allocated buffer if successful, otherwise  $\mathtt{NULL}$ .

## EXAMPLE

To print the names of the current system users:

```
IMPORT WHO *who();
WHO *pwho, *p;
COUNT n;

pwho = who(&n, WHOFILE);
for (p = pwho; 0 <= --n; ++pwho)
    putfmt("$b\n", p->w_uname, sizeof (p->w_uname));
free(pwho, NULL);
```