Supply Chain Planner (SCP)

Module-wise Test Steps

Manual execution guide - 11 modules in the regression order. Version 1.0, 28 Oct 2026. Environment: staging, project **NRVC_Hall**.

How to use this document

- Run the **Common pre-steps** first, then the module sections in order (1 to 11). Later modules reuse records created earlier: Supplier List and Project Management data feed Procurement Log, and Procurement Log deliveries feed Inventory, FDI and International Shipment.
- Use a unique run suffix (for example *RUN-2810-01*) in every name you create (material, supplier, submittal, user email) so records are traceable and do not clash.
- Record each step as Pass / Fail / Blocked. Use Blocked when a prerequisite (data, account, mailbox) is missing. Do not mark it Pass.
- Steps marked **[Write]** create or change data. Do them only on the approved project (NRVC_Hall) and never reuse completed FDI SUB-2026-525.
- Out of scope for this guide: Construction Delivery, Enterprise Shipments, and Integrations workflows.

Module order

#	Module	Scope
1	Project Management	Reference data, configuration, material master, checklists
2	User Management	Invite, activate, search and filter users
3	Supplier List	Create supplier, map materials, export
4	Procurement Log	Submittal to delivery, checklist and GRN
5	Inventory Management	Stock activities, balances, bulk upload, calendar
6	First Delivery Inspection	Assign, fill, submit and view inspections
7	International Shipment	Flag submittal, log and track shipment
8	Management Dashboard	Alerts, notifications, tasks, archive
9	Analytics	Reports, lead time, subcontractor issues
10	Enterprise	Enterprise view, inbox, performance, benchmarks
11	Document Management	All / Spec documents, uploads

Common pre-steps (all modules)

Login and project selection

#	Step	Expected result
1	Open the SCP staging URL in Chrome.	Login page is displayed.
2	Enter the admin email and password and click **Sign in**.	Login succeeds; the platform chooser is displayed. No SSO error.
3	On the platform chooser, select the **Supply Chain Planner** card and click **Open**.	SCP application opens with the left navigation.
4	From the header project selector, choose project **NRVC_Hall**.	Header shows NRVC_Hall; module data reloads for that project.
5	From the site selector, choose the allocated site (where applicable).	Selected site is shown in the header.
6	Expand each left-navigation group (Project Management, User Management, Analytics, Enterprise, Reference Data, Document Management, Reports).	All 11 modules the account is entitled to are listed. Modules the account must not see are absent and cannot be opened by direct URL.

Access check per user role (repeat for each account)

#	Step	Expected result
1	Log in with each role account (Admin, Organization Admin, Supplier, Subcontractor).	Login succeeds.
2	Note which modules appear in the left navigation and which action buttons (Invite Users, Add Supplier, Add Submittal, + Log Shipment) are visible.	Matches the agreed role access matrix.
3	For a module that is hidden for the role, paste its URL directly (for example /international-shipments).	Access denied or redirect. Opening the page is an access defect.

Module 1. Project Management

Purpose: Set up the reference and configuration data that the other modules depend on.

Navigation: Left navigation > Project Management (opens Material Master by default).

1.1 Reference Data - Common Utilities [Write]

#	Step	Expected result
1	Open **Reference Data > Common Utilities**.	Common Utilities list is displayed.
2	Click **Add**, choose type Currency, enter a unique name and save.	Success message; record saved.
3	Search the new name.	The new utility is shown in results.
4	Edit the record, change the name and save; search the new name.	Updated name is shown; old name returns no result.

1.2 Reference Data - Common UoM and Material Category [Write]

#	Step	Expected result
1	Open **Reference Data > Common UoM**; add a unique UoM, then edit it.	Updated UoM appears in search results.
2	Open **Reference Data > Material Category**; add a unique category, then edit it.	Updated category appears in search results.

1.3 Material Master [Write]

#	Step	Expected result
1	Open **Material Master** and click Add.	Add material form opens.
2	Click Save with the form empty.	Required-field errors are shown for each mandatory field; nothing is saved.
3	Enter a unique material name, category, UoM and SKU; save.	Material is created.
4	Search the material.	Material appears with the entered category and UoM.

1.4 Configuration Options [Write]

#	Step	Expected result
1	Open **Configuration Options**.	Current alert values and currency are shown.
2	Change the Project Management alert values and save; reload the page.	New values persist after reload.
3	Switch the project currency and save; reload.	Selected currency persists. (Restore the original value afterwards.)

1.5 First Delivery Inspection Config [Write]

#	Step	Expected result
1	Open **First Delivery Inspection Config**.	Settings, inspectors and questions sections are shown.
2	Toggle one FDI setting (for example photo required) and save; reload.	Setting persists.
3	Open First Delivery Inspections.	Controls matching the enabled settings are available.
4	Add a unique FDI question with an answer type.	Question is listed.
5	Invite a new FDI inspector with a unique Yopmail address.	Inspector shows as Pending acceptance.
6	In a separate (incognito) browser, open the mailbox, accept the invite, set the password and complete profile and address.	Account is activated; user can log in and open First Delivery Inspections.
7	Back in the Admin session, reopen FDI Config.	Inspector is Active and Enabled; Admin session still active.
8	Disable the inspector; in the incognito browser try to self-assign an inspection.	Inspector shows Disabled and cannot self-assign.

1.6 Inventory Control, PreShipping Checklist, Procurement Log Configuration, Site Details [Write]

#	Step	Expected result
1	Open **Inventory Control**; check required fields; add a balance rule.	Rule is listed.
2	Open **PreShipping Checklist**; create a question; enable it with Text answer type for Procurement Log; reload.	Question remains enabled with Text type.
3	Open **Procurement Log Configuration**; check required fields; add a field.	Field is listed.
4	Open **Site Details**; check required fields; add a unique site.	New site is listed.

1.7 Watched Materials, System Messages and other pages

#	Step	Expected result
1	Open **Watched Materials**; add a watch for the new category.	Watch is created.
2	Open Management Dashboard.	Same watched category is displayed.
3	Open **System Messages**; create a message [Write].	Message is created successfully.
4	Open **Bulk Upload Status**.	Each upload shows uploader, file name and Success/Failure. A row with no status is a defect.
5	Open **Submittal Manager**.	Page loads and shows the "being repurposed" notice (notice-only check).

Notes / known limits

- Restore any project setting you changed (currency, alert values, FDI setting) at the end of the run.

Module 2. User Management

Purpose: Invite, activate and manage users and their organisation and role.

Navigation: Left navigation > User Management.

2.1 Page and negative checks

#	Step	Expected result
1	Open User Management.	User list with filters, search and Rows per page is shown; **Invite Users** button visible for Admin.
2	Click **Invite Users** and click **Send Invites** with no email.	Validation error; no invite is sent.

2.2 Invite and activate [Write]

#	Step	Expected result
1	Click Invite Users, enter a unique Yopmail address, select role/project, click Send Invites.	Success message; user listed as invited/pending.
2	In an incognito window open the mailbox, open the invite link, set the password, complete the profile.	Account activated.
3	Log in as the new user in the same incognito window.	Login succeeds with the invited role.
4	In the Admin session, search the user by email.	User row shows Active status, correct role and organisation.
5	Open the User Profile, click **Change Associated Organization**, choose another organisation and Confirm.	New organisation shown in the list.

2.3 Filter and search

#	Step	Expected result
1	Click **Filter**, choose Status = Active, click **Apply Filter**.	Only Active users listed.
2	Filter by project role, then by organisation.	Every row matches the selected value.
3	Search an existing user name.	Matching user shown.
4	Search a random non-existent string.	No records; clearing restores the list.

Notes / known limits

- Needs a controllable mailbox (Yopmail) and a unique email per run.

Module 3. Supplier List

Purpose: Create suppliers and map them to materials with lead times.

Navigation: Left navigation > User Management > Supplier List.

3.1 Form validation (no save)

#	Step	Expected result
1	Click **Add Supplier** and click Save with empty fields.	Required-field errors; nothing saved.
2	Enter valid values, then Cancel.	Dialog closes; no new supplier in the list.

3.2 Create, map and export [Write]

#	Step	Expected result
1	Click Add Supplier, enter a unique supplier name and details, Save.	Supplier appears in the list.
2	Search the supplier.	Exactly that supplier is returned.
3	Click **Export**.	File downloads and contains the new supplier.
4	Click **Bulk Map Material to Supplier** / **Map Suppliers to Materials**.	Mapping dialog opens.
5	Filter by supplier name and by material name (use the material from Module 1).	Lists narrow to the entered names.
6	Select supplier and material, click Continue, enter Default Lead Time (e.g. 2 or 0.5), Save.	Mapping saved and shown for the supplier.

Module 4. Procurement Log

Purpose: Track a submittal from creation through ordering, delivery, pre-shipping checklist and GRN.

Navigation: Left navigation > Procurement Log.

4.1 Search (read-only)

#	Step	Expected result
1	Search an existing submittal number.	Record shows the correct project, site and material.
2	Search a random unique string, then reset.	No match; reset restores the same record set.
3	Open the record and check its component.	Component date, quantity and UoM match what was saved.

4.2 Full flow [Write]

#	Step	Expected result
1	Click **Add Submittal**; enter a unique submittal number and required fields; save.	Submittal is listed.
2	Click **Add Component**; choose the material (Choose Materials / Choose Item Name) and supplier (Choose Suppliers); enter quantity and required-on-site date; save.	Component shown under the submittal.
3	Select the delivery site.	Site saved on the component.
4	Click **Order**; enter PO no. and PO Date; confirm.	Component status changes to Ordered.
5	Click **+ Log Delivery** / **Add Delivery**; enter full quantity and the delivery location; save.	Delivery is logged.
6	Click **Add Pre-Shipping Details**; answer every checklist question; **Confirm Checklist**.	Checklist completed.
7	Click **Approve** on the checklist.	Checklist approved.
8	Update the actual delivery date.	New date saved.
9	Generate the initial GRN.	GRN PDF is stored against the delivery (file name and size visible).
10	Click **Add Shipping Info**; Choose Shipping Mode; enter Shipping Reference Number; save.	Shipping info saved.
11	Click **Add Delivery Conditions**; enter conditions; save.	Conditions saved.
12	Generate the final GRN.	Final GRN stored for the same delivery ID.

Notes / known limits

- Keep the submittal number - Modules 5, 6 and 7 use this delivery.

Module 5. Inventory Management

Purpose: Record stock movements and check balances for delivered materials.

Navigation: Left navigation > Inventory Management. Prerequisite: a completed delivery from Module 4.

5.1 Views and search (read-only)

#	Step	Expected result
1	Open Inventory Management; search the delivered material (Search inventory...).	Material shown with the delivered quantity as stock.
2	Search a non-existent value, then reset.	No match; reset restores the list.
3	Open the Location, Submittals and UoM views.	Same material identity in each view; quantities consistent.

5.2 Add Activity [Write]

#	Step	Expected result
1	Click **Add Activity**; click ADD with each mandatory field left empty in turn (including Comments*).	Each omission is rejected with an error.
2	Enter 0 or a negative quantity.	Rejected.
3	Internal Movement with the same From and To location.	Rejected.
4	Issue more than the available stock.	Rejected; stock unchanged.
5	Internal Movement of exactly the available stock to another location.	Saved; site total unchanged; balances move between locations.
6	Record Issue To Construction, Loss and Return.	Each appears in history; balance changes by the entered quantity.
7	Receive again against the fully delivered schedule.	Rejected; stock and history unchanged.

5.3 Bulk upload [Write]

#	Step	Expected result
1	Download the template; fill rows for Internal Movement, Issue To Construction, Loss and Return; upload.	All rows processed; balances and history updated.
2	Upload a file containing one overdraft row.	Whole file rejected (no partial update); error file can be downloaded.

5.4 Activity calendar and filters

#	Step	Expected result
1	Open the activity calendar without changing dates.	Default range = today minus 2 months to today plus 1 month.
2	Change the From/To dates.	Only activities inside the inclusive range are shown.
3	Filter by location and by site.	Balances limited to the chosen location/site.
4	Pick an activity date in the form before submitting.	Selected date stays visible.

Notes / known limits

- Known application issues: activity date-picker loop and incorrect default range; Reset is not exposed.

Module 6. First Delivery Inspection

Purpose: Assign, complete and review inspections for first deliveries.

Navigation: Left navigation > First Delivery Inspections. Prerequisite: a delivered component (Module 4) and FDI settings (Module 1.5).

6.1 List and filters (read-only)

#	Step	Expected result
1	Open First Delivery Inspections.	List shows material, supplier, submittal, delivery date, status and inspector.
2	Filter by material, supplier, status and assigned inspector, one at a time.	Every row matches the filter.
3	Filter by a delivery-date range whose edges equal a record date.	Boundary records are included.
4	Combine filters; then apply a no-match filter and click reset/clear.	Combined result correct; no-match shows none; reset restores list.
5	Open a Completed inspection.	Report is read-only.

6.2 Fill and submit [Write]

#	Step	Expected result
1	On the new delivery row, click **Self Assign** (or Assign Inspector).	Inspector shown on the row.
2	Click **Fill Inspection Report**; answer some questions; **Save Progress**; reopen.	Answers kept in the draft.
3	Attach a non-image file (PDF) as a photo.	Rejected; saved answers kept.
4	Click **Add photo** and upload a PNG and a JPG; browse with Next photo / Enlarge.	Thumbnails shown; viewer works.
5	Reassign the draft to another inspector, then back.	Answers retained.
6	Submit with a required answer or required photo missing.	Submission blocked; draft retained.
7	Complete all answers, mark PASS/observation, click **Submit Inspection** and **Yes, submit**.	Status Completed; report opens read-only with photos.
8	Trigger provider sync.	Sync feedback is shown once.

Notes / known limits

- Never reuse completed FDI SUB-2026-525. Settings changes affect only the selected project.

Module 7. International Shipment

Purpose: Flag a submittal as international and track its shipment.

Navigation: Left navigation > International Shipments.

7.1 Page checks

#	Step	Expected result
1	Open International Shipments.	Page loads with Total International KPI and shipment list.
2	Click **+ Log Shipment** and save empty.	Validation errors; nothing saved.

7.2 Owned flow [Write]

#	Step	Expected result
1	Note the Total International KPI.	Baseline recorded.
2	In Procurement Log, create a new submittal (or use Module 4) and click **Flag as International Shipment**.	Record flagged.
3	Return to International Shipments.	Linked record visible; KPI increased by 1.
4	Click **Log new shipment**; enter origin country (e.g. China), city/port (e.g. Shenzhen), supplier and container; save.	Shipment listed against the same submittal.
5	Click **Edit shipping details**; change values; **Save changes**; reload.	Changes persist.
6	Set the shipment status; reload.	Status persists; no duplicate shipment created.

Notes / known limits

- Check direct-URL access for the Subcontractor role (open finding).

Module 8. Management Dashboard

Purpose: Monitor alerts, notifications and tasks for the selected project.

Navigation: Left navigation > Management Dashboard.

8.1 Notifications, alerts and tasks

#	Step	Expected result
1	Open the dashboard.	Defaults to the current user's Unread items for the selected project.
2	Switch Read / Unread / All.	All = Read + Unread with no duplicates.
3	Check Alerts cards; expand and collapse.	Card counts match listed alerts.
4	Check Alerts distribution, category and ageing charts.	All required charts present.
5	Compare Notifications pie / category counts with the list.	Counts match the list.
6	Compare Tasks pie and category totals with the task list.	Totals equal unique task records.

8.2 Dates and archive

#	Step	Expected result
1	Change the ageing date range; then choose a single day.	Data limited to the range; boundary day included.
2	Restore default dates.	Original data returns.
3	Task Chart.	Starts October 2025; ends today.
4	Check the archive period setting options.	Configured period shown; all supported options available.

Notes / known limits

- Known failures: task rendering/count, ageing date scope, missing Alert charts.

Module 9. Analytics

Purpose: Review project reports and calculations.

Navigation: Left navigation > Analytics (expand the group).

9.1 Reports

#	Step	Expected result
1	Open Aggregate Stats, Forecast/TOV and Financial reports.	Tables load; totals equal the sum of rows.
2	Open EPD report.	Counts, status distribution and embodied-carbon totals add up.
3	Open Emission Report.	Grouped mass, distance and units reconcile.
4	Open Inventory Report.	Uses the selected project; consumption records shown.
5	Open Status Report.	Quantity columns match the record values.

9.2 Lead Time Analysis and Subcontractor Issues

#	Step	Expected result
1	Open Lead Time Analysis.	Category averages and benchmark comparisons shown; zero values displayed as 0.
2	Open Subcontractor Issues.	Total records shown; repeated subcontractor names kept as separate rows.
3	Search a subcontractor name; reset.	All matching rows; reset restores all.
4	Search a no-match value; reset.	No stale rows; reset restores.
5	Page through results and export.	No record lost; export has all records and all seven values.

Module 10. Enterprise

Purpose: Cross-project view of submittals, supplier performance and lead-time benchmarks.

Navigation: Left navigation > Enterprise (Enterprise View, Supplier Inbox, Supplier Performance, Lead Time Benchmarks). Read-only.

10.1 Enterprise View

#	Step	Expected result
1	Collapse and reopen the Enterprise group.	All four entries remain.
2	Open Enterprise View.	Cards, status totals and project roll-up are consistent.
3	Change the header project.	Enterprise scope does not narrow to that project.
4	Check supplier spend percentages.	Percentages add to 100% and match spend values.
5	Set a single-day range, then a historical range; export CSV.	Summary and CSV respect the selected dates.

10.2 Supplier Inbox

#	Step	Expected result
1	Filter by project, material and supplier; reset.	Every expanded section respects the filter; reset restores.
2	Use Pending With (All / Supplier / Sub-contractor).	Rows filtered by checklist ownership.
3	Open a component.	Opens the same record in Procurement Log.

10.3 Supplier Performance and Lead Time Benchmarks

#	Step	Expected result
1	Open Supplier Performance; switch 6 / 12 months.	KPIs and rows shown; aggregates unchanged by bucket.
2	Open Lead Time Benchmarks; check cards and category values.	Completed, on-time, late and delay cards shown.
3	Sort each column both ways.	No records lost.

Notes / known limits

- Known failures: zero values shown as dashes; Inbox capped at 100 records; missing component summary.

Module 11. Document Management

Purpose: View and manage project documents.

Navigation: Left navigation > Document Management (All Documents, Spec Documents).

11.1 Documents

#	Step	Expected result
1	Open All Documents.	Records, project total and pagination shown.
2	Search a no-match value.	Zero records.
3	Open Spec Documents.	File name, status, uploader and specification shown.
4	Download a document.	File downloads with the correct name and size.
5	In PO / BOM upload, choose an unsupported file type.	Rejected before upload; no data changed.

Notes / known limits

- Known issue: existing download returns 404.