Answers to Homework 1

1 How do clustered systems differ from multiprocessor systems? What is required for two machines belonging to a cluster to cooperate to provide a highly available service?

Answer: Clustered systems are typically constructed by combining multiple computers into a single system to perform a computational task distributed across the cluster. Multiprocessor systems on the other hand could be a single physical entity comprising of multiple CPUs. A clustered system is less tightly coupled than a multiprocessor system.

Clustered systems communicate using messages, while processors in a multiprocessor system could communicate using shared memory. In order for two machines to provide a highly available service, the state on the two machines should be replicated and should be consistently updated. When one of the machines fail, the other could then take-over the functionality of the failed machine.

2 Some computer systems do not provide a privileged mode of operation in hardware. Is it possible to construct a secure operating system for these computer systems? Give arguments both that it is and that it is not possible.

Answer: An operating system for a machine of this type would need to remain in control (or monitor mode) at all times. This could be accomplished by two methods:

- a. Software interpretation of all user programs (like some BASIC, Java, and LISP systems, for example). The software interpreter would provide, in software, what the hardware does not provide.
- b. Require meant that all programs be written in high-level languages so that all object code is compiler-produced. The compiler would generate (either inline or by function calls) the protection checks that the hardware is missing.
- **3** Define the essential properties of the following types of operating systems:
- a. Batch
- b. Interactive
- c. Time sharing
- d. Real time

- e. Network
- f. Parallel
- g. Distributed
- h. Clustered
- i. Handheld

Answer:

- a. **Batch**. Jobs with similar needs are batched together and run through the computer as a group by an operator or automatic job sequencer. Performance is increased by attempting to keep CPU and I/O devices busy at all times through buffering, off-line operation, spooling, and multiprogramming. Batch is good for executing large jobs that need little interaction; it can be submitted and picked up later.
- b. **Interactive**. This system is composed of many short transactions where the results of the next transaction may be unpredictable. Response time needs to be short (seconds) since the user submits and waits for the result.
- c. **Time sharing**. This systems uses CPU scheduling and multiprogramming to provide economical interactive use of a system. The CPU switches rapidly from one user to another. Instead of having a job defined by spooled card images, each program reads its next control card from the terminal, and output is normally printed immediately to the screen.
- d. **Real time**. Often used in a dedicated application, this system reads information from sensors and must respond within a fixed amount of time to ensure correct performance.
- e. **Network**. Provides operating system features across a network such as file sharing.
- f. **SMP**. Used in systems where there are multiple CPU's each running the same copy of the operating system. Communication takes place across the system bus.
- g. **Distributed**. This system distributes computation among several physical processors. The processors do not share memory or a clock. Instead, each processor has its own local memory. They communicate with each other through various communication lines, such as a high-speed bus or local area network.
- h. **Clustered**. A clustered system combines multiple computers into a single system to perform computational task distributed across the cluster.
- i. **Handheld**. A small computer system that performs simple tasks such as calendars, email, and web browsing. Handheld systems differ from traditional

desktop systems with smaller memory and display screens and slower processors.

4 What is the purpose of interrupts? What are the differences between a trap and an interrupt? Can traps be generated intentionally by a user program? If so, for what purpose?

Answer: An interrupt is a hardware-generated change-of-flow within the system. An interrupt handler is summoned to deal with the cause of the interrupt; control is then returned to the interrupted context and instruction. A trap is a software-generated interrupt. An interrupt can be used to signal the completion of an I/O to obviate the need for device polling. A trap can be used to call operating system routines or to catch arithmetic errors.

6 Give two reasons why caches are useful. What problems do they solve? What problems do they cause? If a cache can be made as large as the device for which it is caching (for instance, a cache as large as a disk), why not make it that large and eliminate the device?

Answer: Caches are useful when two or more components need to exchange data, and the components perform transfers at differing speeds. Caches solve the transfer problem by providing a buffer of intermediate speed between the components. If the fast device finds the data it needs in the cache, it need not wait for the slower device. The data in the cache must be kept consistent with the data in the components. If a component has a data value change, and the datum is also in the cache, the cache must also be updated. This is especially a problem on multiprocessor systems where more than one process may be accessing a datum. A component may be eliminated by an equal-sized cache, but only if: (a) the cache and the component have equivalent state-saving capacity (that is, if the component retains its data when electricity is removed, the cache must retain data as well), and (b) the cache is affordable, because faster storage tends to be more expensive.