



OPTIMIZATION TIER


MODULE 14

# Profiling

Measurement and optimization for ML systems

# Module 14: Profiling


## Optimization Begins with with Measurement




You cannot optimize what you cannot measure.

# The Optimization Landscape

A structured approach to improving performance through iterative analysis and refinement.




# What Are We Measuring?



## Model Size (Parameters)

Count (Millions/Billions)

Storage, Fixed Memory Cost.



## Computational Cost (FLOPs)

Floating Point Operations

Theoretical complexity, Energy.



## Memory Footprint

Peak MB/GB

Batch size limits, OOM errors.




## Latency

Milliseconds (ms)

User experience, Throughput.

# Why Measurement is Hard


## Noise & Variance



OS interrupts and background processes create jitter.

Solution: Statistical aggregation  
(Median over Mean).

## Cold Starts



Caches are empty and Python is interpreting on the first run.

Solution: Warmup iterations.

## Memory Complexity



Garbage collection obscures real usage.

Solution: tracemalloc snapshots.

# The Profiler Class Architecture

```
class Profiler
```

```
    __init__()
```

Initialize trackers.

Static

```
    count_parameters(model)
```

Static analysis.

Static

```
    count_flops(model, input_shape)
```

Theoretical cost.

Static

```
    measure_memory(model, input_shape)
```

Dynamic tracking.

Dynamic

```
    measure_latency(model, input_tensor)
```

Statistical timing.

Dynamic

```
    profile_forward_pass(model)
```

Synthesis.

Synthesis

# Concept 1: Counting Parameters

## The Math

Parameters = Weights + Biases.

For Linear(in, out):

Total =  $(in \times out) + out$

Every parameter is a float32 (4 bytes).

Count is invariant to batch size.

## Example: GPT-2 Layer



Linear(768, 3072)

Weights:  $768 \times 3072 = 2,359,296$

Bias: 3072

Total: 2,362,368 params

Memory: ~9.45 MB

# Implementation: count\_parameters

```
def count_parameters(self, model) -> int:  
    total_params = 0  
  
    # 1. Handle models with standard PyTorch-style API  
    if hasattr(model, 'parameters'):  
        for param in model.parameters():  
            total_params += param.data.size  
  
    # 2. Handle single layers (Linear, Conv2d) directly  
    elif hasattr(model, 'weight'):  
        total_params += model.weight.data.size  
  
        # Don't forget the bias!  
        if hasattr(model, 'bias') and model.bias is not None:  
            total_params += model.bias.data.size  
  
    return total_params
```

We count elements here.  
Conversion to bytes  
happens later.


# Concept 2: FLOP Counting

Floating Point Operations (Hardware Independent Work)

A FLOP is a single addition, subtraction, multiplication, or division.

Efficiency Formula:

$$\text{Efficiency} = \frac{\text{Measured FLOPs}}{\text{Hardware Peak FLOPs}}$$



$$\text{Operations} = 2 \times M \times N \times K$$


Why 2? Because each dot product requires 1 multiply + 1 add.

# Implementation: count\_flops

```
def count_flops(self, model, input_shape: Tuple[int, ...]) -> int:  
    total_flops = 0  
  
    if model.__class__.__name__ == 'Linear':  
        # Linear: (batch * in) @ (in * out)  
        # FLOPs = batch_size * in_features * out_features * 2  
        in_features = input_shape[-1]  
        out_features = model.weight.shape[1]  
  
        # Batch size is implicit in input_shape[0]  
        batch_size = np.prod(input_shape[:-1])  
  
        total_flops = batch_size * in_features * out_features * 2  
  
    return total_flops
```

Crucial difference: FLOPs depend on input size (batch), Parameters do not.

# Concept 3: The Three Types of Memory



**Insight:** Most Out-Of-Memory (OOM) errors come from Activations (batch size too high) or Optimizer states, not the model weights themselves.

# Implementation: measure\_memory

```
import tracemalloc

def measure_memory(self, model, input_shape):
    tracemalloc.start() # 1. Start tracking system allocations

    # 2. Calculate theoretical parameter size
    param_count = self.count_parameters(model)
    param_mb = (param_count * 4) / (1024 * 1024)


    # 3. Create dummy input & Run Forward Pass
    dummy_input = Tensor(np.random.randn(*input_shape))
    _ = model.forward(dummy_input)

    # 4. Capture peak usage ←
    current, peak = tracemalloc.get_traced_memory()
    tracemalloc.stop()

    peak_mb = peak / (1024 * 1024)
    return {'parameter_mb': param_mb, 'peak_mb': peak_mb}
```

Peak captures overhead  
+ temporary buffers.

# Concept 4: Latency & Statistics



## Statistical Robustness:

1. **Cold Starts:** Python imports and CPU wake-up skew the first run.
2. **Outliers:** OS interrupts cause spikes.
3. **Rule:** Always use the Median, never the Mean.

# Implementation: measure\_latency

```
def measure_latency(self, model, input_tensor,
                    warmup=10, iterations=100) -> float:
    # 1. Warmup Phase (Results ignored)
    for _ in range(warmup):
        _ = model.forward(input_tensor)


    # 2. Measurement Phase
    times = []
    for _ in range(iterations):
        start = time.perf_counter() # Use high-res timer ←
        _ = model.forward(input_tensor)
        end = time.perf_counter()
        times.append((end - start) * 1000) # Convert to ms

    # 3. Statistical Aggregation (Median)
    return float(np.median(times))
```

Note: `time.perf_counter()` is preferred over `time.time()` for nanosecond precision.

# Bottleneck Identification

## Compute-Bound




**Sign:** High Arithmetic Intensity (High GFLOP/s).  $\uparrow$  G GFLOP/s

**Constraint:** Processor Speed.  $\rightarrow$

**Examples:** Large Matrix Multiplications, Convolutions

**Fix:** Faster hardware, Quantization.  $\downarrow$  bit

## Memory-Bound



**Sign:** Low Arithmetic Intensity (Low GFLOP/s).  $\downarrow$  G GFLOP/s

**Constraint:** Memory Bandwidth.  $\leftarrow$

**Examples:** Element-wise ops, Activations, Attention

**Fix:** Kernel Fusion, Caching, smaller batches.

The Roofline Concept: You are limited by whichever is slower: doing the math, or moving the data.

# Implementation: profile\_forward\_pass

```
def profile_forward_pass(self, model, input_tensor):
    # Gather raw data
    flops = self.count_flops(model, input_tensor.shape)
    latency_ms = self.measure_latency(model, input_tensor)

    # Calculate derived metrics
    latency_sec = latency_ms / 1000.0

    # GFLOP/s = (Total FLOPs / 1e9) / Time in Seconds
    gflops_per_sec = (flops / 1e9) / latency_sec ←

    return {
        'flops': flops,
        'latency_ms': latency_ms,
        'gflops_per_sec': gflops_per_sec,
        'bottleneck': 'memory' if gflops_per_sec < 10 else 'compute'
    }
```


Note: GFLOP/s calculation (Billion Floating Point Operations per Second) is crucial for determining compute vs. memory bounds. The threshold of 10 is illustrative.

# Profiling the Backward Pass (Training)

Why training is expensive


**3X Compute**

Training takes ~3x the FLOPs of inference  
(1 Forward + 2 Backward passes)



**4X Memory**

Training requires ~4x the Parameter Memory  
(Params + Gradients + Optimizer States)



Adam Optimizer:

1. Parameters (1x)
2. Gradients (1x)
3. Momentum State (1x)
4. Velocity State (1x)

A 1GB model can easily require 4GB+ VRAM to train.

# Implementation: profile\_backward\_pass

```
def profile_backward_pass(self, model, input_tensor):
    fwd = self.profile_forward_pass(model, input_tensor)

    # Heuristic Estimates
    backward_flops = fwd['flops'] * 2
    total_flops = fwd['flops'] + backward_flops

    # Optimizer Memory (Adam Estimate)
    grad_mem = fwd['parameter_memory_mb']
    optim_mem = grad_mem * 2

    return {
        'total_flops': total_flops,
        'total_memory_mb': fwd['peak_memory_mb'] + optim_mem,
        'training_latency_est': fwd['latency_ms'] * 3
    }
```

# User Utilities: quick\_profile

What you will use in assignments

```
>>> quick_profile(model, input_data)
```

⌚ Quick Profile Results:

Parameters: 12,500

FLOPs: 4,000,000

Latency: 0.15 ms

Memory: 2.10 MB

Bottleneck: Memory Bound

Efficiency: 5.0%

# Production Context: TinyTorch vs. PyTorch

Feature	TinyTorch API	PyTorch API
Parameter Counting	<code>count_parameters()</code>	<code>sum(p.numel() for p in model.parameters())</code>
Latency	<code>time.perf_counter()</code> (CPU)	<code>torch.profiler / CUDA Events</code> (GPU)
Memory	<code>tracemalloc</code>	<code>torch.cuda.memory_allocated()</code>

The concepts (Warmup, FLOPs, Memory types) are identical; only the API changes.

# Module Summary

**Parameters:**

The static “weight” of the model.

**FLOPs:**

The hardware-independent “work” required.

**Memory:**

Includes dynamic Activations (batch dependent) and static Parameters.


**Latency:**

The real-world time, measured statistically (Median) after Warmup.

**Bottleneck:**

The limiting factor—Compute speed vs. Memory bandwidth.

# What's Next: Quantization (Module 15)



1. **Measure**: We now know our parameters take up X MB.
2. **Transform**: We will compress weights to int8.
3. **Validate**: We will use this Profiler to prove the 4x reduction.

See you in Module 15.