

Oursms.com REST API Document

Version 1.0

This document describes the HTTP Rest API that can be used to integrate and send SMS through Oursms advanced gateway.

1. **To get new account** , [sign up here](#)
2. **To get API token**, [watch This video](#)

3. Authentication:

The authentication is done using an API token passed in the HTTP request authorization header. The token should be passed as a bearer token scheme. You can create API tokens from the API keys manager in your account.

An example request header:

Authorization: Bearer YWxhZMRpbjpvGVuc2VzYW1s

4. Send Message:

This API is used to send a message to one or more recipients.

Method: POST

Url: <https://api.oursms.com/messages>

Body type: JSON

```
{
  "src": "oursms",
  "dests": ["96654XXXXXX", "96656XXXXXX"],
  "body": "Hello",
  "priority": 0,
  "delay": 0,
  "validity": 0,
  "maxParts": 0,
  "dlr": 0,
  "prevDups": 0,
  "msgClass": "promotional"
}
```

src	string Mandatory	The number or text that will appear to the receiver on the mobile device as the sender (sender Id)
dests	string array Mandatory	An array of destination addresses (mobile numbers) to deliver the message to. It can be one destination or multiple destinations up to 500 per request
body	string Mandatory	The text of the message. The text can be in any language. Our system will automatically detect the best encoding to be used when delivering the message.
Priority	int Optional	Default: 0 The priority of the message. The value can be any number from 1 to 4. 1 is the highest priority. If not set or set to 0 a smart algorithm will detect the best priority for the message and set it automatically.
delay	int Optional	Default: 0 The number of minutes to hold the message in the queue before sending it to the receiver. If set to 0 the message will be sent immediately.
validity	int Optional	Default: 0 The number of minutes the message will be valid to send. If for any reason the message was not sent within the validity period, the sending process will be aborted, and the message will be marked as expired. If set to 0 the validity will be the max period.
dlr	int Optional	Default: 0 Request a deliver status report for the message if the route supports it. Setting the value to 1 means a dlr is required.
prevDups	int Optional	Default: 0 This parameter triggers the prevent duplicate process for the message. The value represents the number of minutes to go back and check if an identical message to the current has already been sent. If an identical message has been sent within the period of the value, the message will be rejected.
msgClass	string Optional	Default: empty The msg class that should be taken into consideration when routing the msg. The current supported classes are: - transactional - promotional

Result:

If the request succeeded a HTTP response with the status 200 will be returned with the results in the body as json. However, if the request fails a failed HTTP response will be returned with a json body containing the error code and error description that occurred.

5. Download Dlr:

This API is used to get the Dlr from the user's inbox. Each dlr returned to the client will be deleted from the inbox.

Method: GET

Url: <https://api.oursms.com/inbox/dlrs?count=100>

count	int Optional	Default: 100 The number of dlrs to receive. The maximum amount is 500.
-------	-----------------	---

Result:

If the request succeeded a HTTP response with the status 200 will be returned with the data in the body as json. However, if the request fails a failed HTTP response will be returned with a json body containing the error code and error description that occurred.

6. Get Credits Balance:

This API is used to get the remaining credits in the user's account.

Method: GET

Url: <https://api.oursms.com/billing/credits>

Result:

If the request succeeded a HTTP response with the status 200 will be returned with the data in the body as json. However, if the request fails a failed HTTP response will be returned with a json body containing the error code and error description that occurred.