


Playing sound.





How sound works.














Sound wave properties.






Sound frequency.


hertz (Hz) = 1 cycle per second.




220 HZ



440 HZ




880 HZ





Complex waveforms.


Modulating frequency.




Hello











How digital sound works.

Digital sampling.




Sampling quality.


Sample rate and bits per sample.



Sample rate.


How many discrete samples per second (measured in Hz).





Bits per sample.

Sound quality and bits.



Audio waveform

Waveform sampled at 22 bits.

Wavefrom sampled at 16 bits.

Waveform sampled at 8 bits.

Bitrate.


Bitrate.


Sampling rate combined with bit depth.


Reflects the total bit count processed per second.

Measured in bits per second or bit/s (or bps)

Playing digital audio.







Playing digital sound involves filling an audio buffer with audio data on demand.

Audio Buffer

Playing audio with SDL2


SDL_mixer (the easy way).

Download SDL_mixer.

http://www.libsdl.org/projects/SDL_mixer/


```
Development Libraries:
 Windows
   SDL2_mixer-devel-2.0.0-VC.zip (Visual C++ 32/64-bit)
   SDL2_mixer-devel-2.0.0-mingw.tar.gz (MinGW 32/64-bit)
 Mac OS X
   <u>SDL2_mixer-2.0.0.dmg</u> (Intel 10.5+)
 Linux
   Please contact your distribution maintainer for updates.
 iOS & Android
   Projects for these platforms are included with the <u>source</u>.
```

On Mac




DRAG FROM FINDER

▼ ☐ Frameworks
 ▶ ☐ SDL2_mixer.framework
 ▶ ☐ OpenAL.framework
 ▶ ☐ SDL2_image.framework
 ▶ ☐ OpenGL.framework
 ▶ ☐ SDL2.framework
 ▶ ☐ Cocoa.framework
 ▶ ☐ XCTest.framework
 ▶ ☐ Other Framework
 ▶ ☐ Other Frameworks
 ▼ ☐ Products
 ▶ ☐ NYUCodebase.app



On Windows




RIGHT CLICK PROJECT

```
ıtion 'NYUCodebase' (1 project)
                                       #include <SDL image.h>
YUCo base
              Build
 External Dep
              Rebuild
■ Header Files
                                                 dow* displayWindow;
■ Application
              Project Only
a b Bullet.h
              Scope to This
                                                 n(int argc, char *argv[])
a b Entity.h
              New Solution Explorer View


■ SheetSpri

              Build Dependencies
Source Files
                                               __Init(SDL_INIT_VIDEO);
 Resource
              Add
                                               playWindow = SDL_CreateWindow(
a++ Application
              Class Wizard...
                                      Ctrl+Shift+X
                                                 _GLContext context = SDL_GL_Cre
a ★ Bullet.cpr
              Manage NuGet Packages...
                                                 _GL_MakeCurrent(displayWindow,
• Entity.cpr
at+ main.cpp
              Set as StartUp Project
SheetSpri
                                               1 done = false;
              Debug
              Source Control
                                                 _Event event;
              Cut
                                      Ctrl+X
                                                 le (!done) {
                                      Del
              Remove
                                                   while (SDL_PollEvent(&event))
                                      F2
              Rename
                                                        if (event.type == SDL_QUIT
              Unload Project
                                                              done = true;
              Rescan Solution
              Open Folder in File Explorer
              Properties
                                                   SDL_GL_SwapWindow(displayWindo
```


Add C:\SDL_mixer\include to additional library directories



ADD SDL2_mixer.lib to additional dependencies



Add C:\SDL_mixer\lib\x86 to additional library directories



Do the same thing for both Release and Debug configurations.

Copy all DLL files from C:\SDL_mixer\lib\x86 to where all the other DLL files are in your project.

Initializing SDL_mixer

Include SDL_mixer header.

```
#include <SDL_mixer.h>
```

```
int Mix_OpenAudio(int frequency, Uint16 format, int channels,
int chunksize);
```

Initializes SDL_mixer with frequency, format, channel and buffer size.

```
Mix_OpenAudio(44100, MIX_DEFAULT_FORMAT, 2, 4096);
```

Loading and playing sounds.

Loading a sound.

```
Mix_Chunk *someSound;
someSound = Mix_LoadWAV("some_sound.wav");
```

Playing a sound.

```
int Mix_PlayChannel(int channel, Mix_Chunk *chunk, int loops);
```

Plays a sound on specified channel. You can pass -1 for **channel** to use the first available channel. Loops can be **-1 to loop forever**.

```
Mix_PlayChannel( -1, someSound, 0);
```

Loading and playing music.

Loading music.

```
Mix_Music *music;
music = Mix_LoadMUS( "music.mp3" );
```

Playing music.

int Mix_PlayMusic(Mix_Music *music, int loops);

Plays specified music. Loops can be -1 to loop forever.


```
Mix_PlayMusic(music, -1);
```

Cleaning up.

Need to clean up music and sounds on quit.

```
DemoApp::~DemoApp() {
    Mix_FreeChunk(someSound);
    Mix_FreeMusic(music);
    SDL_Quit();
}
```

Pure audio buffer (the hard way).



Need to add SDL_INIT_AUDIO to SDL_Init flags.

```
SDL_Init(SDL_INIT_VIDE0|SDL_INIT_AUDIO);
```

Define your audio callback function.

```
void myAudioCallback(void *userdata, Uint8 *stream, int len) {
}
```

Open an audio device with your callback and desired settings.

```
SDL_AudioSpec deviceSpec;
deviceSpec.freq = 44100; // sampling rate (samples a second)
deviceSpec.format = AUDIO_F32; // audio format
deviceSpec.channels = 1; // how many channels (1 = mono, 2 = stereo)
deviceSpec.samples = 512; // audio buffer size in samples (power of 2)
deviceSpec.callback = myAudioCallback; // our callback function

// open new audio device with our requested settings
SDL_AudioDeviceID dev = SDL_OpenAudioDevice(NULL, 0, &deviceSpec, 0,
SDL_AUDIO_ALLOW_FORMAT_CHANGE);
SDL_PauseAudioDevice(dev, 0); // start playback on this device
```

The audio callback function will be **called by SDL every time it needs us to refill the audio buffer**.


Here is an example of an audio callback function that's generating a 440Hz tone at 44100 sample frequency in a one channel float buffer.

```
unsigned int numSamples = 0;

float getAudioForTime(long numSamples) {
    double elapsed = ((double)numSamples)/44100.0;
    return sin(elapsed * 2.0 * M_PI * 440.0);
}

void myAudioCallback(void *userdata, Uint8 *stream, int len) {
    for(int i=0; i < len/4; i++) {
        ((float*)stream)[i] = getAudioForTime(numSamples);
        numSamples++;
    }
}</pre>
```

Writing a simple mixer.



```
class MixerSound {
public:
    Uint32 offset;
    Uint32 length;
    Uint8 *buffer;
    float volume;
    SDL_AudioFormat format;
    bool loaded;
    bool playing;
    bool loop;
class DemoApp {
    public:
        std::vector<MixerSound> mixSounds;
```

Create a class for storing loaded sound buffers and some basic sound information. Our app will keep these in a vector.

```
int DemoApp::loadSound(const char *soundFile) {
   Uint8 *buffer;
   SDL_AudioSpec spec;
   Uint32 bufferSize;
   if(SDL_LoadWAV(soundFile, &spec, &buffer, &bufferSize) == NULL) {
       return -1;
                                                                        SDL_LoadWAV can only
   SDL AudioCVT cvt;
   SDL_BuildAudioCVT(&cvt, spec.format, spec.channels, spec.freq,
deviceSpec.format, deviceSpec.channels, deviceSpec.freq);
                                                                                load .wav files.
   cvt.len = bufferSize;
   cvt.buf = new Uint8[bufferSize * cvt.len_mult];
   memcpy(cvt.buf, buffer, bufferSize);
   SDL ConvertAudio(&cvt);
   SDL_FreeWAV(buffer);
   MixerSound sound;
   sound.buffer = cvt.buf;
   sound.length = cvt.len_cvt;
   sound.loaded = true;
   sound.offset = 0;
   sound.format = deviceSpec.format;
   sound.volume = 1.0;
                                                 someSound = loadSound("some_wave_file.wav");
   sound.playing = false;
   mixerSounds.push_back(sound);
   return mixerSounds.size()-1;
```

```
float mixSamples(float A, float B) {
    if (A < 0 && B < 0 ) {
        return (A + B) - (A * B)/-1.0;
    } else if (A > 0 && B > 0 ) {
        return (A + B) - (A * B)/1.0;
    } else {
        return A + B;
void DemoApp::appAudioCallback(void *userdata, Uint8 *stream, int len) {
    ClassDemoApp *app = (DemoApp*) userdata;
    memset(stream, 0, len);
    for(int i=0; i < app->mixerSounds.size(); i++) {
        MixerSound *sound = &app->mixerSounds[i];
        if(sound->loaded && sound->playing) {
            for(int s=0; s < len/4; s++) {
                float *sourceBuffer = (float*) (sound->buffer+sound->offset);
                ((float*)stream)[s] = mixSamples(((float*)stream)[s],(sourceBuffer[s] * sound->volume));
            sound->offset += len;
            if(sound->offset >= sound->length-len) {
                if(sound->loop) {
                    sound->offset = 0;
                } else {
                    sound->playing = false;
```

deviceSpec.callback = DemoApp::appAudioCallback;
deviceSpec.userdata = (void*)this;

Playing a sound.

```
void DemoApp::playSound(int soundIndex, bool loop) {
   if(soundIndex >= 0 && soundIndex < mixerSounds.size()) {
      mixerSounds[soundIndex].playing = true;
      mixerSounds[soundIndex].offset = 0;
      mixerSounds[soundIndex].loop = loop;
   }
}</pre>
```

```
playSound(someSound, false);
```

Sound resources.

SFXR

http://www.superflashbros.net/as3sfxr/

GENERATOR	MANUAL SETTINGS	
PICKUP/COIN	SQUAREWAVE SANTOOTH SINEWAVE NOISE	
LASER/SHOOT	ATTACK TIME	
EXPLOSION	SUSTAIN TIME 0.5.35 X	
	SUSTAIN PUNCH CLICK ON LABELS	
POWERUP	START FREQUENCY TO RESET SLIDERS	
HIT/HURT	MIN FREQUENCY COPY/PASTE SETTINGS	
JUMP	SLIDE TO SHARE SOUNDS	
John	DELTA SLIDE BASED ON SFXR BY	
BLIP/SELECT	VIBRATO DEPTH TOMAS PETTERSSON	
	CHANGE AMOUNT VOLUME	
	CHANGE SPEED PLAY SOUND	
	SQUARE DUTY	
	DUTY SWEEP	
MUTATE	PHASER OFFSET LOAD SOUND	
HOTHIE	PHASER SWEEP SAVE SOUND	
RANDOMIZE	LP FILTER CUTOFF	
васк	LP FILTER CUTOFF SWEEP EXPORT .WAY	
EODIJODS	LP FILTER RESUNHNCE	
FORWARD	HP FILTER CUTOFF SWEEP44100 HZ	
SFBTOM	PLAY ON CHANGE [16-BIT	

Free Music Archive

http://freemusicarchive.org/



Assignment.

- Add **sound** and **music** to a previous game.
- Start thinking about your final project.