Numerical Analysis & Scientific Computing II

Lesson 4

Numerical Solution of PDE

4.3 Hyperbolic PDE



Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$.

Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$. Then,

$$\frac{dU}{dt} = \frac{\partial u}{\partial x} \frac{d(x_0 + ct)}{dt} + \frac{\partial u}{\partial t} \equiv 0.$$

Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$. Then,

$$\frac{dU}{dt} = \frac{\partial u}{\partial x} \frac{d(x_0 + ct)}{dt} + \frac{\partial u}{\partial t} \equiv 0.$$

So $U(t) = U(0) = u(x_0, 0) = u_0(x_0)$ where u_0 is the initial data.



For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$. Then,

$$\frac{dU}{dt} = \frac{\partial u}{\partial x} \frac{d(x_0 + ct)}{dt} + \frac{\partial u}{\partial t} \equiv 0.$$

So $U(t) = U(0) = u(x_0, 0) = u_0(x_0)$ where u_0 is the initial data.

Thus, for $x \in \mathbb{R}$, t > 0, we have

$$u(x,t) = u((x-ct) + ct, t) = u_0(x-ct).$$



For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$. Then,

$$\frac{dU}{dt} = \frac{\partial u}{\partial x} \frac{d(x_0 + ct)}{dt} + \frac{\partial u}{\partial t} \equiv 0.$$

So $U(t) = U(0) = u(x_0, 0) = u_0(x_0)$ where u_0 is the initial data.

Thus, for $x \in \mathbb{R}$, t > 0, we have

$$u(x,t) = u((x-ct) + ct, t) = u_0(x-ct).$$

We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0).

Numerical Methods for PDE: Hyperbolic PDE

For the first example, we take the advection equation

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0,$$

where c is a constant. We consider an initial value problem so that the function u = u(x, t) is given when t = 0 and is to be found for t > 0.

The spatial domain can be an interval in which case we will need to impose boundary conditions to obtain a well posed initial value-boundary value problem, or the entire real line (no boundaries) for which the pure initial value problem is well-posed.

For the solution of the pure initial value problem, if u is the exact solution, consider $U(t) = u(x_0 + ct, t)$. Then,


$$\frac{dU}{dt} = \frac{\partial u}{\partial x} \frac{d(x_0 + ct)}{dt} + \frac{\partial u}{\partial t} \equiv 0.$$

So $U(t) = U(0) = u(x_0, 0) = u_0(x_0)$ where u_0 is the initial data.


Thus, for $x \in \mathbb{R}$, t > 0, we have

$$u(x,t) = u((x-ct) + ct, t) = u_0(x-ct).$$


Numerical Methods for PDE: Hyperbolic PDE




Numerical Methods for PDE: Hyperbolic PDE




Numerical Methods for PDE: Hyperbolic PDE



Numerical Methods for PDE: Hyperbolic PDE




Numerical Methods for PDE: Hyperbolic PDE



Numerical Methods for PDE: Hyperbolic PDE

We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.


Suppose that the spatial domain is an interval, say (0,1).





We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.


Suppose that the spatial domain is an interval, say (0,1).



Numerical Methods for PDE: Hyperbolic PDE

We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.

Suppose that the spatial domain is an interval, say (0,1).




Numerical Methods for PDE: Hyperbolic PDE

We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.

Suppose that the spatial domain is an interval, say (0,1).

For determining solution at (x,t) with x - ct < 0, we need boundary condition at x = 0. This can be specified for all t > 0, and reads u(0,t) = g(t) for a given g.






We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.

Suppose that the spatial domain is an interval, say (0,1).

For determining solution at (x,t) with x - ct < 0, we need boundary condition at x = 0. This can be specified for all t > 0, and reads u(0,t) = g(t) for a given g.

Thus, to obtain a well-posed problem, we need

$$\begin{split} \frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} &= 0, 0 < x < 1, t > 0, \\ u(x, 0) &= u_0(x), 0 < x < 1, \\ u(0, t) &= g(t), t > 0. \end{split}$$



Numerical Methods for PDE: Hyperbolic PDE

We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.

Suppose that the spatial domain is an interval, say (0,1).

For determining solution at (x,t) with x - ct < 0, we need boundary condition at x = 0. This can be specified for all t > 0, and reads u(0,t) = g(t) for a given g.


Thus, to obtain a well-posed problem, we need

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0, 0 < x < 1, t > 0,$$

$$u(x, 0) = u_0(x), 0 < x < 1,$$

$$u(0, t) = g(t), t > 0.$$

The only boundary condition needed is on the left or inflow boundary. It is not necessary or permissible to impose a boundary condition on the right or outflow boundary.





We, therefore, see that the pure initial value problem for advection equation can be solved analytically/exactly. The initial data simply travels to the right with speed c (for c > 0). The solution u is constant along the lines $\{(x_0 + ct, t): t > 0\}$ called the characteristics of the equation.

Suppose that the spatial domain is an interval, say (0,1).

For determining solution at (x,t) with x - ct < 0, we need boundary condition at x = 0. This can be specified for all t > 0, and reads u(0,t) = g(t) for a given g.

Thus, to obtain a well-posed problem, we need

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0, 0 < x < 1, t > 0,$$

$$u(x, 0) = u_0(x), 0 < x < 1,$$


$$u(0, t) = g(t), t > 0.$$



Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.



Numerical Methods for PDE: Hyperbolic PDE

Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.

If we change dependent variable by v = Su, then we get

$$\frac{\partial v}{\partial t} + D \frac{\partial v}{\partial x} = 0,$$



Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.

If we change dependent variable by v = Su, then we get

$$\frac{\partial v}{\partial t} + D \frac{\partial v}{\partial x} = 0,$$

that is,

$$\frac{\partial v_i}{\partial t} + d_i \frac{\partial v_i}{\partial x} = 0, \qquad i = 1, \dots, n.$$

Numerical Methods for PDE: Hyperbolic PDE

Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.

If we change dependent variable by v = Su, then we get

$$\frac{\partial v}{\partial t} + D \frac{\partial v}{\partial x} = 0,$$

that is,

$$\frac{\partial v_i}{\partial t} + d_i \frac{\partial v_i}{\partial x} = 0, \qquad i = 1, \dots, n.$$

Thus, the system decouples into n advection equations whose speeds are the eigenvalues of the original coefficient matrix.



Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.

If we change dependent variable by v = Su, then we get

$$\frac{\partial v}{\partial t} + D \frac{\partial v}{\partial x} = 0,$$

that is,

$$\frac{\partial v_i}{\partial t} + d_i \frac{\partial v_i}{\partial x} = 0, \qquad i = 1, \dots, n.$$

Thus, the system decouples into n advection equations whose speeds are the eigenvalues of the original coefficient matrix.

Example:

Consider the wave equation

$$\frac{\partial^2 w}{\partial t^2} = \frac{\partial^2 w}{\partial x^2}.$$



Now consider a system of the form

$$\frac{\partial u}{\partial t} + C \frac{\partial u}{\partial x} = 0,$$

where C is an $n \times n$ symmetric matrix (that is, has real eigenvalues). Suppose $C = S^{-1}DS$ with S invertible and D a diagonal matrix.

If we change dependent variable by v = Su, then we get

$$\frac{\partial v}{\partial t} + D \frac{\partial v}{\partial x} = 0,$$

that is,

$$\frac{\partial v_i}{\partial t} + d_i \frac{\partial v_i}{\partial x} = 0, \qquad i = 1, \dots, n.$$

Thus, the system decouples into n advection equations whose speeds are the eigenvalues of the original coefficient matrix.

Example:

Consider the wave equation

$$\frac{\partial^2 w}{\partial t^2} = \frac{\partial^2 w}{\partial x^2}.$$

Let $u_1 = \partial w/\partial t$ and $u_2 = \partial w/\partial x$. Then,



Example:

Consider the wave equation

$$\frac{\partial^2 w}{\partial t^2} = \frac{\partial^2 w}{\partial x^2}.$$

Let
$$u_1 = \partial w/\partial t$$
 and $u_2 = \partial w/\partial x$. Then,

$$\left[\frac{\partial}{\partial t}\begin{bmatrix} u_1 \\ u_2 \end{bmatrix} + \begin{bmatrix} 0 & -1 \\ -1 & 0 \end{bmatrix} \frac{\partial}{\partial x}\begin{bmatrix} u_1 \\ u_2 \end{bmatrix} = 0.$$

Numerical Methods for PDE: Hyperbolic PDE

Example:

Consider the wave equation

$$\frac{\partial^2 w}{\partial t^2} = \frac{\partial^2 w}{\partial x^2}.$$

Let $u_1 = \partial w/\partial t$ and $u_2 = \partial w/\partial x$. Then,

$$\frac{\partial}{\partial t} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} + \begin{bmatrix} 0 & -1 \\ -1 & 0 \end{bmatrix} \frac{\partial}{\partial x} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} = 0.$$

Thus,

$$C = \begin{bmatrix} 0 & -1 \\ -1 & 0 \end{bmatrix} = S^{-1}DS, \qquad S = \begin{bmatrix} 1 & 1 \\ 1 & -1 \end{bmatrix}, \qquad D = \begin{bmatrix} -1 & 0 \\ 0 & 1 \end{bmatrix}.$$



Example:

Consider the wave equation

$$\frac{\partial^2 w}{\partial t^2} = \frac{\partial^2 w}{\partial x^2}.$$

Let $u_1 = \partial w/\partial t$ and $u_2 = \partial w/\partial x$. Then,

$$\frac{\partial}{\partial t} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} + \begin{bmatrix} 0 & -1 \\ -1 & 0 \end{bmatrix} \frac{\partial}{\partial x} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} = 0.$$

Thus,

$$C = \begin{bmatrix} 0 & -1 \\ -1 & 0 \end{bmatrix} = S^{-1}DS, \qquad S = \begin{bmatrix} 1 & 1 \\ 1 & -1 \end{bmatrix}, \qquad D = \begin{bmatrix} -1 & 0 \\ 0 & 1 \end{bmatrix}.$$

Finally, we find the solution (u_1, u_2) from $u_1 + u_2$ which is a wave moving from right to left and from $u_1 - u_2$, a wave moving to the right.