Introduction

1.1 Motivation

Before going to study the course, let us try to motivate ourselves by asking the following five **Wh** questions.

- 1. What is Numerical Analysis?
- 2. Where is Numerical Analysis used?
- 3. When is Numerical Analysis required?
- 4. Who requires Numerical Analysis?
- 5. Why should we learn Numerical Analysis?

And, finally we ask the following:

How to do Numerical Analysis ?

1. What is Numerical Analysis?

Numerical Analysis is a branch of mathematics that deals with

(a) Developing approximation procedure (called Numerical Methods) to solve mathematical problems.

1. Introduction 2

(b) Developing efficient algorithm to implement the above approximation procedure as computer codes (called Implementation).

(c) Analyzing error for the above approximation procedure (a bit of error analysis, convergence, stability).

Numerical Analysis is not about playing with numerical values in computer. It is about mathematical ideas, insights.

What are Numerical methods?

They are algorithms to compute:

- (i) approximations of functions,
- (ii) approximations of derivatives of functions at some point,
- (iii) approximations of integrals of functions in some interval,
- (iv) approximations of solution/s of linear/nonlinear single/system of algebraic/differential equation/s.
- 2. Where is Numerical Analysis used?

(I will put a picture describing whole situation.)

3. When is Numerical Analysis required?

In the following situation one can go for numerical approximations:

- (a) The mathematical problem is known to have solution but does not have any method to obtain exact analytical expression.
- (b) Mathematical problem is very difficult to handle exactly.
- (c) There is a lack of enough data about the inputs for the mathematical problem and therefore not possible to use the available exact methods.
- 4. Who requires Numerical Analysis?

Everyone working in the field of science and engineering field. For eg:

- Mathematicians,
- Statisticians,
- · Physicists,
- · Chemists,
- Engineers, etc.
- 5. Why should we learn Numerical Analysis?

There are at least three reasons for which we need to learn and understand numerical methods.

- (a) Learning different numerical methods and their analysis will make a person more familiar with the techniques of developing new numerical methods. This is important because when the available methods are not enough or not efficient for a specific problem to solve.
- (b) In many situations, one has more methods for a given problem. Hence choosing an appropriate method is important for producing an accurate result in lesser time.
- (c) With a good enough knowledge of numerical methods, one can use it properly and efficiently to get solution of problems and understand what is going wrong if the results obtained are not expected.

Through the rest of the course we will answer 'How to do numerical analysis?'

1.2 Syllabus we are going to cover

(Already I mentioned in the class. This portion will be filled.)

1.3 Prerequisite

(Already I mentioned in the class. This portion will be filled.)

1. Introduction 4

2

Floating Point Approximation of Real Numbers and Error Analysis

We have known that Numerical Analysis is all about


- Developing approximation procedure called numerical methods, to approximate a solution of a given Mathematical problem (whenever a solution exists),
- Developing algorithms and implement them as computer codes,
- Analyzing error in numerical approximation.

Therefore, the approximate solution, obtained by numerical method, will involve an error which is precisely the difference between the exact solution and the approximate solution. Thus, we have

Exact Solution = Approximate Solution + Error.

This error is called the **Mathematical** error.

In the next step while developing the algorithm and implementing them as computer code, we use a set of numerical values to evaluate the approximate solution obtained in numerical method. After evaluation we obtain a set of numerical values which is called the **numerical solution** to the given Mathematical problem. Due to memory restrictions, a computing device can store only a finite number of digits. Therefore, a real number cannot be stored exactly. Certain approximation needs to be done, and only an



approximate value of the given number is stored in the device. For further calculations, this approximate value is used instead of the exact value of the number. Hence, during the process of computation, the computer introduces a new error, called the **arithmetic error**. Then, we note that

Approximate Solution = Numerical Solution + Arithmetic Error.

Therefore, we have

Exact Solution = Numerical Solution + Mathematical Error + Arithmetic Error.

The Total Error is defined as

Total Error = Mathematical Error + Arithmetic Error.

The error (arithmetic error) involved in the numerical solution when compared to the exact solution can be worse than the mathematical error.

In this chapter, we introduce the floating-point representation of a real number and see two method to obtain floating-point approximation of a given real number. We introduce different types of errors that we come across in numerical analysis and their effects in the computation. At the end of this chapter, we will be familiar with the arithmetic errors, their effect on computed results and some ways to minimize this error in the computation.

2.1 Floating-Point Representation

Let $\beta \in \mathbb{N}$, with $\beta \geqslant 2$. Let $x \in \mathbb{R}$ be a real number. The real number x can be represented in base β as

$$x := (-1)^s \times (.d_1 d_2 \dots d_t d_{t+1} \dots)_{\beta} \times \beta^e, \tag{2.1.1}$$

where $d_i \in \{0, 1, ..., \beta - 1\}$ for all $i \in \mathbb{N}$ with $d_1 \neq 0$ or $d_i = 0$, for all $i \in \mathbb{N}$, $s \in \{0, 1\}$, and $e \in \mathbb{Z}$. Here in above

- β is called the **base** or **radix**,
- s is called the **sign**,
- $(.d_1d_2...d_nd_{n+1}...)_{\beta}$ is called the **mantissa**,
- e is called the **exponent**,

of the given number x. The representation (2.1.1) of a real number is called the **floating-point representation**. The mantissa part can also be written as

$$(.d_1d_2...d_nd_{n+1}...)_{\beta} = \sum_{i=1}^{\infty} \frac{d_i}{\beta^i}.$$
 (2.1.2)

We note that the right hand side of (2.1.2) is convergent series in \mathbb{R} and hence is well defined.

Remark 2.1.1. We note the following.

- When $\beta = 2$, the floating-point representation (2.1.1) is called the binary floating-point representation.
- When $\beta = 10$, the floating-point representation (2.1.1) is called the **decimal** floating-point representation.

There are other representation of real numbers. For example octal with $\beta = 8$, hexadecimal (used in ancient China) with $\beta = 16$, vigesimal (used in France) with $\beta = 20$ etc. In the course we will consider $\beta = 10$.

2.1.1 Floating-Point Number System in a Computing Device

Due to memory restrictions, a computing device can store only a finite number of digits in the mantissa. In this section, we introduce the floating-point approximation and discuss how a given real number can be approximated.

A computing device stores a real number with only a finite number of digits in the mantissa. Although different computing devices have different ways of representing the numbers, here we introduce a mathematical form of this representation, which we will use throughout this course.

Definition 2.1.1 (*n*-digit floating point number). Let $\beta \in \mathbb{N}$, with $\beta \geqslant 2$. An *n*-digit floating point number x_f in base β is of the form

$$x_f := (-1)^s \times (.d_1 d_2 \dots d_n)_{\beta} \times \beta^e$$
 (2.1.3)

where $d_i \in \{0, 1, ..., \beta - 1\}$ for all i = 1, 2, ..., n, with $d_1 \neq 0$ or $d_i = 0$, for all i = 1, 2, ..., n, $s \in \{0, 1\}$, $e \in \mathbb{Z}$ is an appropriate exponent. Here

$$(.d_1d_2...d_n)_{\beta} = \sum_{i=1}^n \frac{d_i}{\beta^i}.$$
 (2.1.4)

The number of digits n in the mantissa is called the **precision** or **length** of the floating-point number.

Remark 2.1.2. We note the following.

- When $\beta = 2$, the n-digit floating-point representation (2.1.1) is called the n-digit binary floating-point representation. This is used in computer.
- When $\beta = 10$, the n-digit floating-point representation (2.1.1) is called the n-digit decimal floating-point representation. It is used in daily life computation.

Example 2.1.1. The following are examples of real numbers in the decimal floating point representation.

(i). The real number $x_f = 2347$ is represented in the decimal floating-point representation as

$$x_f = (-1)^0 \times .2347 \times 10^4.$$

In the above, we note that $\beta = 10$, s = 0, $d_1 = 2$, $d_2 = 3$, $d_3 = 4$, $d_4 = 7$, e = 4.

(ii). The real number $y_f = -0.000739$ is represented in the decimal floating-point representation as

$$y_f = (-1)^1 \times .739 \times 10^{-3}$$
.

In the above, we note that $\beta = 10$, s = 1, $d_1 = 7$, $d_2 = 3$, $d_3 = 9$, e = -3.

Remark 2.1.3. Any computing device has its own memory limitations in storing a real number. In terms of the floating-point representation, these limitations lead to the restrictions in the range of the exponent (e) and the number of digits in the mantissa (n).

2.1.2 Characterization of Floating-Point Number System in a Computing Device

For a given computing device, there are integers $L, U, n \in \mathbb{Z}$ such that the exponent e is limited to a range

$$L \leqslant e \leqslant U$$
,

and n is the precision. Therefore, a floating point number system, denoted by \mathbb{F} , is characterized by four integer $\beta, n \in \mathbb{N}, L, U \in \mathbb{Z}$ such that

- β = base or radix,
- *n*= precision,
- L=lower bound of the exponent range,
- *U*=upper bound of the exponent range.

Any floating point number $x_f \in \mathbb{F}$, can be represented as in (2.1.3).

2.1.3 Properties of \mathbb{F}

- (i). The *n*-digit floating-point representation of a number is unique.
- (ii). A floating point number system \mathbb{F} is finite and discrete.
- (iii). The total numbers in a given floating point number system is

$$2(\beta-1)\beta^{n-1}(U-L+1)+1.$$

Indeed, while counting the numbers, there are

- 2 choices of the sign s,
- $(\beta 1)$ number of choices of leading digit d_1 ,
- β number of choices of each of the remaining digits $d_2, d_2, \dots d_n$,
- (U-L+1) number of possible values of the exponent e.

Therefore, in total $2(\beta - 1)\beta^{n-1}(U - L + 1)$ numbers. Finally, 1 for number zero.

(iv). The mantissa $m(x_f) := (.d_1 d_2 ... d_n)_{\beta} = \sum_{i=1}^n \frac{d_i}{\beta^i}$ satisfies

$$\frac{1}{\beta} \leqslant m(x_f) < 1.$$

(v). The smallest positive floating point number is

UFL =
$$\beta^{L-1}$$
.

Indeed, for the smallest positive floating point number

- the sign, s = 0,
- the leading digit, $d_1 = 1$,
- the remaining digits, $d_2 = d_2 = \cdots = d_n = 0$,
- the exponent, e = L.

Hence,

UFL =
$$(.10...,0)_{\beta}\beta^{L} = \frac{1}{\beta}\beta^{L} = \beta^{L-1}$$
.

It is also called Under Flow Level (UFL).

(vi). The largest positive floating point number is

$$OFL = (1 - \beta^{-n})\beta^{U}.$$

Indeed, for the largest positive floating point number

- the sign, s = 0,
- all the digits, $d_1 = d_2 = d_2 = \cdots = d_n = (\beta 1)$,
- the exponent, e = U.

Hence,

$$\begin{split} \text{OFL} &= (.(\beta-1)(\beta-1)\dots(\beta-1))_{\beta}\beta^U, \\ &= \sum_{i=1}^n \frac{(\beta-1)}{\beta^i}\beta^U, \\ &= \frac{(\beta-1)}{\beta}\beta^U \left(1 + \frac{1}{\beta} + \dots + \frac{1}{\beta^{n-1}}\right), \\ &= \frac{(\beta-1)}{\beta}\beta^U \left(\frac{1 - \left(\frac{1}{\beta}\right)^n}{1 - \left(\frac{1}{\beta}\right)}\right), \\ &= \frac{(\beta-1)}{\beta}\beta^U \frac{(1 - \beta^{-n})}{\beta^n}, \end{split}$$

$$= (1 - \boldsymbol{\beta}^{-n}) \boldsymbol{\beta}^{U}.$$

It is also called Under Flow Level (OFL).

(vii). All floating point number $x_f \in \mathbb{F}$ must satisfies

$$UFL \leq |x_f| \leq OFL$$
.

- (viii). Floating point numbers are not uniformly distributed throughout their range, but they are equally spaced only between successive powers of β .
 - (ix). If an arithmetic operation leads to a result in which a computed number x satisfies |x| > OFL, then, the calculation may terminate. Then error occurs in the computation. It is called an overflow error.
 - (x). If an arithmetic operation leads to a result in which a computed number x satisfies |x| < UFL, then, the floating point representation of x (note that floating point representation of real number will be discussed in subsection 2.1.5) will be set to zero. This also makes error in the computation. It is called an underflow error.

In subsection 2.1.4, we introduce the concept of under and over flow of memory, which is a result of the restriction in the exponent. The restriction on the length of the mantissa is discussed in subsection 2.1.5.

2.1.4 Overflow and Underflow of Memory

- When the value of the exponent *e* in a floating-point number exceeds the maximum limit of the memory, we encounter the overflow of memory.
- When the value of the exponent *e* goes below the minimum of the range, then we encounter underflow.

During a computation,

- if some computed number x_f has an exponent e > U (this also occurs if $|x_f| >$ OFL) then we say, the memory **overflow** occurs.
- if e < L, (this also occurs if $|x_f| < \text{UFL}$) we say the memory **underflow** occurs.

and

Remark 2.1.4. We note the following.

(i). • In the case of overflow of memory in a floating-point number, a computer will usually produce meaningless results or simply prints the symbol inf or NaN.

- When a computation involves an undetermined quantity (like 0 × ∞, ∞ − ∞, 0/0), then the output of the computed value on a computer will be the symbol NaN (means 'not a number'). For instance, if x_f is a sufficiently large number that results in an overflow of memory when stored on a computing device, and y_f is another number that results in an underflow, then their product will be returned as NaN.
- (ii). On the other hand, we feel that the underflow is more serious than overflow in a computation. Because, when underflow occurs, a computer will simply consider the number as zero without any warning. The error is disguised in the computation and computer will not inform you about that whereas for the case of overflow computer will give you warning to modify the computer algorithm(code). If a computation involves such an underflow of memory, then there is a danger of having a large difference between the actual value and the computed value. However, by writing a separate subroutine, one can monitor and get a warning whenever an underflow occurs.

2.1.5 Floating-Point Approximation of Real Numbers

In general, a real number can have infinitely many digits, which a computing device cannot hold in its memory. Rather, each computing device will have its own limitation on the length of the mantissa. If a given real number has infinitely many digits in the mantissa of the floating-point form as in (2.1.1), then the computing device converts this number into an n-digit floating-point form as in (2.1.3). Such an approximation is called the **floating-point approximation** of a real number.

There are many ways to get floating-point approximation of a given real number. Here we introduce two types of floating-point approximations.

Definition 2.1.2 (Chopping). Let $x \in \mathbb{R}$ be a real number given in the floating-point representation (2.1.1) as

$$x = (-1)^{s} \times (.d_{1}d_{2} \dots d_{n}d_{n+1} \dots)_{\beta} \times \beta^{e}.$$
 (2.1.5)

The floating-point approximations of x using n-digit chopping is given by

$$f(x) = (-1)^s \times (.d_1 d_2 \dots d_n)_{\beta} \times \beta^e.$$
 (2.1.6)

The floating-point approximations of x using n-digit rounding is given by

$$f(x) = \begin{cases} (-1)^s \times (.d_1 d_2 \dots d_n)_{\beta} \times \beta^e &, & 0 \leqslant d_{n+1} < \frac{\beta}{2}, \\ (-1)^s \times (.d_1 d_2 \dots (d_n + 1))_{\beta} \times \beta^e &, & \frac{\beta}{2} \leqslant d_{n+1} < \beta, \end{cases}$$
(2.1.7)

where

$$(.d_1d_2...(d_n+1))_{\beta} = (.d_1d_2...(d_n)_{\beta} + (\underbrace{00...0}_{(n-1)- \text{ times}} 1)_{\beta},$$
$$= \sum_{i=1}^n \frac{d_i}{\beta^i} + \frac{1}{\beta^n}.$$

Remark 2.1.5. We note the following. If for a real number x, $d_{n+1} \geqslant \frac{\beta}{2}$ and $d_n = \beta - 1$, then in case of n-th digit rounding $d_n + 1$ in fl(x) would be β . Therefore, we put $d_n = 0$ and add 1 to d_{n-1} . Again, if $d_{n-1} = \beta - 1$, we put $d_{n-1} = 0$ and add 1 to d_{n-2} . We continue further if required until all the digits are exhausted. It may happen that $d_1 = d_2 = \cdots = d_n = \beta - 1$ and $d_{n+1} \geqslant \frac{\beta}{2}$, then for fl(x) we put $d_1 = 1$, all other $d_i = 0$ for $i = 2, 3, \ldots, n$ and increase the exponent by 1, if

$$x = (-1)^s \times (\underbrace{(\beta - 1)(\beta - 1)\dots(\beta - 1)}_{n-times} d_{n+1})_{\beta} \times \beta^e, \quad d_{n+1} \geqslant \frac{\beta}{2}$$

then in case of n-th digit rounding

$$f(x) = (-1)^s \times (\underbrace{100...0}_{(n-1)-times})_{\beta} \times \beta^{e+1}.$$

Example 2.1.2. (i). The floating-point representation of π is given by

$$\pi = (-1)^0 \times (.31415926...)_{10} \times 10^1.$$

The floating-point approximation of π using 5-digit chopping is given by

$$f(\pi) = (-1)^0 \times (.31415)_{10} \times 10^1.$$

The floating-point approximation of π using 5-digit rounding is given by

$$f(\pi) = (-1)^0 \times (.31416)_{10} \times 10^1.$$

because $d_6 = 9 \ge 5$. So in $f(\pi)$, $d_5 = 5 + 1 = 6$.

Remark 2.1.6. Most of the modern processors, including Intel, uses IEEE 754 standard format. This format uses 52 bits in mantissa, (64-bit binary representation), 11 bits in exponent and 1 bit for sign. This representation is called the **double precision**. number. When we perform a computation without any floating-point approximation, we say that the computation is done using **infinite precision** (also called **exact arithmetic**).

2.1.6 Arithmetic Operations of Floating-Point Approximations

In this subsection, we describe the procedure of performing arithmetic operations using n-digit rounding. The procedure of performing arithmetic operation using n-digit chopping can be done in a similar way.

Procedure of performing arithmetic operations

Let \odot denote any one of the basic arithmetic operations $+, -, \times, \div$. Let $x, y \in \mathbb{R}$ be two real numbers. The process of computing $x \odot y$ using *n*-digit rounding is as follows.

- Step 1: First, we consider the *n*-digit rounding approximations f(x) and f(y) of the numbers x and y, respectively.
- Step 2:Then, we perform the calculation $f(x) \odot f(y)$ using exact arithmetic.
- **Step 3:** Finally, we consider the *n*-digit rounding approximations $fl(fl(x) \odot fl(y))$ of $fl(x) \odot fl(y)$.

The result from **Step 3** is the value of $x \odot y$ using *n*-digit rounding.

Example 2.1.3. Let us consider the function $f:[0,\infty)\to\mathbb{R}$ given by

$$f(x) = x(\sqrt{x+1} - \sqrt{x}), \quad x \in \mathbb{R}.$$

We evaluate f(100000) using 6-digit rounding arithmetic. We have

$$f(100000) = 100000(\sqrt{100001} - \sqrt{100000})$$

We see that

$$\sqrt{100001} = 316.229347 \dots = .316229347 \dots \times 10^3,$$

and

$$\sqrt{100000} = 316.227766 \dots = .316227766 \dots \times 10^3.$$

Using 6-digit rounding we note that

$$f(\sqrt{100001}) = .316229 \times 10^3$$
, and $f(\sqrt{100000}) = .316228 \times 10^3$.

Then,

$$f(\sqrt{100001}) - f(\sqrt{100000}) = .000001 \times 10^3 = .1 \times 10^{-2}.$$

Hence,

$$f(f(\sqrt{100001}) - f(\sqrt{100000})) = .1 \times 10^{-2}.$$

Types of Errors

Again we see that fl(100000) = $.1 \times 10^{6}$. *Then,*

$$f(100000) \times f(f(\sqrt{100001}) - f(\sqrt{100000})) = .1 \times 10^6 \times .1 \times 10^{-2} = .01 \times 10^4 = .1 \times 10^3.$$

Finally, we have

$$f(f(100000)) = .1 \times 10^3 = 100.$$

Similarly, using 6-digit chopping, the value of fl(f(100000)) = 200.

2.2 Types of Errors

The approximate representation of a real number obviously differs from the actual number, whose difference is called an **error**.

Definition 2.2.1 (Errors). (i). The **error** in a computed quantity is defined as

Error = **True Value** - **Approximate Value**.

- (ii). Absolute value of an error is called the **absolute error**.
- (iii). The **relative error** is a measure of the error in relation to the size of the true value as given by

Relative Error =
$$\frac{\mathbf{Error}}{\mathbf{True\ Value}}$$
, Provided **True Value** $\neq 0$.

- (iv). Absolute value of the relative error is called the absolute relative error.
- (v). The percentage error is defined as

Percentage Error = $100 \times |\text{Relative Error}|$.

Remark 2.2.1. Let x_A denote the approximation to the real number $x \in \mathbb{R}$. We use the following notations.

$$E(x_A) := Error(x_A) = x - x_A. \tag{2.2.1}$$

$$E_a(x_A) := Absolute\ Error(x_A) = |x - x_A|. \tag{2.2.2}$$

$$E_r(x_A) := Relative\ Error(x_A) = \frac{x - x_A}{x}, \quad x \neq 0.$$
 (2.2.3)

$$E_{ar}(x_A) := Absolute \ Relative \ Error(x_A) = \left| \frac{x - x_A}{x} \right|, \quad x \neq 0.$$
 (2.2.4)

The absolute error has to be understood more carefully because a relatively small difference between two large numbers can appear to be large, and a relatively large

difference between two small numbers can appear to be small. On the other hand, the relative error gives a percentage of the difference between two numbers, which is usually more meaningful as illustrated below.

Example 2.2.1. (i). I will provide example here to say why Absolute Relative error is more important than Absolute error.

2.3 Sources of Errors

- Mathematical modeling of a physical problem.
- Uncertainty in physical data or empirical measurements.
- Errors from previous computations.
- Blunders in arithmetic computations or in methods.
- Machine Errors.
- Mathematical Truncation Error.

2.4 Machine Errors

In this chapter we will be discussing Machine Errors.

2.4.1 Errors in Floating-point Approximations

With most of real numbers $x \in \mathbb{R}$, we have $fl(x) \neq x$. We now measure the errors for floating for approximations of real numbers.

Theorem 2.4.1. Let $x \in \mathbb{R}$, $x \neq 0$ be such that $UFL \leq |fl(x)| \leq OFL$. Then,

$$E_{ar}(f(x)) \leqslant \begin{cases} \beta^{-n+1}, & \text{in case of chopping,} \\ \frac{1}{2}\beta^{-n+1}, & \text{in case of rounding.} \end{cases}$$

Proof. Let us assume that x has floating-point representation

$$x = (-1)^s \times (.d_1 d_2 \dots d_n d_{n+1} \dots)_{\beta} \times \beta^e = (-1)^s \beta^e \sum_{i=1}^{\infty} \frac{d_i}{\beta^i}.$$

First, We note that

$$|x| = \left| (-1)^s \beta^e \left(\sum_{i=1}^\infty \frac{d_i}{\beta^i} \right) \right| = \beta^e \sum_{i=1}^\infty \frac{d_i}{\beta^i} \geqslant \beta^e \frac{d_1}{\beta} \geqslant \beta^{e-1}. \tag{2.4.1}$$

17 Machine Errors

We prove the result for two cases separately.

Case of chopping : In case of *n*-digit chopping

$$fl(x) = (-1)^s \times (.d_1 d_2 \dots d_n)_{\beta} \times \beta^e = (-1)^s \beta^e \sum_{i=1}^n \frac{d_i}{\beta^i}.$$

Hence,

$$E_{a}(fl(x)) = |x - fl(x)| = \left| (-1)^{s} \beta^{e} \left(\sum_{i=1}^{\infty} \frac{d_{i}}{\beta^{i}} - \sum_{i=1}^{n} \frac{d_{i}}{\beta^{i}} \right) \right|,$$

$$= \left| \beta^{e} \left(\sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} \right) \right|,$$

$$= \beta^{e} \sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} \leqslant \beta^{e} \sum_{i=n+1}^{\infty} \frac{\beta - 1}{\beta^{i}},$$

$$= \beta^{e} (\beta - 1) \sum_{i=n+1}^{\infty} \frac{1}{\beta^{i}},$$

$$= \beta^{e} (\beta - 1) \frac{\frac{1}{\beta^{n+1}}}{1 - \frac{1}{\beta}} = \frac{\beta^{e}}{\beta^{n}} = \beta^{e-n}.$$

Using (2.4.1), we have

$$E_{ar}(\mathrm{fl}(x)) = \frac{|x - \mathrm{fl}(x)|}{|x|} \leqslant \frac{\beta^{e-n}}{\beta^{e-1}} = \beta^{-n+1}.$$

Case of rounding: Sub-case: $0 \le d_{n+1} < \frac{\beta}{2}$. We note that

$$fl(x) = (-1)^s \times (.d_1 d_2 \dots d_n)_{\beta} \times \beta^e = (-1)^s \beta^e \sum_{i=1}^n \frac{d_i}{\beta^i}.$$

Hence,

$$E_{a}(fl(x)) = |x - fl(x)| = \left| (-1)^{s} \beta^{e} \left(\sum_{i=1}^{\infty} \frac{d_{i}}{\beta^{i}} - \sum_{i=1}^{n} \frac{d_{i}}{\beta^{i}} \right) \right|,$$

$$= \left| \beta^{e} \left(\sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} \right) \right|,$$

$$= \beta^{e} \sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} = \beta^{e} \left\{ \frac{d_{n+1}}{\beta^{n+1}} + \sum_{i=n+2}^{\infty} \frac{d_{i}}{\beta^{i}} \right\},$$

$$\leq \beta^{e} \left\{ \frac{\frac{\beta}{2} - 1}{\beta^{n+1}} + (\beta - 1) \sum_{i=n+2}^{\infty} \frac{1}{\beta^{i}} \right\}$$

$$\left(\because 0 \leqslant d_{n+1} < \frac{\beta}{2} \implies 0 \leqslant d_{n+1} \leqslant \frac{\beta}{2} - 1, \text{ and } d_{i} \leqslant \beta - 1 \right)$$

$$\begin{split} &=\beta^{e}\left\{\frac{\beta-2}{2\beta^{n+1}}+(\beta-1)\frac{\frac{1}{\beta^{n+2}}}{1-\frac{1}{\beta}}\right\},\\ &=\beta^{e}\left\{\frac{\beta-2}{2\beta^{n+1}}+\frac{1}{\beta^{n+1}}\right\},\\ &=\beta^{e}\frac{\beta-2+2}{2\beta^{n+1}}=\beta^{e}\frac{\beta}{2\beta^{n+1}}=\frac{1}{2}\beta^{e-n}. \end{split}$$

Using (2.4.1), we have

$$E_{ar}(fl(x)) = \frac{|x - fl(x)|}{|x|} \le \frac{1}{2} \frac{\beta^{e-n}}{\beta^{e-1}} = \frac{1}{2} \beta^{-n+1}.$$

Case of rounding: Sub-case: $\frac{\beta}{2} \leqslant d_{n+1} < \beta$. We note that

$$fl(x) = (-1)^s \times (.d_1 d_2 \dots (d_n + 1))_{\beta} \times \beta^e = (-1)^s \beta^e \left(\sum_{i=1}^n \frac{d_i}{\beta^i} + \frac{1}{\beta^n} \right).$$

Hence,

$$E_{a}(\mathbf{fl}(x)) = |x - \mathbf{fl}(x)| = \left| (-1)^{s} \beta^{e} \left(\sum_{i=1}^{\infty} \frac{d_{i}}{\beta^{i}} - \sum_{i=1}^{n} \frac{d_{i}}{\beta^{i}} - \frac{1}{\beta^{n}} \right) \right|,$$

$$= \left| \beta^{e} \left(\sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} - \frac{1}{\beta^{n}} \right) \right|,$$

$$\left(\because \sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} \le (\beta - 1) \sum_{i=n+1}^{\infty} \frac{1}{\beta^{i}} = (\beta - 1) \frac{\frac{1}{\beta^{n+1}}}{1 - \frac{1}{\beta}} = \frac{1}{\beta^{n}} \right)$$

$$= \beta^{e} \left(\frac{1}{\beta^{n}} - \sum_{i=n+1}^{\infty} \frac{d_{i}}{\beta^{i}} \right)$$

$$\leq \beta^{e} \left(\frac{1}{\beta^{n}} - \frac{d_{n+1}}{\beta^{n+1}} \right)$$

$$\left(\because \frac{\beta}{2} \leqslant d_{n+1} \right)$$

$$\leq \beta^{e} \left(\frac{1}{\beta^{n}} - \frac{\beta}{2\beta^{n+1}} \right) = \frac{1}{2} \beta^{e-n}.$$

Finally, using (2.4.1), we have

$$E_{ar}(fl(x)) = \frac{|x - fl(x)|}{|x|} \le \frac{1}{2} \frac{\beta^{e-n}}{\beta^{e-1}} = \frac{1}{2} \beta^{-n+1}.$$

This completes the proof.

Remark 2.4.1. There are real numbers for which we have two types of floating point representation. For example, take $\beta = 10$ (decimal representation). The number 1 has two

19 Machine Errors

representation say

$$1 = (-1)^0 \times .100000000 \cdots \times 10^1 = x_1$$
, or $1 = (-1)^0 \times .9999999 \cdots \times 10^0 = x_2$.

In case of n-digit floating point approximation of 1 by **chopping**, we have (take for example n = 5),

$$fl(x_1) = .10000 \times 10^1$$
, but $fl(x_2) = .99999$.

In general we do not have unique n-digit floating point approximation for a given real number because it might not have unique floating point representation. See the example above.

The question is: Which representation of 1 does the computer convert into n-digit floating point approximation? The answer is: The computer uses that representation for which the error for the approximation is less. Here, in the above example computer uses x_1 for 1's floating point approximation and it does $fl(x_1) = .10000 \times 10^1$.

2.4.2 Accuracy of Floating-point Approximations

Unit round-off

We now introduce two measures that give a fairly precise idea of the possible accuracy in a floating-point approximation.

Definition 2.4.1 (Unit round-off (**u**)). *The* **unit round-off** *of a computer is denoted by* **u** *and is defined as*

$$\mathbf{u} = \sup \Big\{ E_{\mathbf{ar}}(f(\mathbf{x})) : \mathbf{x} \in \mathbb{R}, \ OFL \le |\mathbf{x}| \le UFL \Big\}.$$

i.e., it is the maximum possible value of $E_{ar}(f(x))$ for any x satisfying the condition as in Theorem 2.4.1.

Remark 2.4.2. By Theorem 2.4.1 we note that the subset

$$U := \left\{ E_{ar}(f(x)) : x \in \mathbb{R}, \ OFL \le |x| \le UFL \right\}$$

in the Definition 2.4.1 is non empty and bounded above. Therefore, by completeness axiom of real numbers, \mathbf{u} exists as a real number.

Actually, we have the following.

Theorem 2.4.2.

$$\mathbf{u} = \begin{cases} \beta^{-n+1}, & \text{in case of chopping,} \\ \frac{1}{2}\beta^{-n+1}, & \text{in case of rounding.} \end{cases}$$

Proof. See book: Atkinson: Introduction of Numerical Analysis, 2ed., p-15.

Alternative characterization of unit round-off

Definition 2.4.2 (Machine Epsilon(e_{mach})). The machine epsilon of a computer is denoted by ε_{mach} and is defined as

$$\varepsilon_{mach} = \inf \{ \delta \in \mathbb{F} : \delta > 0, \quad and \quad fl(1+\delta) > 1 \}.$$

Remark 2.4.3. We note that the subset

$$E_M := \{ \delta \in \mathbb{F} : \delta > 0, \quad and \quad fl(1+\delta) > 1 \}$$

in the Definition 2.4.2, is bounded below (by 0) and non empty as $1 \in E_M$. Indeed, fl(1+1) = 2 > 1. So 1 belongs to the set above. Therefore, by completeness axiom of real numbers, ε_{mach} exists as a real number.

Indeed, we have the following result.

Theorem 2.4.3.

$$\varepsilon_{mach} = \begin{cases} \beta^{-n+1}, & \text{in case of chopping,} \\ \frac{1}{2}\beta^{-n+1}, & \text{in case of rounding.} \end{cases}$$

Proof. See book: Atkinson: Introduction of Numerical Analysis, 2ed., p-15. (Hint of the proof): First we note that the number 1 van be represented as

$$1 = (.1 \underbrace{00...00}_{n-1-\text{times}}) \times \beta^1 = \left(\frac{1}{\beta}\right) \times \beta$$

We will consider $\delta \in \mathbb{F}$, so that $\mathrm{fl}(1+\delta) > 1$. The next larger number (than 1) in \mathbb{F} is

$$(.1\underbrace{00...00}_{n-2\text{-times}}1) \times \beta^1.$$

Therefore, first, we will find $\delta \in \mathbb{F}$, $\delta > 0$ so that

$$fl(1+\delta) = (.1\underbrace{00...00}_{n-2\text{-times}}1) \times \beta^1.$$

Among those δ 's, the smallest one will be ε_{mach} .

Case of chopping:

Consider
$$\delta_c = (\underbrace{00...00}_{n-1\text{-times}}1) \times \beta^1$$
. Therefore,

$$1 + \delta_c = (.1 \underbrace{00...00}_{n-2\text{-times}} 1) \times \beta^1$$

21 Machine Errors

and

$$fl(1 + \delta_c) = (.1\underbrace{00...00}_{n-2\text{-times}} 1) \times \beta^1 > 1.$$

We note that for any $\delta \geqslant \delta_c$, $\delta \in \mathbb{F}$ we have $\mathrm{fl}(1+\delta) \geqslant \mathrm{fl}(1+\delta_c) > 1$ and for $0 < \delta < \delta_c$, $\delta \in \mathbb{F}$ we have $\mathrm{fl}(1+\delta) = 1$. Hence,

$$\varepsilon_{mach} = \delta_c = (\underbrace{00...00}_{n-1\text{-times}} 1) \times \beta^1 = \beta^{-n+1}.$$

Case of rounding: Consider $\delta_r = (\underbrace{00...00}_{n\text{-times}} \frac{\beta}{2}) \times \beta^1$. Therefore,

$$1 + \delta_r = (.1\underbrace{00...00}_{n-1\text{-times}} \frac{\beta}{2}) \times \beta^1$$

and

$$fl(1 + \delta_r) = (.1 \underbrace{00...00}_{n-2 \text{ times}} 1) \times \beta^1 > 1.$$

We note that for any $\delta \geqslant \delta_r$, $\delta \in \mathbb{F}$ we have $\mathrm{fl}(1+\delta) \geqslant \mathrm{fl}(1+\delta_r) > 1$ and for $0 < \delta < \delta_r$, $\delta \in \mathbb{F}$ we have $\mathrm{fl}(1+\delta) = 1$. Indeed, the numbers $0 < \delta < \delta_r$ in \mathbb{F} is of the form

$$\delta = (\underbrace{00...00}_{n-\text{times}}(\frac{\beta}{2} - 1)d_{n+2}d_{n+3}...d_p) \times \beta^1.$$

We note that

$$1 + \delta = (.1\underbrace{00...00}_{n-1\text{-times}}(\frac{\beta}{2} - 1)d_{n+2}d_{n+3}...d_p) \times \beta^1$$

and

$$fl(1+\delta) = (.1\underbrace{00...00}_{n-1\text{-times}}) \times \beta^1 = 1.$$

Hence,
$$\varepsilon_{mach} = \delta_r = (\underbrace{00...00}_{n\text{-times}} \frac{\beta}{2}) \times \beta^1 = \left(\frac{\beta/2}{\beta^{n+1}}\right) \times \beta = \frac{1}{2}\beta^{-n+1}.$$

- **Remark 2.4.4.** (i). From the definition of ε_{mach} , we note that for any $\delta \in \mathbb{F}$ with $0 < \delta < \varepsilon_{mach}$ implies $fl(1+\delta) = 1$, i.e., in computer the number $1+\delta$ is identical with 1.
- (ii). We note that $\varepsilon_{mach} \neq UFL$. ε_{mach} is determined by the precision i.e., the number of digits in the mantissa field of floating-point system, whereas the UFL is determined by the lower bound in the exponent field.
- (iii). In all practical floating-point systems, we have

$$0 < UFL < \varepsilon_{mach} < OFL$$
.

(iv). For IEEE floating-point system

- $\varepsilon_{mach} = 2^{-24} \sim 10^{-7}$ in single precision,
- $\varepsilon_{mach} = 2^{-53} \sim 10^{-16}$ in double precision.

Therefore, IEEE single and double precision systems have about 7 and 16 decimal digits of precision, respectively.

Example 2.4.1. For 5-digit rounding with $\beta = 10$ we have $\varepsilon_{mach} = .5 \times 10^{-4}$. Let $\delta = .4 \times 10^{-4} < \varepsilon_{mach}$. Let us compute $1 + \delta$ using the exact arithmetic

$$1 + \delta = .100000 \times 10^{1} + .000004 \times 10^{1} = .100004 \times 10^{1}$$
.

Hence, using 5-digit rounding with $fl(1+\delta) = .10000 \times 10^1 = 1$.

Maximal Accuracy

Definition 2.4.3 (Maximal Accuracy). The maximal accuracy in a floating-point representation is denoted by M_{acc} and is defined as

$$M_{acc} = \sup \{ m \in \mathbb{Z} : m \geqslant 0, \quad and \quad fl(m) = m \}.$$

Remark 2.4.5. From the definition of maximal accuracy, we note that $f(M_{acc} + 1) \neq M_{acc} + 1$.

Theorem 2.4.4.

$$M_{acc} = \beta^n$$
.

Proof. See book: Atkinson: Introduction of Numerical Analysis, 2ed., p-16.

2.4.3 Loss of Significance

In place of relative error, we often use the concept of significant digits that is closely related to relative error.

Definition 2.4.4 (Significant digits). *Let us consider a floating-point number system with base* $\beta \in \mathbb{N}$ *with* $\beta \geqslant 2$. *For* $x \in \mathbb{R}$ *, let* x_A *be an approximation of* x. *Let*

$$s = s_x := \sup \left\{ k \in \mathbb{Z} : \beta^k \leqslant |x| \right\}$$
 and $r = r_{x,x_A} := \sup \left\{ t \in \mathbb{Z} : |x - x_A| \leqslant \frac{1}{2}\beta^{s+1-t} \right\}$.

Then, we say x_A has r significant digits to approximate x.

23 Machine Errors

Remark 2.4.6. We note in the above definition of Significant digits that $k \leq \frac{\ln |x|}{\ln \beta} < e$, where

$$x = (-1)^s \times (d_1 d_2 \dots d_n d_{n+1} \dots)_{\beta} \times \beta^e = (-1)^s \times m(x) \times \beta^e, x \neq 0$$

and m(x) =mantissa of x Indeed, by property (iv) in subsection 2.1.3,

$$\beta^{e-1} \le |x| = m(x)\beta^e < \beta^e,$$

 $e-1 \le \frac{\ln|x|}{\ln \beta} < e.$

This shows $e-1 \le s < e$. Hence, s=e-1. Again, if $x_A \ne x$, then

$$t \le s + 1 - \frac{\ln(2|x - x_A|)}{\ln \beta} = e - \frac{\ln(2|x - x_A|)}{\ln \beta}.$$

Therefore, the set

$$\left\{t \in \mathbb{Z} : |x - x_A| \leqslant \frac{1}{2}\beta^{s+1-t}\right\}$$

is a nonempty bounded subset of \mathbb{R} and hence r is a finite integer.

Example 2.4.2. We find significant digits for the following approximations.

(i).
$$x = \frac{1}{3} = .3333...$$
 and $x_A = .333$. We note that

$$10^{-1} = .1 < x$$
, hence, $s = -1$

and

$$|x - x_A| = (.0003333...) \le (.3333...) \times 10^{-3},$$

 $= \frac{1}{2} \times (.6666...) \times 10^{-3},$
 $< \frac{1}{2} \times 10^{-3} = \frac{1}{2} \times 10^{-1+1-3}$

Therefore, x_A has 3 significant digits to approximate x.

(ii). x = 23.496 and $x_A = 23.494$ We note that

$$10^1 < x$$
, hence, $s = 1$,

and

$$|x - x_A| = (.002) = .2 \times 10^{-2},$$

$$= \frac{1}{2} \times .4 \times 10^{-2},$$

$$< \frac{1}{2} \times 10^{-2} = \frac{1}{2} \times 10^{1+1-4}$$

Therefore, x_A has 4 significant digits to approximate x.

(iii). x = 0.02138 and $x_A = 0.02144$ We note that

$$10^{-2} < x$$
, hence, $s = -2$,

and

$$|x - x_A| = (.00006) = .6 \times 10^{-4},$$

$$= \frac{1}{2} \times 1.2 \times 10^{-4},$$

$$= \frac{1}{2} \times .12 \times 10^{-3},$$

$$< \frac{1}{2} \times 10^{-3} = \frac{1}{2} \times 10^{-2+1-2}$$

Therefore, x_A has 2 significant digits to approximate x.

Remark 2.4.7. (*i*). We note that

$$E_{ar}(x_A) = \frac{|x - x_A|}{|x|} \le \frac{1}{2} \frac{\beta^{s - r + 1}}{\beta^s} = \frac{1}{2} \beta^{1 - r}.$$

Hence, absolute relative error decreases with an increase in the number of significant digits.

- (ii). Number of significant digits roughly measures the number of leading non-zero digits of x_A that are correct relative to the corresponding digits in the true value x. However, this is **not a precise way** to get the number of significant digits as we have seen in the above examples.
- (iii). The role of significant digits in numerical calculations is very important in the sense that the loss of significant digits may result in drastic amplification of the relative error as illustrated in the following example.

Example 2.4.3. (Loss of Significance)

(i). Let us consider two real numbers

$$x = 7.6545428 = .76545428 \times 10^{1}, \quad y = 7.6544201 = .76544201 \times 10^{1}.$$

25 Machine Errors

Let

$$x_A = 7.6545421 = .76545421 \times 10^1, \quad y_A = 7.6544200 = .76544200 \times 10^1$$

be approximations of x and y respectively. Then

$$z = x - y = .00001227 = .12270000 \times 10^{-3}$$
, and $z_A = x_A - y_A = .12210000 \times 10^{-3}$

Therefore, the absolute relative error in the subtraction x - y is

$$\frac{|z - z_A|}{|z|} = .488997556 \times 10^{-2} < .5 \times 10^{-2}.$$

Therefore, z_A has only 2 significant digits to approximate z. Thus, we started with two approximate numbers x_A and y_A which are correct to 6 and 7 significant digits with respect to x and y respectively, but their difference z_A has only 2 significant digits with respect to z. Hence, there is a loss of significant digits in the process of subtraction.

Loss of significant digits is therefore dangerous. The loss of significant digits in the process of calculation is referred to as Loss of Significance.

(ii). Let us take the function $f:[0,\infty)\to\mathbb{R}$ given by

$$f(x) = x(\sqrt{x+1} - \sqrt{x}), \quad x \in \mathbb{R}.$$

We consider evaluating f(100000) using 6-digit rounding. We have seen in example 2.1.3 that the value of f(100000) using six-digit rounding is 100, whereas the true value is 158.113. There is a large amount (in compare to true value) of error in the value of the function, which is due to the loss of significant digits. It is evident that as x increases, the terms $\sqrt{x+1} - \sqrt{x}$ comes closer to each other and therefore loss of significance in their computed value increases. Such a loss of significance can be avoided by rewriting the given expression of f in such a way that subtraction of near-by non-negative numbers is avoided. For example, we can rewrite the expression of the function f as

$$f(x) = \frac{x}{\sqrt{x+1} + \sqrt{x}}, \quad x \geqslant 0.$$

With this new form of f, we obtain f(100000) = 158.114 using six-digit rounding.

(iii). Let us take the function $f: \mathbb{R} \to \mathbb{R}$ given by

$$f(x) = 1 - \cos x, \quad x \in \mathbb{R}.$$

We consider evaluating f(0). Since $\cos x \to 1$ for $x \to 0$, there will be loss of significance in the process of evaluating f(x) for x near zero. So, we have to use an alternative formula for such as

$$f(x) = 1 - \cos x = \frac{1 - \cos^2 x}{1 + \cos x} = \frac{\sin^2 x}{1 + \cos x}.$$

which can be evaluated quite accurately for small x.

(iv). Let us consider finding roots of the quadratic equation

$$ax^2 + bx + c = 0$$

for given $a,b,c \in \mathbb{R}$, $a \neq 0$. Further, assume b > 0 and $b^2 - 4ac > 0$. The equation has two distinct real roots, which are given by

$$r^{\pm} = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a}.$$

If 4ac is small compare to b^2 , then $\sqrt{b^2 - 4ac}$ will agree with b to several digits in floating point representation. Let us consider the example of finding roots of the quadratic equation

$$x^2 - 26x + 1 = 0.$$

By the above formula

$$r_T^+ = 13 + \sqrt{168}, \quad r_T^- = 13 - \sqrt{168}$$

In a computer with 5-digit decimal we get $\sqrt{168} = 12.961$. Then, denoting the approximated roots as

$$r_A^+ = 13 + 12.961 = 25.961, \quad r_A^- = 13 - 12.961 = .039.$$

Hence,

$$E_{ar}(r_A^+) \approx 1.85 \times 10^{-5}, \quad E_{ar}(r_A^-) \approx 1.25 \times 10^{-2}$$

For the data entering into the calculation above

$$x_T = 13 = x_A$$
, $y_T = \sqrt{168}$, $y_A = 12.961$.

$$E_{ar}(x_A) = 0$$
, $E_{ar}(y_A) \approx 3.71 \times 10^{-5}$.

The accuracy in r_A^- is much less than of the data x_A and y_A entering into the calculation. We say that significance digits have been lost in the subtraction

 $r_A^- = x_A - y_A$. In r_A^+ we have five significant digits (**chekc it!**) of accuracy, whereas we have only two significant digit (**chekc it!**) in r_A^- . The remedy of this situation of calculating r_A^- is to consider

$$r_T^- = 13 - \sqrt{168} = \frac{(13 - \sqrt{168})(13 + \sqrt{168})}{13 + \sqrt{168}} = \frac{1}{13 + \sqrt{168}}.$$

This yields

$$r_A^- = .038519$$
, and $E_{ar}(r_A^-) \approx 1.03 \times 10^{-5}$.

Remark 2.4.8. Unlike the above examples, we may not be able to write an equivalent formula for the given function to avoid loss of significance in the evaluation. In such cases, we have to go for a suitable approximation of the given function by other functions, for example Taylor's polynomial of desired degree, that do not involve loss of significance.

2.5 Propagation of Errors

2.5.1 Propagation of Relative Error in Arithmetic Operations

Once an error is committed, it affects subsequent results as this error propagates through subsequent calculations. We first study how the results are affected by using approximate numbers instead of actual numbers and then will take up the effect of errors on function evaluation in the next section.

Let $x, y \in \mathbb{R}$ be two real numbers. Let x_A and y_A denote the approximate numbers used in the calculation. The errors that we have in these approximations as

$$E(x_A) = x - x_A, \quad E(y_A) = y - y_A.$$

We will now see how relative error propagates with the four basic arithmetic operations.

Addition

Let us assume that both x, y > 0. Error due to addition is

$$E(x_A + y_A) = (x + y) - (x_A + y_A) = (x - x_A) + (y - y_A) = E(x_A) + E(y_A).$$

For the relative error

$$E_r(x_A + y_A) = \frac{(x+y) - (x_A + y_A)}{x+y} = \frac{E(x_A) + E(y_A)}{x+y},$$

= $\frac{E(x_A)}{x+y} + \frac{E(y_A)}{x+y} \leqslant E_r(x_A) + E_r(x_A).$

Also, we see that

$$E_{ar}(x_A + y_A) = |E_r(x_A + y_A)| = \left| \frac{E(x_A) + E(y_A)}{x + y} \right|,$$

$$\leq \frac{|E(x_A)| + |E(y_A)|}{x + y} = \frac{|E(x_A)|}{x + y} + \frac{|E(y_A)|}{x + y},$$

$$\leq \frac{|E(x_A)|}{x} + \frac{|E(y_A)|}{y} = E_{ar}(x_A) + E_{ar}(y_A).$$

Therefore, we note that propagation of relative errors due to addition is controlled by the sum of the relative errors in the approximations of the inputs (here x and y).

Subtraction

Let us assume that both $x, y > 0, x \neq y$. Error due to addition is

$$E(x_A - y_A) = (x - y) - (x_A - y_A) = (x - x_A) - (y - y_A) = E(x_A) - E(y_A).$$

For relative error

$$E_r(x_A - y_A) = \frac{(x - y) - (x_A - y_A)}{x - y} = \frac{E(x_A) - E(y_A)}{x - y},$$

$$E_{ar}(x_A - y_A) = |E_r(x_A - y_A)| = \frac{|E(x_A) - E(y_A)|}{|x - y|} \le \left(\frac{1}{|x - y|}\right) |E(x_A)| + |E(y_A)|$$

In case of subtraction, we see that if x and y are close (in the sense that for a given $\delta \in (0,1)$, if $|x-y| < \delta$), then the relative error is magnified with the factor $\left(\frac{1}{|x-y|}\right)$ of the relative errors in the approximations of the inputs.

Multiplication

Let us assume that both x, y > 0. Error due to multiplication is

$$E(x_A \times y_A) = (x \times y) - (x_A \times y_A) = (x \times y) - (x - E(x_A)) \times (y - E(y_A))$$
$$= y \times E(x_A) + x \times E(y_A) - E(x_A) \times E(y_A).$$

For the relative error

$$E_r(x_A \times y_A) = \frac{y \times E(x_A) + x \times E(y_A) - E(x_A) \times E(y_A)}{x \times y},$$

$$= \frac{E(x_A)}{x} + \frac{E(y_A)}{y} - \frac{E(x_A)}{x} \frac{E(y_A)}{y},$$

$$= E_r(x_A) + E_r(y_A) - E_r(x_A) E_r(y_A).$$

Also, we see that

$$E_{ar}(x_A \times y_A) = |E_r(x_A \times y_A)|,$$

$$\leq |E_r(x_A)| + |E_r(y_A)| + |E_r(x_A)| |E_r(x_A)|,$$

$$\leq E_{ar}(x_A) + E_{ar}(y_A) + E_{ar}(x_A) E_{ar}(y_A).$$

We note that when $E_{ar}(x_A)$ and $E_{ar}(y_A)$ are very small so that their product is negligible when compared to $E_{ar}(x_A) + E_{ar}(y_A)$. Therefore, the above inequality reduces to

$$E_{ar}(x_A \times y_A) \leqslant E_{ar}(x_A) + E_{ar}(y_A)$$

Therefore, we note that propagation of relative errors due to multiplication is controlled by the sum of the relative errors in the approximations of the inputs (here *x* and *y*).

Division

Let us assume that both x, y > 0. Error due to multiplication is

$$E(x_A \div y_A) = (x \div y) - (x_A \div y_A) = \frac{x}{y} - \frac{(x - E(x_A))}{(y - E(y_A))}$$
$$= \frac{xy - xE(y_A) - xy + yE(x_A)}{y(y - E(y_A))}$$
$$= \frac{yE(x_A) - xE(y_A)}{y(y - E(y_A))}.$$

For the relative error

$$E_{r}(x_{A} \div y_{A}) = \frac{\frac{yE(x_{A}) - xE(y_{A})}{y(y - E(y_{A}))}}{x \div y} = \frac{yE(x_{A}) - xE(y_{A})}{x(y - E(y_{A}))},$$

$$= \left(\frac{y}{y - E(y_{A})}\right) \left(\frac{E(x_{A})}{x} - \frac{E(y_{A})}{y}\right),$$

$$= \left(\frac{1}{1 - E_{r}(y_{A})}\right) (E_{r}(x_{A}) - E_{r}(y_{A})).$$

Also, we see that

$$E_{ar}(x_A \div y_A) = |E_r(x_A \div y_A)|,$$

$$\leq \frac{1}{|1 - E_r(y_A)|} (|E_r(x_A)| + |E_r(y_A)|),$$

$$= \frac{E_{ar}(x_A) + E_{ar}(y_A)}{|1 - E_r(y_A)|}.$$

We note that when $E_r(y_A)$ are very small compared to 1, the above inequality reduces to

$$E_{ar}(x_A \div y_A) \leqslant E_{ar}(x_A) + E_{ar}(y_A)$$

Therefore, we note that propagation of relative errors due to division is controlled by the sum of the relative errors in the approximations of the inputs (here x and y).

2.5.2 Total Error in arithmetic operations

We discussed the procedure of performing arithmetic operations using n-digit floating-point approximation. The computed value $fl(fl(x) \odot fl(y))$ involves an error when compared to the exact value $x \odot y$. Therefore the total error is

$$x\odot y - \mathrm{fl}(\mathrm{fl}(x)\odot\mathrm{fl}(y)) = \underbrace{(x\odot y - \mathrm{fl}(x)\odot\mathrm{fl}(y))}_{\text{propagated error}} + \underbrace{(\mathrm{fl}(x)\odot\mathrm{fl}(y) - \mathrm{fl}(\mathrm{fl}(x)\odot\mathrm{fl}(y)))}_{\text{computational error}}.$$

The relative total error is obtained by dividing both sides of the above expression by $x \odot y$.