

Goldman Simpro AI Tool

Individual PC Setup Guide (15-20 minutes)

What this is

This guide installs the Goldman Simpro AI tool directly on your PC. Use this guide if the office server version is unavailable, or if you need to work from outside the office without VPN.

NOTE. If you have access to the office LAN setup (your IT person sent you a connector URL and token), use that instead - it is much simpler. Use this guide only as a fallback or if you specifically need to work offline.

Time and prerequisites

- About 15-20 minutes the first time.
- Windows 10 or 11.
- Claude Desktop installed (free plan is fine).
- Permission to install Node.js (you may need to ask IT).
- The shared installer folder from IT.

Part 1 - Create your own Simpro API key

Each person uses their own key so audit logs in Simpro show who did what. Never share keys. If you leave Goldman, IT just deletes your key.

1. Log into Simpro at <https://goldmanplumbingservices.simprosuite.com>
2. Click the gear icon (top right) -> **System** -> **Setup** -> **API Keys**

[Screenshot placeholder]

Simpro: API Keys page location in System menu

(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

3. Click **Add**, name the key after yourself (e.g. *Jane Smith - Claude Desktop*).
4. Set the linked employee to your own employee record.
5. Start with read-only permissions for the first week.
6. Click **Save**. Simpro shows the access token. **COPY IT NOW** into a private note - it is only shown once.

WARNING. Treat the access token like your password. Never share it, never email it, never paste it in chat. If it leaks, delete it in Simpro and create a new one.

Part 2 - Install Node.js

This is the engine that runs the Simpro tool. One-time install.

1. Open **<https://nodejs.org>** in your browser.
2. Click the big green **LTS** button on the left to download the .msi installer.

[Screenshot placeholder]

nodejs.org homepage with the green LTS button highlighted
(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

3. Run the installer. Click **Next, Next, Next, Install**. Defaults are fine.
4. **Restart your PC** after the install completes.
5. Verify: open the **Start menu**, type *PowerShell*, press Enter, then type:

```
node --version
```

It should print a version number like v20.11.0. If it does, close PowerShell - Part 2 is done.

Part 3 - Get the installer folder from IT

IT will share a OneDrive or network folder containing the compiled tool plus an **install.cmd** file. Sync or copy that folder to your PC. The exact location does not matter - the installer handles paths automatically.

NOTE. If you do not have access to the share folder, ask IT (currently Tayfun / Sinan). The folder is too big to email - it will be a OneDrive link or a copy on a USB stick.

[Screenshot placeholder]

File Explorer: contents of the share folder showing install.cmd
(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

Part 4 - Run the installer

1. Open the installer folder you got in Part 3.
2. **Double-click** the file named **install.cmd**.

NOTE. Windows may show a blue 'Windows protected your PC' warning the first time. Click **More info** then **Run anyway**. The script is from your IT team.

3. When the script asks for your **Simpro API key**, paste the access token from Part 1.

4. When it asks which company, type **3** for both Plumbing and Energy (or 1 for Plumbing only, 2 for Energy only).
5. Wait about 30 seconds. The script copies the tool, configures Claude Desktop, and tells you it is done.

[Screenshot placeholder]

PowerShell window showing 'All done' message at end of install

(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

Part 5 - Restart Claude Desktop properly

WARNING. Just closing the Claude Desktop window is not enough. You must **Quit** from the system tray (the small icons near the clock).

1. Look at the bottom-right of your screen, near the clock.
2. Find the **Claude icon**. You may need to click the small up-arrow to expand the hidden tray icons.
3. **Right-click** the Claude icon.
4. Click **Quit**.

[Screenshot placeholder]

Windows system tray with Claude icon right-click menu showing Quit
(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

5. Wait 3 seconds, then open Claude Desktop again from the Start menu.

Part 6 - Test it works

1. In Claude Desktop, click the small **tools / hammer icon** near the message box. You should see two entries: *simpro_plumbing* and *simpro_energy*.

[Screenshot placeholder]

Claude Desktop tools menu showing simpro_plumbing and simpro_energy
(Tayfun: paste real screenshot here. Right-click box in your PDF editor and replace.)

2. Type into the chat:

Use Simpro Plumbing to test the connection.

3. You should see: *'Simpro connection OK. Base URL... Company ID: 4...'*

4. Try the other one to confirm both work:

Use Simpro Energy to test the connection.

This one should report **Company ID: 37**. If both work, you are done.

More things to try

- Use *Simpro Plumbing* to search for customers named *Goldman*.
- Use *Simpro Plumbing* to find recent jobs.
- Use *Simpro Plumbing* to list line items for purchase order *[number]*.

- *Use Simpro Energy to find supplier invoices from Reece in May 2026.*

Part 7 - Turning on writes (later, when you are ready)

After a few days of comfortable read-only use, you can let Claude create or update Simpro records. Do this in two stages.

Stage 1 - Dry run (safe preview)

Ask IT to flip `SIMPRO_ENABLE_WRITE_TOOLS` to true while keeping `SIMPRO_DRY_RUN` true. From then on, when you ask Claude to update something, it will **show you what it would do** but not actually send it. Read each preview carefully.

SAFETY. Every write also requires *confirm: true*. If you forget, Claude returns a confirmation request instead of doing anything. Two safety layers, on purpose.

Stage 2 - Real writes

Once you are confident, ask IT to flip `SIMPRO_DRY_RUN` to false. Now writes really happen. Start small - add a note to a test job before doing anything bulk. If anything feels wrong, ask IT to flip the switch back, and writes stop immediately.

Common problems and fixes

Problem	Fix
Claude Desktop does not show the simpro tools	You did not fully Quit Claude Desktop. Right-click tray icon -> Quit. Wait 3 seconds. Reopen.
'401 Unauthorized' or 'API key invalid'	Your Simpro API key is wrong, expired, or was deleted. Generate a new one in Simpro (Part 1) and re-run <code>install.cmd</code> to update it.
'403 Forbidden'	The key works but lacks permission. In Simpro, edit your API key and grant the missing permission.
'404 Not Found' on every request	Wrong company. Goldman Plumbing = ID 4, Goldman Energy = ID 37. Try the other one.
'Write tools are disabled'	Safety guard. Ask IT to enable writes for you (see Part 7).
'Confirmation required'	Add <i>confirm: true</i> to your request, or tell Claude <i>'...and confirm true'</i> .
'Could not reach Simpro'	Check you can open https://goldmanplumbingservices.simprosuite.com in your browser. If the office is on VPN, connect to it.
Anything else	Send IT a screenshot of the error. Never include your API key in the screenshot.

Rotating or revoking your API key

Do this if your key may have leaked, or if you are leaving Goldman.

1. Log into Simpro -> API Keys page (Part 1, Step 2).
2. Click **Add** to create a new key, copy the new access token.
3. Re-run **install.cmd** on your PC. When asked for the API key, paste the new one.
4. Quit and reopen Claude Desktop, test the connection.
5. Once the new key works, go back to Simpro and **delete** the old key.

If anything is unclear

Contact IT (currently Tayfun / Sinan). Tell them: which step number you are on, the exact error message you see, and your Windows version (right-click *This PC* -> Properties). **Never include your Simpro API key** in screenshots - blur it out first.