Hazel PHI: 10-modules

how to read

800000	kinds	800080	signatures
008000	types (constructors)	008080	modules
000080	terms		

syntax

kind	κ	::=	$\texttt{Type}$	kind of types
		|	$\texttt{S}(\tau)$	singleton kind
		|	$\texttt{KHole}$	kind hole
		|	$\Pi_{t::\kappa_1}.\kappa_2$	dependent function kind
		|	$\Sigma_{t::\kappa_1}.\kappa_2$	dependent product kind
internal HTyp	τ	::=	t	type variable
		|	bse	base type
		|	$\lambda t :: \kappa.\tau$	type function
		|	$\tau_1\ \tau_2$	type application
		|	$\tau_1 \oplus \tau_2$	type binop
		|	$\langle \tau_1, \tau_2 \rangle$	type pair
		|	$\pi_1\ \tau$	type projection
		|	$\pi_2\ \tau$	type projection
		|	$\{lab_1 \hookrightarrow \tau_1, \ldots\ lab_n \hookrightarrow \tau_n\}$	labelled product type (record)
		|	$mod.lab$	module type projection
		|	$(\!\vert\vert\!)$	empty type hole
		|	$(\!\vert \tau \vert\!)$	nonempty type hole
base type	bse	::=	$\texttt{Int}$	
		|	$\texttt{Float}$	
		|	$\texttt{Bool}$	
HTyp BinOp	$\oplus$	::=	$\times$	
		|	$+$	
		|	$\rightarrow$	
internal expression	δ	::=	x	
		|	$\texttt{signature}\ s = sig\ \texttt{in}\ \delta$	
		|	$\texttt{module}\ m = mod\ \texttt{in}\ \delta$	
		|	$\texttt{module}\ m :: s = mod\ \texttt{in}\ \delta$	
		|	$mod.lab$	module term projection
		|	*elided*	
signature	sig	::=	s	signature variable
		|	$\{sdecs\}$	structure signature
		|	$\Pi_{m::sig_1}.sig_2$	functor signature
module	mod	::=	m	module variable
		|	$\{sbnds\}$	structure
		|	$\lambda m :: sig.mod$	functor
		|	$mod_1\ mod_2$	functor application
		|	$mod.lab$	submodule projection
signature declarations	$sdecs$	::=	ϵ	
		|	$sdec, sdecs$	
signature declaration	$sdec$	::=	$\texttt{type}\ lab$	
		|	$\texttt{type}\ lab = \tau$	
		|	$\texttt{val}\ lab : \tau$	
		|	$\texttt{module}\ lab :: sig$	
structure bindings	$sbnds$	::=	ϵ	
		|	$sbnd, sbnds$	
structure binding	$sbnd$	::=	$\texttt{type t} = \tau$	