### **Functions and Text**

Troels Henriksen

#### Procedures at machine level

#### The call stack

Calling conventions Recursion by example

### Data representations

Examining data in C A machine view of text Binary IO

### The problem with procedures

```
f(a,b,c);
g(x,y,z);
h(a,y,c);
```

- Calling a procedure (or function) requires jumping to different code.
- But:
  - How do we pass arguments to the procedure?
  - How does it return its results?
  - How do we prevent the procedure we call from overwriting the registers we are using?

### The basic problem

How do we "suspend" execution of the current procedure, let another procedure take over, and resume execution from the *call site* afterwards?

## Main instructions: jal and jalr

Instruction	Meaning
jal $x_i$ , $k$	$x_i = PC + 4; PC += k$
$jalr x_i, k(x_j)$	$x_i = PC + 4; PC = x_j + k$
jalr $x_i$ , $x_j$ , $k$	$x_i = PC + 4; PC = x_j + k$

- Jump-and-Link jumps to an address and stores the call site address in the "link register"  $x_i$ .
- Jump-and-Link-Register takes address from register value.
  - Used to return from procedure.

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

 0x102	0x101	0x100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
 de	ad	be	ef	13	37	04	20	
				1				

# SP: 0x0fe Operation:

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

 0x102	0x101	0 <b>x</b> 100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
 de	ad	be	ef	13	38	04	20	

SP: 0x0fd

Operation: push (0x38)

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

 0x102	0×101	0x100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
 de	ad	be	ef	13	38	14	20	
						$\uparrow$		

SP: 0x0fc

Operation: push (0x14)

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

 0x102	0×101	0x100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
 de	ad	be	ef	13	38	14	20	

SP: 0x0fd

Operation: pop()

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

 0x102	0×101	0x100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
 de	ad	be	ef	13	38	14	20	
				1				

SP: 0x0fe

Operation: pop()

- We have seen structured control flow encoded using conditional jumps.
- Similarly, memory is a flat array of bytes, and it is up to us where we put things.
  - Freedom requires discipline.

#### A stack at machine level

A stack is a region of memory where a *stack pointer* points to the top element.

	0x102	0x101	0x100	0x0ff	0x0fe	0x0fd	0x0fc	0x0fb	
	de	ad	be	ef	13	38	14	20	
				$\uparrow$					

SP: 0x0ff

Operation: pop()

### The call stack

A program can use many stacks for various things, but when we say *the stack*, we almost alway means *the call stack*.

#### High level idea

- When we call a function, we push enough information to the stack to allow the called function to resume us when we are done.
- When we return from a function, we pop information from the stack to resume execution of the caller.
- Call stack is essentially a queue of functions waiting to resume execution.

### The call stack

# A program can use many stacks for various things, but when we say *the stack*, we almost alway means *the call stack*.

#### High level idea

- When we call a function, we push enough information to the stack to allow the called function to resume us when we are done.
- When we return from a function, we pop information from the stack to resume execution of the caller.
- Call stack is essentially a queue of functions waiting to resume execution.

#### **Important**

- The call stack is not special hardware, but uses ordinary memory.
- By RISC-V convention, sp register points to top of stack (the stack pointer).
- Grows from high address to low address.
  - ► To **pop**: *increment* sp.
  - ► To push: decrement sp.

leaf:

```
leaf:
                        addi sp, sp, -12 # make room for 3 words
                        sw t0, 8(sp) # save old value of t0
int leaf(int a0,
                        sw t1, 4(sp) # save old value of t1
         int a1.
                        sw s4, 0(sp) # save old value of s4
         int a2,
         int a3) {
  int t0 = a0 + a1:
  int t1 = a2 + a3:
  int s4 = t0 - t1:
  return s4:
```

```
leaf:
                        addi sp, sp, -12 # make room for 3 words
                       sw t0, 8(sp) # save old value of t0
int leaf(int a0,
                       sw t1, 4(sp) # save old value of t1
         int a1.
                        sw s4, 0(sp) # save old value of s4
         int a2,
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
 int s4 = t0 - t1:
 return s4:
```

```
leaf:
                        addi sp, sp, -12 # make room for 3 words
                        sw t0, 8(sp) # save old value of t0
int leaf(int a0,
                        sw t1, 4(sp) # save old value of t1
         int a1.
                        sw s4, 0(sp) # save old value of s4
         int a2,
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
                        addi a0, s4, 0
                                           # return value in a0
  int s4 = t0 - t1:
  return s4:
```

```
leaf:
                        addi sp, sp, -12 # make room for 3 words
                       sw t0, 8(sp) # save old value of t0
int leaf(int a0,
                       sw t1, 4(sp) # save old value of t1
         int a1.
                        sw s4, 0(sp) # save old value of s4
         int a2.
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
                                       # return value in a0
                        addi a0, s4, 0
  int s4 = t0 - t1:
                        lw s4, 0(sp)
                                          # restore s4
 return s4:
                                          # restore t1
                        lw t1, 4(sp)
                        lw t0, 8(sp)
                                          # restore t0
                                          # pop 3 words from stack
                        addi sp, sp, 12
```

```
leaf:
                        addi sp, sp, -12 # make room for 3 words
                        sw t0, 8(sp)
                                          # save old value of t0
int leaf(int a0,
                        sw t1, 4(sp) # save old value of t1
         int a1.
                        sw s4, 0(sp) # save old value of s4
         int a2.
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
                                       # return value in a0
                        addi a0, s4, 0
  int s4 = t0 - t1:
                        lw s4, 0(sp)
                                           # restore s4
 return s4:
                                           # restore t1
                        lw t1, 4(sp)
                        lw t0, 8(sp)
                                           # restore t0
                        addi sp, sp, 12
                                           # pop 3 words from stack
                                           # jump to call site
                        jalr zero, 0(ra)
```

#### Procedures at machine level

The call stack

### Calling conventions

Recursion by example

### Data representations

Examining data in C A machine view of text Binary IO

## Motivation for calling conventions

### Terminology

Caller The procedure making the procedure call (jumping *from*).

Callee The procedure being called (jumping *to*).

## Motivation for calling conventions

### Terminology

Caller The procedure making the procedure call (jumping *from*). Callee The procedure being called (jumping *to*).

- Large modular programs consist of procedures that
  - can be called from any other procedure.
  - can call any other procedure without knowing how they work internally.

### Calling convention

A set of rules for how to pass arguments to another procedure, what that procedure can expect of its environment, and how the callee should clean up and return to the caller.

### Calling convention

A set of rules for how to pass arguments to another procedure, what that procedure can expect of its environment, and how the callee should clean up and return to the caller.

- Differs between architectures and operating systems.
  - We'll ignore lots of features that are important in practice, e.g. exception handlers, destructors, or debugging information.

### Calling convention

A set of rules for how to pass arguments to another procedure, what that procedure can expect of its environment, and how the callee should clean up and return to the caller.

- Differs between architectures and operating systems.
  - We'll ignore lots of features that are important in practice, e.g. exception handlers, destructors, or debugging information.

#### Basics:

- ► Caller puts arguments in a0-a7.
- Caller puts return address in ra.
- ► Callee puts return value in a0.
- But what about the other registers?

### Caller-save and callee-save registers (simplified)

Caller-save registers, e.g. t0-t6

From callers perspective

- Not preserved by procedure calls.
- Must be saved on stack before call if we want to preserve value.

#### From callees perspective

- May be overwritten freely.
- Can have any value when returning.

# Caller-save and callee-save registers (simplified)

Caller-save registers, e.g. t0-t6

From callers perspective

- Not preserved by procedure calls.
- Must be saved on stack before call if we want to preserve value.

#### From callees perspective

- May be overwritten freely.
- Can have any value when returning.

#### Callee-save registers, e.g. s0-s11

From callers perspective

Preserved by procedure calls.

#### From callees perspective

- Must save value on stack before overwriting.
- Must restore original value before returning.

# Full table of integer registers

Register	Name	Description	Saver
x0	zero	Hard-wired zero	-
x1	ra	Return address	Caller
x2	sp	Stack pointer	Callee
<b>x</b> 3	gp	Global pointer	-
x4	tp	Thread pointer	-
x5-7	t0-t2	Temporaries	Caller
x8	s0/fp	Saved register/frame pointer	Callee
x9	s1	Saved register	Callee
x10-11	a0-a1	Arguments/return values	Caller
x12-17	a2-a7	Arguments	Caller
x18-27	s2-s11	Saved registers	Callee
x28-31	t3-t6	Temporaries	Caller

- 16 are caller-save.
- 13 are callee-save.

# Leaf procedure, saving only callee-saves registers

```
leaf:
int leaf(int a0.
                                           # make room for 1 word
                        addi sp, sp, -4
         int a1.
                                           # save old value of s4
                        sw s4, 0(sp)
         int a2,
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
                        addi a0, s4, 0 # return value in a0
  int s4 = t0 - t1:
                                           # restore s4
                        1w s4, 0(sp)
  return s4;
                        addi sp, sp, 4
                                           # pop 1 word from stack
                        jalr zero, 0(ra)
                                           # jump to call site
```

# Leaf procedure, saving only callee-saves registers

```
leaf:
int leaf(int a0.
                        addi sp, sp, -4 # make room for 1 word
         int a1.
                        sw s4, 0(sp)
                                          # save old value of s4
         int a2,
                        add t0, a0, a1
         int a3) {
                        add t1, a2, a3
  int t0 = a0 + a1:
                        add s4, t0, t1
  int t1 = a2 + a3:
                        addi a0, s4, 0 # return value in a0
  int s4 = t0 - t1:
                                          # restore s4
                        lw s4, 0(sp)
  return s4;
                        addi sp, sp, 4
                                           # pop 1 word from stack
                                           # jump to call site
                        jalr zero, 0(ra)
```

Can we do even better?

```
leaf(t0,t1,t2,t3);
```

```
addi a0, t0, 0 # first argument
addi a1, t1, 0 # second argument
addi a2, t2, 0 # third argument
addi a3, t3, 0 # fourth argument
```

```
leaf(t0,t1,t2,t3);
```

```
addi a0, t0, 0 # first argument
addi a1, t1, 0 # second argument
addi a2, t2, 0 # third argument
addi a3, t3, 0 # fourth argument
addi sp, sp, -64 # make room for 16 words
```

```
leaf(t0,t1,t2,t3);
```

```
addi a0, t0, 0 # first argument
addi a1, t1, 0 # second argument
addi a2, t2, 0 # third argument
addi a3, t3, 0 # fourth argument
addi sp, sp, -64 # make room for 16 words
sw ra, 0(sp) # save ra
```

```
leaf(t0,t1,t2,t3);
```

```
addi a0, t0, 0 # first argument
addi a1, t1, 0 # second argument
addi a2, t2, 0 # third argument
addi a3, t3, 0 # fourth argument
addi sp, sp, -64 # make room for 16 words
sw ra, 0(sp) # save ra
sw t0, 4(sp) # save t0
```

```
leaf(t0,t1,t2,t3);
```

leaf(t0,t1,t2,t3);

```
# first argument
addi a0, t0, 0
                   # second argument
addi a1, t1, 0
addi a2, t2, 0
                   # third argument
                   # fourth argument
addi a3, t3, 0
                   # make room for 16 words
addi sp, sp, -64
sw ra, 0(sp)
                   # save ra
sw t0, 4(sp)
                   # save t.0
sw a7, 60(sp)
                  # save a7
```

leaf(t0.t1.t2.t3):

```
addi a0, t0, 0
                   # first argument
                   # second argument
addi a1, t1, 0
addi a2, t2, 0
                   # third argument
                   # fourth argument
addi a3, t3, 0
addi sp, sp, -64
                   # make room for 16 words
sw ra, 0(sp)
                   # save ra
sw t0, 4(sp)
                   # save t.0
sw a7, 60(sp)
                   # save a7
jal ra, leaf
                   # jump to procedure
```

leaf(t0.t1.t2.t3):

```
addi a0, t0, 0
                   # first argument
addi a1, t1, 0
                   # second argument
                   # third argument
addi a2, t2, 0
                   # fourth argument
addi a3, t3, 0
                   # make room for 16 words
addi sp, sp, -64
sw ra, 0(sp)
                   # save ra
sw t0, 4(sp)
                   # save t.0
sw a7, 60(sp)
                   # save a7
jal ra, leaf
                   # jump to procedure
lw ra, 0(sp)
                   # restore ra
```

leaf(t0.t1.t2.t3):

```
addi a0, t0, 0
                   # first argument
addi a1, t1, 0
                   # second argument
addi a2, t2, 0
                   # third argument
                   # fourth argument
addi a3, t3, 0
                   # make room for 16 words
addi sp, sp, -64
sw ra, 0(sp)
                   # save ra
sw t0, 4(sp)
                   # save t.0
sw a7, 60(sp)
                   # save a7
jal ra, leaf
                   # jump to procedure
lw ra, 0(sp)
                   # restore ra
lw t0, 4(sp)
                   # restore t.0
```

```
addi a0, t0, 0
                                           # first argument
                        addi a1, t1, 0
                                           # second argument
                        addi a2, t2, 0
                                           # third argument
                                           # fourth argument
                        addi a3, t3, 0
                                           # make room for 16 words
                        addi sp, sp, -64
                        sw ra, 0(sp)
                                           # save ra
                        sw t0, 4(sp)
                                           # save t.0
leaf(t0,t1,t2,t3):
                        sw a7, 60(sp)
                                          # save a7
                        jal ra, leaf
                                           # jump to procedure
                        lw ra, 0(sp)
                                           # restore ra
                        lw t0, 4(sp)
                                           # restore t.0
                        lw a7, 60(sp)
                                           # restore a 7
```

```
addi a0, t0, 0
                                           # first argument
                        addi a1, t1, 0
                                           # second argument
                        addi a2, t2, 0
                                           # third argument
                                           # fourth argument
                        addi a3, t3, 0
                                           # make room for 16 words
                        addi sp, sp, -64
                        sw ra, 0(sp)
                                           # save ra
                        sw t0, 4(sp)
                                           # save t.0
leaf(t0,t1,t2,t3):
                        sw a7, 60(sp) # save a7
                        jal ra, leaf
                                           # jump to procedure
                        lw ra, 0(sp)
                                          # restore ra
                        lw t0, 4(sp)
                                           # restore t.0
                        lw a7, 60 (sp) # restore a7
                                           # restore stack pointer
                        addi sp, sp, 64
                                           # continue on
```

```
addi a0, t0, 0
                                            # first argument
                         addi a1, t1, 0
                                            # second argument
                         addi a2, t2, 0
                                            # third argument
                                            # fourth argument
                         addi a3, t3, 0
                                            # make room for 16 words
                         addi sp, sp, -64
                         sw ra, 0(sp)
                                            # save ra
                         sw t0, 4(sp)
                                            # save t.0
leaf(t0.t1.t2.t3):
                         sw a7, 60(sp)
                                            # save a7
                         jal ra, leaf
                                            # jump to procedure
                         lw ra, 0(sp)
                                            # restore ra
                         lw t0, 4(sp)
                                            # restore t.0
                        lw a7, 60 (sp) # restore a7
                                            # restore stack pointer
                         addi sp, sp, 64
                                            # continue on
Should we restore all registers?
```

```
addi a0, t0, 0
                                              # first argument
                                              # second argument
                          addi a1, t1, 0
                          addi a2, t2, 0
                                              # third argument
                          addi a3, t3, 0
                                              # fourth argument
                                              # make room for 16 words
                          addi sp, sp, -64
                          sw ra, 0(sp)
                                              # save ra
                          sw t0, 4(sp)
                                              # save t.0
leaf(t0,t1,t2,t3);
                          sw a7, 60(sp)
                                              # save a7
                          jal ra, leaf
                                              # jump to procedure
                          lw ra, 0(sp)
                                              # restore ra
                          lw t0, 4(sp)
                                              # restore t.0
                          lw a7, 60 (sp) # restore a7
                                              # restore stack pointer
                          addi sp, sp, 64
                                              # continue on
Should we restore all registers? Possibly not a 0 (would overwrite return value)
```

#### Procedures at machine level

The call stack
Calling conventions
Recursion by example

#### Data representations

Examining data in C A machine view of text Binary IO

```
int fact(int n) {
  if (n == 0) {
    return 1;
  } else {
```

return n \* fact(n-1);

mul\_end:

jalr zero, ra, 0

```
fact:
        addi sp, sp, -8
        sw ra, 4(sp)
        sw a0, 0(sp)
        beq a0, zero, fact_base
        addi a0, a0, -1
        jal ra, fact
        lw a1, 0(sp)
        jal ra, mul
        jal zero, fact return
fact base:
        li a0, 1
fact_return:
        lw ra, 4(sp)
        addi sp, sp, 8
        jalr zero, ra, 0
```

#### Procedures at machine level

The call stack
Calling conventions
Recursion by example

# Data representations

Examining data in C

A machine view of text Binary IO

# **Examining data representations**

#### Code to print byte representation of data

Casting pointer to unsigned char\* allows treatment as byte array.

```
void show_bytes(unsigned char* start, size_t len) {
    size_t i;
    for (i = 0; i < len; i++) {
        printf("%p\t0x%.2x\n", start+i, start[i]);
    }
    printf("\n");
}</pre>
```

#### printf directives:

- %p: Print pointer.
- %x: Print hexadecimal.

# show\_bytes execution example

```
int a = 15213;
printf("int a = 15213;\n");
show_bytes((unsigned char*) &a, sizeof(int));
```

### Result (Linux x86-64):

```
0x7fffb7f71dbc 6d
0x7fffb7f71dbd 3b
0x7fffb7f71dbe 00
0x7fffb7f71dbf 00
```

#### Procedures at machine level

The call stack
Calling conventions
Recursion by example

#### Data representations

Examining data in C

A machine view of text

Binary 10

```
printf("Hello, world!\n");
```

```
printf("Hello, world!\n");
Hello, world!
```

```
printf("Hello, world!\n");
                                          Hello, world!
int x = 123;
                                          an integer: 123
printf("an integer: %d\n", x);
printf("an integer: %5d\n", x);
                                          an integer:
                                                        123
double y = 1.23;
                                          a float: 1.230000
printf("a float: %f\n", y);
printf("a mess: %d\n", y);
```

```
printf("Hello, world!\n");
                                         Hello, world!
int x = 123;
                                         an integer: 123
printf("an integer: %d\n", x);
printf("an integer: %5d\n", x);
                                         an integer:
                                                     123
double y = 1.23;
                                         a float: 1.230000
printf("a float: %f\n", y);
printf("a mess: %d\n", y);
                                         a mess: 4202562
```

```
printf("Hello, world!\n");
                                          Hello, world!
int x = 123;
                                         an integer: 123
printf("an integer: %d\n", x);
printf("an integer: %5d\n", x);
                                         an integer: 123
double v = 1.23;
                                         a float: 1.230000
printf("a float: %f\n", v);
printf("a mess: %d\n", y);
                                         a mess: 4202562
```

Make sure format specifiers and argument types match!

## **Text representation**

- Machines only understand numbers, and text is an abstraction!
- E.g. when the terminal receives a byte with the value 65, it draws an A.
- printf() determines which bytes must be written to the terminal to produce the text corresponding to e.g. the number 123: [49, 50, 51].

#### Character sets

A character set maps a *number* to a *character*.

- ASCII defines characters in the range 0-127 (asciitable.com).
- Some are invisible/unprintable control characters
- Unicode is a superset of ASCII that defines tens of thousands of characters for all the world's scripts.

We'll assume ASCII, which has the simple property that 1 byte = 1 character.

## The ASCII table

Control characters				Normal characters											
000	nul	016	dle	032		048	0	064	@	080	Р	096	•	112	р
001	soh	017	dc1	033	!	049	1	065	Α	081	Q	097	а	113	q
002	stx	018	dc2	034	"	050	2	066	В	082	R	098	b	114	r
003	etx	019	dc3	035	#	051	3	067	C	083	S	099	С	115	s
004	eot	020	dc4	036	\$	052	4	068	D	084	Τ	100	d	116	t
005	enq	021	nak	037	%	053	5	069	Ε	085	U	101	е	117	u
006	ack	022	syn	038	&	054	6	070	F	086	V	102	f	118	V
007	bel	023	etb	039	'	055	7	071	G	087	W	103	g	119	w
800	bs	024	can	040	(	056	8	072	Н	088	Χ	104	h	120	x
009	tab	025	em	041	)	057	9	073	- 1	089	Υ	105	i	121	у
010	lf	026	eof	042	*	058	:	074	J	090	Z	106	j	122	z
011	vt	027	esc	043	+	059	;	075	K	091	[	107	k	123	{
012	np	028	fs	044	,	060	<	076	L	092		108	l	124	1
013	cr	029	gs	045	-	061	=	077	М	093	]	109	m	125	}
014	SO	030	rs	046		062	>	078	Ν	094	^	110	n	126	~
015	si	031	us	047	/	063	?	079	0	095	_	111	0	127	del

# **Turning numbers into text**

```
int x = 1234;
printf("x: %d\n", x);
```

# **Turning numbers into text**

```
int x = 1234;
printf("x: %d\n", x);
```

The text *string* that is passed to printf() looks like this in memory:

Characters	Х	:		૾ૢ	d	\n	\0
Bytes	120	58	32	37	100	10	0

# **Turning numbers into text**

```
int x = 1234;
printf("x: %d\n", x);
```

The text *string* that is passed to printf() looks like this in memory:

Characters	Х	:		용	d	\n	\0
Bytes	120	58	32	37	100	10	0

printf() rewrites format specifiers (%d) to the textual representation of their corresponding value argument:

Characters	Х	:		1	2	3	4	\n	\0
Bytes	120	58	32	49	50	51	52	10	0

These bytes (except the 0) are then written to *standard output* (typically the terminal) which interprets them as characters and eventually draws pixels on the screen.

# Machine representation versus text representation

```
int x = 305419896;
```

- Written as hexadecimal (base-16), this number is 0x12345678.
- One hexadecimal digit is 4 bit, so each group of two digits is one byte, and the number takes four bytes (32 bits).
- The machine representation in memory on an x86 CPU is  $0x78 \quad 0x56 \quad 0x34 \quad 0x12$
- A decimal text representation in memory on any CPU is
   0x33 0x30 0x35 0x34 0x35 0x36 0x37 0x38
- Endianness has no effect on text (at least not with single-byte characters).
- In C, we have the additional convention that any string must be NUL-terminated.
- We identify a string with the address of its first character.

#### Procedures at machine level

The call stack
Calling conventions
Recursion by example

#### Data representations

Examining data in C A machine view of text Binary IO

# Writing bytes

The fwrite procedure writes raw data to an open file:

```
size t fwrite (const void *ptr,
                 size t size.
                 size t nmemb.
                 FILE *stream);
      ptr: the address in memory of the data.
     size: the size of each data element in bytes.
   nmemb: the number of data elements.
  stream: the target file (opened with fopen ()).
```

- Returns the number of data elements written (equal to nmemb unless an error occurs).
- Usually no difference between writing one size x\*y element or x size-y elements—do whatever is convenient

# Example of fwrite()

```
#include <stdio h>
int main() {
  // Open for writing ("w")
  FILE *f = fopen("output", "w");
  char c = 42;
  fwrite(&c, sizeof(char), 1, f);
  fclose(f);
```

- Produces a file output.
- File contains the byte 42, corresponding to the ASCII character \*.
- char is just an 8-bit integer type!
  - No special "character" meaning.
  - Most Unicode characters will not fit in a single char (e.g. 'æ' needs 16 bits in UTF-8).
  - Name is unfortunate/historical.
  - Signedness is implementation-defined for historical reasons.

# **Another example**

```
#include <stdio h>
int main() {
  FILE *f = fopen("output", "w");
  int x = 0x53505048;
  // Stored as 0x48 \ 0x50 \ 0x50 \ 0x53
  fwrite(&x, sizeof(int), 1, f);
  fclose(f);
```

- Writes bytes 0x48 0x50 0x50 0x53.
- Corresponds to ASCII characters HPPS.
- A big-endian machine would produce SPPH.
- Don't write code that depends on this!

# Converting a non-negative integer to its ASCII representation

```
FILE *f = fopen("output", "w");
int x = 1337:
                  // Number to write;
char s[10];
             // Output buffer.
int i = 10:
                       // Index of last character written.
while (1) {
 int d = x % 10;  // Pick out last decimal digit.
 x = x / 10:
             // Remove last digit.
 i = i - 1:
            // Index of next character.
 s[i] = '0' + d; // Save ASCII character for digit.
 if (x == 0) { break; } // Stop if all digits written.
fwrite(&s[i], sizeof(char), 10-i, f); // Write ASCII bytes.
fclose(f);
                                   // Close output file.
```

# Reading bytes

```
size t fread (void *ptr,
                size t size,
                size t nmemb,
                FILE *stream);
      ptr: where to put the data we read.
     size: the size of each data element in bytes.
    nmemb: the number of data elements.
  stream: the target file (opened with fopen ()).
                          Very similar to fwrite()!
```

# Reading all the bytes in a file

```
#include <stdio.h>
#include <assert.h>
int main(int arqc, char* argv[]) {
  FILE *f = fopen(arqv[1], "r");
  unsigned char c:
  while (fread(\&c, sizeof(char), 1, f) == 1) {
    printf("%3d...", (int)c);
    if (c > 31 && c < 127) {
      fwrite(&c, sizeof(char), 1, stdout);
    printf("\n");
```

# Running fread-bytes

```
$ gcc -o fread-bytes -Wall -Wextra -pedantic fread-bytes.c
```

# Running fread-bytes

```
$ qcc -o fread-bytes -Wall -Wextra -pedantic fread-bytes.c
$ ./fread-bytes fread-bytes.c
35 #
105 i
110 n
99 C
108 1
117 11
100 d
101 e
 32
 60 <
```

# Running fread-bytes

```
$ gcc -o fread-bytes -Wall -Wextra -pedantic fread-bytes.c
$ ./fread-bytes fread-bytes.c $ ./fread-bytes fread-bytes
35 #
                               127
105 i
                                 69 E
                                 76 L
110 n
99 C
                                 70 F
108 1
117 11
100 d
101 e
32
60 <
```

# Text files versus binary files

- To the system there is no difference between "text files" and "binary files"!
- All files are just byte sequences.
- Colloquially: a text file is a file that is understandable when the bytes are interpreted as characters (in ASCII or some other character set).

# **Text files versus binary files**

- To the system there is no difference between "text files" and "binary files"!
- All files are just byte sequences.
- Colloquially: a text file is a file that is understandable when the bytes are interpreted as characters (in ASCII or some other character set).

### Compactness of storage

- A 32-bit integer takes up to 12 bytes to store as base-10 ASCII digits
- 4 bytes as raw data
- Raw data takes up less space and is much faster to read.
- But we need special programs to decode the data to human-readable form.

### **IO** takeaways

- Use printf() for text output.
- (And scanf() for text input.)
- Use fwrite() to write raw data.
- Use fread() to read raw data.
- Raw data files are more compact and faster to read/write.