# Tableau Server on Windows in the Google Cloud Platform Administrator Guide



# Install Tableau Server on the Google Cloud Platform

When you install Tableau Server on a Google Compute Engine (GCE) virtual machine (VM), you still have the advanced capabilities of Tableau Server in a local environment. Running Tableau Server on a GCE VM is an excellent choice if you want the flexibility of scaling up and scaling out without having to purchase and maintain an expensive fleet of servers. For instance, you can configure Tableau Server to be highly available, and integrate with all of the common enterprise applications (for example, Active Directory) that many organizations rely on.

Looking for Tableau Server on Linux? See Install Tableau Server on the Google Cloud Platform.

Tableau Server can take advantage of many native Google Cloud Services:

- Google Persistent Disk: Cloud-based block storage for virtual machines (VMs).
- Google Cloud Storage: Cloud-based unified object storage for data archiving.
- Google Cloud Dataflow: Cloud-based service for stream and batch data processing.
- Google Cloud Dataproc: Cloud-based service for running Spark and Hadoop clusters.

In addition, you can store the data you use with Tableau Server using any of the following Google Cloud Services. Tableau provides native data connectors that enable you to connect to data in the following Google data sources:

- Google Analytics: Web analytics tool for tracking and reporting website traffic.
- Google BigQuery: Managed enterprise data warehouse for analytics.
- Google Cloud SQL: Managed SQL database service.
- Google Sheets: Spreadsheet included in Google Docs.

# Tableau Server on the Google Cloud Platform deployment options

You can deploy Tableau Server on a Google Compute Engine (GCE) virtual machine (VM). A Tableau Server deployment on GCE supports the following:

Tableau Server	Google Compute Engine VM Self-Deployment
Production ready	<b>⊘</b>
Upgradable	<b>⊘</b>
Install on Linux	<b>⊘</b>
Install on Windows	<b>⊘</b>
Scale-up	<b>⊘</b>
Scale-out (add additional nodes)	<b>⊘</b>
Active Directory support	<b>⊘</b>
14-day trial license	<b>⊘</b>
BYOL license	<b>⊘</b>
Subscription license	<b>⊘</b>

The self-deployment option is described in more detail below:

 Self-Deploy to Google Compute Engine VM - Provides the most flexibility and options to customize Tableau Server to your environment.

Self-deployment of Tableau Server on a Google Compute Engine VM is recommended for development, test, and production environments that start simple but may need to scale later.

For more information about self-deployment, see Self-Deploy a Single Tableau Server on the Google Cloud Platform. For more information about deploying in a distributed environment, see Self-Deploy Tableau Server on the Google Cloud Platform in a Distributed Environment.

For more information about Tableau Server licensing options, search for "Licensing Overview" in the Tableau Server Help.

### What You Need Before You Begin

To work with Tableau Server on the Google Cloud Platform, you will need:

- A Google Cloud Platform account. If you don't already have one, sign up for a new account.
- A Tableau Server license.
  - For a standalone deployment, you can use a 14-day trial version of Tableau Server, which doesn't require the use of a product key. After 14 days, you'll need to purchase a Tableau Server license and activate the associated product key.
  - For a cluster-based deployment, you need a user-based license (which covers all authorized users of Tableau Server), a core-based license (with a minimum

of 16 cores), or a Tableau Server subscription license. To obtain a product key, contact sales.

For more information about Tableau Server licensing options, search for "Licensing Overview" in the Tableau Server Help.

# Best Practices for Installing Tableau Server on the Google Cloud Platform

The following best practices make installing Tableau Server in the cloud a better experience.

- Search for "Plan Your Deployment" in the Tableau Server Help.
- Read the Tableau Server on Google Cloud Platform Prerequisites.
- Search for "Security Hardening Checklist" in the Tableau Server Help
- If you're new to the cloud, use the Google Cloud Platform free tier to get familiar with working in the cloud before you deploy Tableau Server on the Google Cloud Platform.
- Read about and understand network topology on the Google Cloud Platform and how to architect it.


### Keeping Costs Down

The Google Cloud Platform offers cloud-based services on a pay-as-you-go basis. Costs are determined by the services you run and amount of time you use them. Different combinations of instance types and sizes have different costs. For more information about services pricing, see Google Cloud Platform pricing. You can estimate your total monthly costs using the Google Cloud Platform pricing calculator. You can also compare on-premises vs the cloud using the Google Cloud Platform TCO calculator.

To help monitor and control usage costs on an ongoing basis, you can set up billing alerts for the Google Cloud Platform to alert you when your monthly Google Cloud Platform costs reach your predefined spending threshold. For more information, see Set budgets and alerts at the Google website.


## Tableau Server on the Google Cloud Platform Topology

When deploying Tableau Server on the Google Cloud Platform, you may choose the level and depth of integration between Tableau Desktop and Tableau Server on your Google Compute Engine (GCE) virtual machines (VMs). You can use Tableau Desktop and its ability to extract data from your data sources to act as a bridge between your data and Tableau Server. Based on your needs, or if you already have a lot of data in the Google Cloud Platform, you might instead choose to leverage the full range of Google Cloud Platform services in conjunction with Tableau Server. The following diagram shows data source integration with Tableau Desktop and Tableau Server.



In the following diagram, all of your data is hosted on the Google Cloud Platform. You can analyze both structured and unstructured data managed in a secure, scalable manner. You may leverage data that resides on the Google Cloud Platform only, unmanaged data that

lives outside of the Google Cloud Platform, or a combination of both. This flexibility greatly increases the ability of your organization to support moves to the cloud from on-premise data, since both types of data is supported equally.



# Selecting a Google Compute Engine Virtual Machine Type and Size

The Google Cloud Platform offers many types of Google Compute Engine (GCE) virtual machines (VMs) in various sizes. Choosing the right VM for your workload is an important factor for a successful Tableau Server deployment. You can choose from a wide range of VMs. For a complete list of all available VM types and sizes, see the Machine Types page at the Google website.

It is important to select a VM that can run Tableau Server. The VM must meet the Tableau Server hardware guidelines (a minimum of 8 cores and 32 GB of RAM).

At minimum, a 64-bit Tableau Server requires a 2-core CPU (the equivalent of 4 Google Compute Engine vCPUs) and 8 GB RAM. However, a total of 8 CPU cores (16 Google

Compute Engine vCPUs) and 64GB RAM are strongly recommended for a single production Google Compute Engine VM.

The Windows Operating system will recognize these 16 vCPU as 8 cores, so there is no negative licensing impact.

### Typical VM types and sizes for development, test, and production environments

• n1-standard-16

### Recommended specifications for a single production instance

Component/Resource	Google Cloud Platform
CPU	16+ vCPU
Operating System	Windows:
	Windows Server 2012r2, 64-bit
	Windows Server 2016, 64-bit
Memory	64+ GB RAM (4GB RAM per vCPU)
Storage	Two volumes:
	30-50 GiB volume for the operating system
	100 GiB or larger volume for Tableau Server
Storage type	SSD persistent disk, 200GB++
	For more information about SSD persistent disks, see Storage
	Options at the Google Cloud Platform website.
Disk latency	Less than or equal to 20ms as measured by the <b>Avg. Transfer disk/sec</b> Performance Counter in Windows.
	along ood i Shormanoo Oodintoi iii Wiindows.

# Self-Deploy a Single Tableau Server on the Google Cloud Platform

You can install and run Tableau Server on a Google Compute Engine (GCE) virtual machine (VM). Perform the following tasks to install and configure Tableau Server on a Google Compute Engine VM.

Step 1: Set up a Google Compute Engine VM

Step 2: Connect to your Google Compute Engine VM

Step 3: Install Tableau Server on your Google Compute Engine VM

Step 4: Access Tableau Server from a remote browser

Step 5: Publish data to Tableau Server on your Google Compute Engine VM

Step 6: Manage Tableau Server licenses

### Step 1: Set up a Google Compute Engine VM

Create a Google Compute Engine virtual machine (VM) where you'll install Tableau Server.

- 1. Sign in to the Google Cloud Platform Console (https://console.cloud.google.com/).
- 2. If you haven't already, create a new project and set up billing. For more information, see Creating and Managing Projects at the Google website.
- 3. On the Google Cloud Platform dashboard, in the navigation pane, under **Compute**, click **Compute Engine**.
- 4. In the Compute Engine VM instances dialog box, click Create.

- 5. On the **Create an instance** page, specify the following instance properties:
  - a. Name: Enter a name for your virtual machine (VM).
  - b. **Zone:** To help reduce latency, choose the zone closest to your data source and users.
  - c. Machine type: Select a VM that meets the system requirements for Tableau Server. For example, select the n1-standard-16 machine type, click Customize, and then increase the memory to 64 GB.
  - d. Container: If selected, clear the Deploy a container image to this VM instance check box (the default).
  - e. Boot disk: Click Change, and then select Windows Server 2016 Datacenter with a 128 GB SSD persistent disk, and then click Select.
  - f. Identity and API access: Use the default setting.
  - g. Firewall: Select Allow HTTP traffic and Allow HTTPS traffic.
- 6. When you've finished the settings, review your selections, and then click **Create**.

### Step 2: Connect to your Google Compute Engine VM

After you create your Google Compute Engine (GCE) virtual machine (VM), you must connect to it and prepare it to install Tableau Server.

- 1. In the Compute Engine console, click VM instances.
- 2. In the list of VM instances, select your instance.
- 3. In the Connect column, click the RDP pop-up menu, click Set Windows password.
- 4. On the **Set new Windows password** dialog box, in the **Username** field, specify a

username (or leave the default one). Store the username in a safe place.

Click Set to generate a password. It might take several seconds before the New Windows password dialog box appears. Store the password in a safe place.

**Important:** This is your only chance to copy the password.

- 6. On the **VM instances** page, in the **Connect** column, click the **RDP** pop-up menu, and then select **Download the RDP file**. Save the .rdp file to your computer.
- 7. Connect to your VM using the .rdp file you saved. Provide the username and password you generated above for the Google Compute Engine VM. (If you're already signed into a Windows network, such as your organization's network, choose **Other User** and enter your credentials in those boxes.)

You will see one or more messages telling you that the remote connection can't be identified. This is normal.

**Note:** The RDP file references the instance by using an external IP address. By default, this is an ephemeral IP address, which might be renewed when you stop or restart the server. In that case, you'll need to get a new copy of the RDP file. For longer-term use, GCP provides static IP addresses at additional cost.

Remote Desktop signs you in to the Google Compute Engine VM.

For more information about how to connect to Google Compute Engine VMs, see Connecting to Instances at the Google website.

### Step 3: Install Tableau Server on your Google Compute Engine VM

Installing Tableau Server on a Google Compute Engine (GCE) virtual machine (VM) is similar to installing it on any other server.

#### Notes:

- You can select local authentication or Active Directory (AD) authentication only
  during initial installation. AD is only required for multi-worker configurations. For
  more information, see Setting up Active Directory on Google Compute Engine at
  the Google website.
- The Run As user must be a local user on the server instance.
- Copy the Tableau Server installation program to your VM by doing one of the following:
  - Download the installer directly. While logged into the VM, open a browser, browse to the Tableau Server download page, and download the 64-bit version of Tableau Server.

**Note:** The default enhanced security configuration on Windows Server dictates that Internet Explorer is always set to High for the Internet zone and cannot be changed for that zone. Therefore, as you browse to public sites using Internet Explorer, you must add those sites to the list of trusted sites.

- Copy the installer to the VM. If you already have a copy of the Tableau
   Server installer on your computer, copy it to the VM. Create a folder on the VM
   where you want to put the installer. From your computer, upload the Tableau
   Server installer file (for example, TableauServer-64bit-10.5.exe) to the VM. For
   more information about how to copy files to a Google Compute Engine VM, see
   Transferring Files to Instances at the Google website.
- 2. Run the Tableau Server installer on the VM to start the server installation process.

The installation process works the same as it does on any other server. For more information, search for "Install and Configure Tableau Server" in the Tableau Server Help.

### Step 4: Access Tableau Server from a remote browser

Make sure that users can access the Google Compute Platform virtual machine (VM) where you've installed Tableau Server.

- 1. In the Google Compute Platform console, under **Compute**, click **Compute Engine**, and then click **VM instances**. Find the external IP address associated with the VM.
- 2. On another computer (not on the VM), open a browser.
- 3. In the browser, type the external IP address of the Tableau Server you installed on the VM. For example, http://l3.64.47.61.

**Note:** As noted earlier, the external IP is an ephemeral address. It is released when you stop the instance and a new external IP is assigned on restart. If you stop your instance, you may need to retrieve the new external IP address to access the server using your browser. GCP provides persistent static IP addresses. This time the URL resolves correctly and you reach the sign-in page for your instance of Tableau Server.

4. Sign in using the credentials for the administrator user that you created at the end of the installation process. When you've signed in, you see the Projects page in Tableau Server.

### Step 5: Publish data to Tableau Server on your Google Compute Engine VM

After you set up Tableau Server on a Google Compute Engine (GCE) virtual machine (VM), users in your organization can publish workbooks and data sources to the server. The process works the same way that it does if Tableau Server is installed on premises, except that users must sign in to the server that is running on the VM.

Before you allow users to publish, make sure that each user has been created with the Publisher site role in Tableau Server and that the users have Publisher permissions. For more information, search for "Add Users to the Server" in the Tableau Server Help.

To publish workbooks and data sources to Tableau Server, users must sign in to the server by using the cloud server IP address using credentials they've been assigned. For more information, see How to Publish Workbooks to a Tableau Server.

### Step 6: Manage Tableau Server licenses

You don't need to manage your Tableau Server license if you shut down your Google Compute Engine (GCE) virtual machine (VM) using the Google Cloud Platform console or from inside the VM itself. When you stop a Google Compute Engine VM with persistent SSD disk using the GCP Compute Engine console, the VM does not incur charges, but resources attached to the VM will still incur charges.

Deleting a VM deallocates all of its resources, including external storage. You might delete your VM when you no longer need it. Always deactivate your Tableau Server license before you shut down and delete your VM.

Before you delete your VM, do the following:

- 1. Sign in to your VM.
- 2. Create a backup of Tableau Server, and then copy the .tsbak file to another location, such as Google Cloud Storage, that will be accessible after the VM is no longer available. For more information, search for "Perform a Full Backup and Restore of

Tableau Server" in the Tableau Server Help.

3. Use the tsm licenses deactivate command to deactivate your Tableau Server product key. You can now shut down and delete your VM.

### Self-Deploy Tableau Server on the Google Cloud Platform in a Distributed Environment

If you want to run Tableau Server in a distributed environment, also known as a cluster, you need to launch three or more Google Compute Engine (GCE) virtual machines (VMs) of the same type and capacity and configure them as additional nodes. This scenario assumes that you have three Google Compute Engine VMs with Tableau Server installed on each instance. One instance is configured as the initial node, and the other two instances are configured as additional nodes.

Use the following steps to install and deploy Tableau Server on a cluster of three Google Compute Engine VMs in a highly available and scalable configuration.

Step 1: Create a Google Cloud Platform Virtual Private Cloud (VPC)


Step 2: Deploy Three Google Compute Engine VMs

Step 3: Create a Google Cloud Platform Load Balancer for the Tableau Server Cluster

### Step 1: Create a Google Cloud Platform Virtual Private Cloud (VPC)

You must have an existing Google Cloud Platform custom mode Virtual Private Cloud (VPC) with a private and a public subnet across three different zones. For information about


how to plan and create a custom mode VPC network with custom subnets, see Using VPC Networks at the Google website.



### Step 2: Deploy Three Google Compute Engine VMs

Deploy three Google Compute Engine virtual machines (VMs) of the same type and capacity, in the private subnet, with each VM in its own zone. Select VMs that meet the system requirements for Tableau Server. You'll install Tableau Server on each of the Google Compute Engine VMs, and use one node as the initial server and the two other nodes as additional servers.

For more information about installing Tableau Server in a distributed Windows environment, search for "Distributed and Highly Available Installations" and "Install and Configure Additional Nodes" in the Tableau Server Help.



Step 3: Create a Google Cloud Platform Load Balancer for the Tableau Server Cluster

Read Setting up a load balancer at the Google website, and follow the steps to launch a load balancer within your Google Cloud Platform Virtual Private Cloud (VPC).

1. Create and launch either an Internet-facing load balancer or an internally accessible load balancer:

- To launch a public, Internet-facing load balancer, follow the steps in Setting Up
  HTTP(S) Load Balancing at the Google website, and select the two public subnets. Make sure that you configure the load balancer with SSL, as explained in
  SSL Certificates at the Google website.
- To launch an internally accessible load balancer, follow the steps in Setting Up Internal Load Balancing at the Google website, and select the two private subnets.
- Ensure that your VPC network firewall rules are configured to allow access on port 80
  or 443 only, with the source limited to hosts or ranges of hosts that will access Tableau
  Server. For more information about firewall rules, see Firewall Rules Overview at the
  Google website.
- 3. Specify the ping path as /.
- 4. Select the Tableau Server instances and follow the instructions in Creating Cross-Region Load Balancing at the Google website, so that the load balancer can balance the traffic across the instances in multiple zones.
- Update Tableau Server to use the load balancer. For more information, search for "Add a Load Balancer" in the Tableau Server Help.

# Troubleshooting Tableau Server on the Google Cloud Platform

If you're having trouble with Tableau Server on your Google Compute Engine (GCE) virtual machine (VM), or with getting access to Tableau Server after installation, review these troubleshooting tips.

Cannot connect to the VM using RDP

One or more of the following issues might prevent you from connecting to your VM using RDP:

- Make sure you're using the right credentials.
- Choose the **Other User** option and enter your credentials there.
- Make sure that you're using a username that is valid on the GCP instance. For
  instance, if you created the instance with an administrator account of myuser,
  enter .\myuser as the username in the RDP dialog box.

#### Cannot access the server from a remote browser

One or more of the following issues might prevent you from accessing the server from a remote browser:

- Sign in to the instance and make sure that the server is running.
- In the instance, open a browser and access the server locally (for example, using http://localhost or http://localhost:port, where port is the port number that the server was configured to listen on).
- In the GCP Compute Engine console, make sure that you've configured an endpoint to allow HTTP traffic to the instance.

**Note:** You cannot use the Windows ping utility to test connectivity to the instance. The ping utility will always report a timeout when used from the public internet.

#### • You receive the following error message: Tableau Server is unlicensed

This error can occur if you've shut down instances without first deactivating the license. Contact Tableau Support.

#### Tableau Server does not use all CPU cores

One or more of the following symptoms might occur when working with Tableau Server core-based licensing:

- When installing Tableau Server, the installer might show fewer cores than you would expect to see for the computer running Tableau Server.
- On the Licenses page on Tableau Server, the number of cores listed under Licenses in Use is less than you would expect to see.
- When you run tsm licenses list, Tableau Server might report fewer cores in use that you would expect to see.

For more information, see Not All Cores Recognized by Tableau Server.