

HENCEFORTH

A FORTH Programming Environment for iOS

+ Bitcoin SV Wallet

```
> : SQUARE DUP * ;
```

```
> 5 SQUARE .
```

```
25 ok.
```

```
> TX-NEW 5000 TX-SET-FEE
```

```
> TX-ADD-OUTPUT TX-BROADCAST
```

Write Bitcoin Script in FORTH – the language
Bitcoin Script was modeled on. No compiler gap,
no IR, no formal proofs needed, because source
and target are the same kind of machine.

You think on a stack.

You type on a stack.

You publish to a stack.

Henry Hudson
henry@henceforth.club

v1.0 · 2026

```
ok.
```

1	About	1
1.1	Links to Source Code	1
1.2	Support	1
2	Goals	2
2.1	Achieved	2
2.2	Get People Coding	2
2.3	Future	2
3	Credits	4
3.1	Starting Forth – Leo Brodie	4
3.2	BITSRFR	4
3.3	Bitcoin	4
3.4	SwiftBSV	4
4	Documentation	5
4.1	Built-in Words	5
4.1.1	Compile Words	5
4.1.2	Meta Programming	6
4.1.3	Arithmetic Operators	7
4.1.4	Double-Cell Arithmetic	9
4.1.5	Numeric Output	9
4.1.6	Comparison Operators	10
4.1.7	Bitwise Operators	11
4.1.8	Stack Operators	12
4.1.9	Return Stack Operators	13
4.1.10	Decision Operators	14
4.1.11	Loop Operators	16
4.1.12	Base Operations	17
4.1.13	Pop-up Operations	17
4.1.14	Constants and Variables	18

4.1.15	Terminal Operators	20
4.1.16	Other Words	23
4.1.17	Data Conversion	23
4.1.18	String Operations	24
4.1.19	Networking Operations	25
4.1.20	Transaction Builder	25
4.1.21	Bitcoin Cryptography	28
4.1.22	BAP Identity	29
4.1.23	Script Recording	29
4.1.24	Script Bridge Words	30
4.1.25	Script Helper Words	31
4.1.26	OPCodes	33
5	Bitcoin Wallet	40
5.1	Wallet Architecture	40
5.1.1	Address Discovery	40
5.2	Wallet Cards	41
5.3	Transactions	41
5.3.1	Receiving	41
5.3.2	Notifications	42
5.3.3	Sending	42
5.3.4	Paymail	44
5.3.5	Transaction History	44
5.4	SPV Architecture	44
5.4.1	Trust Anchor	45
5.4.2	Header Store	45
5.4.3	Validated Tip	45
5.4.4	Commit Path	46
5.4.5	Auto-Sync Service	46
5.4.6	Bounded Lookup and Verification	47
5.4.7	Checkpoint Maintenance	47
5.5	Cold Mode and Air-Gap Bundles	48
5.5.1	Bundle Formats	48
5.5.2	Air-Gap Tools UI	48
5.5.3	Watcher-Side Persistence	49
5.6	Wallet Data Management	49

5.7	UTXOs and Balance	50
5.7.1	Ordinal Protection	50
5.7.2	UTXO Split	50
5.8	API Providers	51
5.9	Security	51
5.9.1	Payment Approval Cache	51
5.9.2	Encrypted Off-Device Backup	52
5.9.3	QR Code Scanner	53
5.9.4	BRC-103 Authentication	53
5.9.5	BRC-100 Wallet Interface	53

1.1 Links to Source Code

github.com/henryhudson/FORTHapp

Running the project requires Xcode on any iPhone / iPad device. Will soon be optimised for all Apple products.

Private for the time being – get in touch if you would like access.

1.2 Support

[Follow us on Twitter](#)

2.1 Achieved

- **Bitcoin (BSV) integration** – full wallet with HD key derivation (BIP-44 and Type42), transaction building, ARC broadcasting with failover, SPV verification, Paymail support, and 140+ Bitcoin Script opcodes including the Chronicle upgrade.
- **Block headers** – locally chain-linked header store anchored to a hardcoded checkpoint, auto-synced from chain tip on every launch via a WebSocket history stream. SPV Merkle proof verification is bounded to the chain-validated range – no silent network fallback for missing headers.
- **SwiftBSV** – fully integrated for transactions, Script building, BIP-32/39 key management, and ECDSA signing.
- **OPCodes** – all standard and Chronicle-restored opcodes available as FORTH words. Script Recording mode assembles Bitcoin Scripts from the terminal.
- **Files** – full CRUD for .fs and .forth files with iCloud backup. Script files identified by SCRIPT-BEGIN/SCRIPT-END markers.
- **Colour customisation** – foreground and background colour pickers, keyboard selection, and Dynamic Type support throughout.
- **Forth-2012 compliance** – 133/133 CORE words implemented, verified by the Hayes test suite.

2.2 Get People Coding

Provide a simple interface for the FORTH programming language, making it easy for people to learn to code.

2.3 Future

- Full sCrypt capability – each FORTH file will create a sCrypt that runs the opcodes within.

- CRDT (Conflict-free Replicated Data Type) system using the timestamp server for user-defined words.
- Trigonometry and calculus extensions.

3.1 Starting Forth – Leo Brodie

Leo Brodie, author of Starting Forth – a great textbook, suitable for both novices and professionals.

[Starting FORTH \(PDF\)](#)

3.2 BITSRFR

Fellow surfer of the binary ocean who has made FORTH tutorials and is making a Swift command line FORTH application.

[YouTube](#) · [cruxFORTH on GitHub](#)

3.3 Bitcoin

The greatest monetary system ever created. Invented by Satoshi Nakamoto – please read the white paper.

[Bitcoin White Paper](#)

3.4 SwiftBSV

The Swift SDK that powers every cryptographic operation in the Henceforth wallet – BIP-32/39 key derivation, Type42 (BRC-42) invoice keys, ECDSA signing, BSM, ECIES (BIE1 wire format), Script construction, the full BSV opcode set, transaction building, and SPV verification. Originally written by Will Townsend at [wtsnz/SwiftBSV](#); the fork at [henryhudson/SwiftBSV](#) continues that foundation with Swift 6 strict concurrency, modern Apple platform targets, and a 41-page LaTeX book of its own.

[SwiftBSV Book \(PDF\)](#)

Everything in FORTH is a **word** separated by spaces. That's all there is to the syntax. It's so simple.

FORTH is LIFO – FORTH is a stack-based programming language which operates on a Last In, First Out principle.

4.1 Built-in Words

Ideally we give the user just enough to make use of FORTH and through FORTH some of Swift's functionality such as networking requests, the timer built into Swift, etc. But not so much as to be relied upon – user creation of words should be encouraged, and if possible a community database of words and their definitions be made.

4.1.1 Compile Words

One of the great things about FORTH is its ability to extend the compiler during run time.

Compile Operators

:	puts the user into compile mode where they can start to define their own word.
;	exits compile mode so that word interpretation can again occur.
recurse	calls the word being executed.
exit	exits the current word.
immediate	marks the most recently defined word as immediate, causing it to execute during compilation rather than being compiled.
postpone	forces compilation of the next word, even if it is marked IMMEDIATE. Used inside definitions to defer execution of immediate words.
value	(x --) Creates a named value that can be read by name and changed with T0. Usage: 42 value myval

```

to      (x --)
        Change the value of a word created with VALUE.
        Usage: 99 to myval

does>   ( -- )
        Defines the runtime behaviour of a CREATE'd word.
        Everything after DOES> runs when the created word
        is executed, with the data-field address on the
        stack.
        Usage: : array create cells allot does> swap
        cells + ;

include ( -- )
        Loads and runs a FORTH file.
        Usage: include maths.fs

```

4.1.2 Meta Programming

Meta Programming

```

'      ( -- xt)
        Gets the execution token of the named word. Used to
        get a reference to a word for later execution.

[']    ( -- xt)
        Compile-time version of ' (tick). Compiles the
        execution token of a word into the current definition.

execute (i*x xt -- j*x)
        Executes the word whose execution token is on the stack.
        The i*x/j*x notation acknowledges that the executed
        word may consume and produce arbitrary values; only the
        xt itself is consumed by EXECUTE.

literal Compile: (x -- ) Run-time: ( -- x)
        At compile time, compiles a numeric literal into the
        current definition; at run time of the containing word,
        pushes that literal onto the stack. Used inside
        IMMEDIATE words to inject computed constants into the
        word being defined.

state  ( -- addr)
        Returns the address of the STATE variable. STATE is 0
        when interpreting, -1 when compiling.

[      (--)
        Switches from compilation mode to interpretation mode.

]      (--)
        Switches from interpretation mode to compilation mode.

```

```

evaluate (c-addr u --)
  Interprets the string at c-addr of length u as if
  it were typed at the terminal.

find      (c-addr -- c-addr 0 | xt 1 | xt -1)
  Searches the dictionary for the counted string at
  c-addr. Returns xt and 1 (immediate) or -1 (normal),
  or c-addr and 0 if not found.

>body     (xt -- a-addr)
  Returns the data-field address of a CREATE'd word
  given its execution token.

>in        ( -- a-addr)
  Returns the address of the variable holding the
  current input parse position.

>number    (ud1 c-addr1 u1 -- ud2 c-addr2 u2)
  Converts characters at c-addr to a number using
  the current BASE. Stops at the first non-convertible
  character.

```

4.1.3 Arithmetic Operators

Arithmetic is done using reverse Polish notation, so the numbers are required on the stack before the arithmetic operator can be used.

Arithmetic Operators

```

+          (n1 n2 -- sum)
  Takes the top two items from the stack and returns
  their sum to the stack.

-          (n1 n2 -- difference)
  Takes the top two items from the stack and returns
  their difference to the stack.

*          (n1 n2 -- product)
  Takes the top two items from the stack and returns
  their product to the stack.

/          (n1 n2 -- quotient)
  Takes the top two items from the stack and returns
  their quotient to the stack.

*/         (n1 n2 n3 -- result)   result = (n1*n2/n3)
  Takes the top three items from the stack. The first
  two are multiplied together, then divided by the last
  item. The result is appended to the stack.

mod        (n1 n2 -- modulus)

```

```
Takes two items from the stack, divides the first by
the second and the remainder is added to the stack.

/mod      (n1 n2 -- modulus quotient)
Takes the last two items from the stack and returns
their modulus and their quotient to the stack.

abs       (n -- |n|)
Takes the last value from the stack and returns its
absolute value.

negate    (n -- -n)
Takes the last item from the stack and returns its
value negated.

max       (n1 n2 -- max)
Takes the last two values from the stack and returns
the greatest value to the stack.

min       (n1 n2 -- min)
Takes the last two values from the stack and returns
the smallest value to the stack.

1+        (n -- n+1)
Takes the top item from the stack, adds one to it and
returns the result to the stack.

1-        (n -- n-1)
Takes the top item from the stack, minuses one from it
and returns the result to the stack.

2+        (n -- n+2)
Adds 2 to the top of the stack. Henceforth extension ---
Forth-2012 has only 1+ and 1-. Equivalent to \texttt{2
+}.

2-        (n -- n-2)
Subtracts 2 from the top of the stack. Henceforth
extension. Equivalent to \texttt{2 -}.

2*        (n -- n*2)
Takes the top item from the stack, multiplies it by
two and returns the result to the stack.

2/        (n -- n/2)
Takes the top item from the stack, halves it and
returns the result to the stack.

sumStack  (n1 ... n -- sum)
Sums every value on the stack into a single result.
Henceforth extension --- not in Forth-2012.

*/mod     (n1 n2 n3 -- remainder quotient)
Multiplies n1 by n2, then divides by n3. Returns
```

```
both the remainder and the quotient.
```

4.1.4 Double-Cell Arithmetic

Double-cell words operate on 64-bit values represented as two stack items (high cell on top). These are required by the Forth-2012 CORE standard for intermediate precision in calculations.

Double-Cell Arithmetic

```
s>d      (n -- d)
          Sign-extends a single-cell number to a double-cell
          number. Required before FM/MOD or SM/REM.

m*        (n1 n2 -- d)
          Signed multiply of n1 by n2, producing a double-cell
          result. No overflow possible.

um*       (u1 u2 -- ud)
          Unsigned multiply of u1 by u2, producing an unsigned
          double-cell result.

fm/mod    (d n1 -- n2 n3)
          Floored division of double-cell d by n1. The quotient
          n3 rounds toward negative infinity. The remainder n2
          has the same sign as the divisor.

sm/rem    (d n1 -- n2 n3)
          Symmetric division of double-cell d by n1. The
          quotient n3 rounds toward zero. The remainder n2 has
          the same sign as the dividend.

um/mod    (ud u1 -- u2 u3)
          Unsigned division of unsigned double-cell ud by u1.
          Returns remainder u2 and quotient u3.
```

4.1.5 Numeric Output

Numeric Output

```
<#       (--)
          Initialises pictured numeric output conversion.

#        (ud1 -- ud2)
          Converts one digit from the double number and adds it
          to the pictured numeric output buffer.

#s       (ud -- 0 0)
          Converts all remaining digits from the double number
```

```

        until it becomes zero.

#>      (xd -- c-addr u)
        Completes pictured numeric conversion and returns the
        address and length of the formatted string.

hold    (char --)
        Adds a character to the beginning of the pictured
        numeric output buffer.

sign    (n --)
        If the number is negative, adds a minus sign to the
        pictured numeric output.

.r      (n1 n2 --)
        Displays a number right-aligned in a field of n2
        characters width.

u.      (u --)
        Displays an unsigned number followed by a space.

u.r     (u n --)
        Displays an unsigned number right-aligned in a field
        of n characters width.

```

4.1.6 Comparison Operators

f is a flag or bool [true|false]. Per the Forth-2012 standard, TRUE is -1 (all bits set) and FALSE is 0. Any non-zero value is considered true by IF, AND, OR, and other conditional words.

Comparison Operators

```

=      (n1 n2 -- f)
        Takes the top two values from the stack, checks if they
        are equal, then returns the flag to the stack.

<>     (n1 n2 -- f)
        Takes the top two values from the stack, checks if they
        are NOT equal, then returns the flag to the stack.

<      (n1 n2 -- f)
        Takes the top two values from the stack, checks if n1 is
        less than n2, then returns the flag to the stack.

>      (n1 n2 -- f)
        Takes the top two values from the stack, checks if n1 is
        greater than n2, then returns the flag to the stack.

&&     (n1 n2 -- f)

```

Logical AND --- Henceforth extension. Returns -1 if both values are non-zero, 0 otherwise. Forth-2012 has no separate logical AND because the standard `\texttt{AND}` is bitwise, which produces logical AND when both operands are well-formed flags.

```
|| (n1 n2 -- f)
Logical OR --- Henceforth extension. Returns -1 if either
value is non-zero, 0 otherwise. See \texttt{\&\&} note above
for why Forth-2012 doesn't ship a separate operator.

0= (n1 -- f)
Takes the top value from the stack, checks if it is equal
to zero, then returns the flag to the stack.

0< (n1 -- f)
Takes the top value from the stack, checks if it is less
than zero, then returns the flag to the stack.

0> (n1 -- f)
Takes the top value from the stack, checks if it is
greater than zero, then returns the flag to the stack.

u< (u1 u2 -- f)
Unsigned comparison. Returns true if u1 is less than u2
when both are treated as unsigned values.
```

4.1.7 Bitwise Operators

Bitwise Operators

```
and (x1 x2 -- x3)
Bitwise AND of the top two values (Forth-2012 6.1.0720).
Note: when both operands are well-formed flags (0 or
-1), bitwise AND produces logical AND --- so you don't
need a separate logical operator if you keep flags
well-formed.

or (x1 x2 -- x3)
Bitwise OR of the top two values (Forth-2012 6.1.1980).
Same flag-friendliness as AND.

xor (x1 x2 -- x3)
Bitwise XOR of the top two values (Forth-2012 6.1.2490).

invert (n -- ~n)
Bitwise inversion. Flips every bit of the top value
on the stack.

rshift (n1 n2 -- n3)
Takes the top two values from the stack and returns the
```

```

    result of n1 bitwise right-shifted by n2.

lshift (n1 n2 -- n3)
    Takes the top two values from the stack and returns the
    result of n1 bitwise left-shifted by n2.

```

4.1.8 Stack Operators

Stack Operators

```

.s      ( -- )
    Displays the current stack to the terminal.

.      (n -- )
    Takes the last value from the stack and pops it
    to terminal.

dup     (n -- n n)
    The top value is taken from the stack, duplicated
    and both the original and copy returned.

?dup    (n -- 0 | n n)
    Duplicates the top item on the stack only if it
    is non-zero.

nip     (n1 n2 -- n2)
    The first item below the top of the stack is
    dropped.

swap    (n1 n2 -- n2 n1)
    The last two values are taken from the stack,
    swapped and then returned to the stack.

drop    (n -- )
    Discards the top item from the stack.

2dup    (n1 n2 -- n1 n2 n1 n2)
    The top two values from the stack are taken,
    copied and both original and copy returned.

over    (n1 n2 -- n1 n2 n1)
    The second value from the stack is copied and
    added to the stack.

pick    (x_u ... x_1 x_0 u -- x_u ... x_1 x_0 x_u)
    Pops u and pushes a copy of the u-th item from
    the stack (0-indexed from top: 0 PICK is DUP,
    1 PICK is OVER).

rot     (n1 n2 n3 -- n2 n3 n1)
    The top three values of the stack are taken and

```



```

rotated left then returned to the stack.

-rot      (n1 n2 n3 -- n3 n1 n2)
The top three values of the stack are taken and
rotated right then returned to the stack.

tuck      (n1 n2 -- n2 n1 n2)
The top two values from the stack are taken. The
top value is copied and placed before the second
value in the stack (third value deep).

2drop     (n1 n2 -- )
The top two values are taken from the stack and
discarded.

2swap     (n1 n2 n3 n4 -- n3 n4 n1 n2)
The top four values are taken from the stack, and
the order of the two pairs is reversed.

2over     (n1 n2 n3 n4 -- n1 n2 n3 n4 n1 n2)
The first four values are taken from the stack,
with items 3 and 4 deep being copied and added.

reverseStack (n1 n2 ... nlast -- nlast ... n2 n1)
Reverses the order of every item on the stack.
Henceforth extension --- not in Forth-2012.

depth     ( -- n)
Returns the number of items currently on the data
stack before depth was executed.

roll      (xu xu-1 ... x0 u -- xu-1 ... x0 xu)
Rotates u+1 items on the stack. The u-th item is
moved to the top of the stack.

stackCount ( -- n)
Pushes the number of items currently on the stack.
Novice-friendly Henceforth alias for \texttt{depth}
(Forth-2012 6.1.1200).

```

4.1.9 Return Stack Operators

Return Stack Operators

```

>r      (x -- ) ( R: -- x)
Pops the parameter stack and pushes onto the return stack.

r>      ( -- x) ( R: x -- )
Pops the return stack and pushes onto the parameter stack.

r@      ( -- x) ( R: x -- x)

```

Copies the top of the return stack to the parameter stack.

i (-- x)
The innermost DO LOOP's index. Copies the top of the return stack.

i' (-- x)
The next-outer loop's index in nested DO LOOPS. Copies the second-from-top of the return stack. Note: differs from FIG-FORTH `\texttt{I'}` (which returned the inner loop's limit) because Henceforth stores only loop indices on the return stack, not [limit, index] pairs. In Henceforth `\texttt{i'}` and `\texttt{j}` return the same value.

j (-- x)
The next-outer loop's index in nested DO LOOPS (Forth-2012 6.1.1730). In Henceforth's storage model this is the second-from-top of the return stack --- same value as `\texttt{i'}`.

nth (u -- x)
Pops u and pushes the u-th item from the return stack (0-indexed from top). Henceforth extension --- Forth-2012 has no return-stack analogue of PICK.

4.1.10 Decision Operators

f is a flag or bool [true | false].

Decision Operators

if (x --)
Pops one cell. If non-zero, executes the words up to ELSE or THEN. If zero, skips over them.

else (--)
The optional false branch of an IF...THEN. Has no runtime stack effect --- the flag was already consumed by IF.

then (--)
Denotes the end of the IF...THEN statement. Has no runtime stack effect.

not (x -- f)
Synonym for `\texttt{0=}` (returns -1 if x is 0, 0 otherwise)

.
Retained for FIG-FORTH compatibility. Forth-2012 dropped `\texttt{NOT}` because pre-2012 implementations disagreed on whether it meant `\texttt{0=}` (logical) or `\texttt{INVERT}`

(bitwise). Henceforth's `\texttt{NOT}` is the logical version
 .
 Prefer `\texttt{0=}` or `\texttt{INVERT}` in new code.

`within` (n1 n2 n3 -- f)
 Takes three values from the stack and checks if n2 is a
 number within n1 and n3.

`true` (-- -1)
 Pushes the true flag (-1, all bits set) to the stack.
 Per Forth-2012 standard.

`false` (-- 0)
 Pushes the false flag (0) to the stack.

`case` (--)
 Begins a CASE...OF...ENDOF...ENDCASE switch statement.
 The selector value must be on the stack.

`of` (x1 x2 -- | x1)
 Compares the top of stack with the selector. If equal,
 drops both and executes the clause. If not, skips to
 ENDOF.

`endof` (--)
 Ends an OF clause. Branches to after ENDCASE.

`endcase` (x --)
 Ends a CASE statement. Drops the selector value if no
 OF clause matched.

`catch` (i*x xt -- j*x 0 | i*x n)
 Executes the word referred to by xt while protecting the
 data stack. Returns 0 on success. If THROW is called
 during execution, restores the stack to its pre-CATCH
 depth and returns the thrown error code n. The i*x/j*x
 notation makes it explicit that the stack contents may
 differ between success and failure paths.

`throw` (k*x n -- k*x | i*x n)
 If n is 0, does nothing (no-op). Otherwise unwinds the
 stack to the nearest CATCH, leaving n as the result.
 The exception code is implementation-defined; -1 is
 conventional for ABORT, -2 for ABORT".

4.1.11 Loop Operators

Loop Operators

```

do      (n1 n2 --)
        n1 is endValue, n2 is startValue. Repeats words between
        do and loop from startValue until endValue is met.

loop    ( -- )
        Ends loop.

+loop   (n1 -- )
        Loops in n1 increments.

every   (n1 -- )
        Performs the following word every n1 seconds until STOP
        is called. Henceforth scheduling extension --- not in
        Forth-2012.

stop    ( -- )
        Stops the EVERY loop. Henceforth extension --- pairs
        with EVERY only.

begin   ( -- )
        Marks the start of a BEGIN...UNTIL or BEGIN...WHILE
        ...REPEAT loop. Has no runtime stack effect itself.

while   (x -- )
        Tests a condition within a BEGIN...REPEAT loop. Pops
        one cell; if zero, exits the loop.

repeat  ( -- )
        Marks the end of a BEGIN...WHILE...REPEAT loop and
        jumps back to BEGIN.

until   (x -- )
        Pops one cell; if zero, jumps back to BEGIN. If non-zero,
        falls through.

leave   ( -- )
        Exits the current DO...LOOP or DO...+LOOP immediately.
        Must be used within a loop.

unloop  ( -- )
        Discards the loop control parameters from the return
        stack. Used when exiting a loop early with LEAVE.

?do     (n1 n2 --)
        Like DO but skips the loop entirely if the start and
        end values are equal. Executes loop from n1 to n2-1.

again   ( -- )
        Unconditional branch back to BEGIN. Creates an infinite
        loop (BEGIN...AGAIN). Use LEAVE or the Escape key to

```

```
exit.
```

4.1.12 Base Operations

Much like FORTH, Henceforth accepts integers as binary, octal, decimal and hexadecimal. Just be sure to change the base.

Base Operations

```
base      ( -- addr)
           Returns the address of the BASE variable (Forth-2012
           compliant). Use BASE @ to read and n BASE ! to write.
           Supports bases 2 through 36.

decimal   (--)
           Sets BASE to 10. Forth-2012 6.1.1170.

binary    (--)
           Sets BASE to 2. Henceforth extension. Equivalent to
           \texttt{2 BASE !}.

octal     (--)
           Sets BASE to 8. Henceforth extension. Equivalent to
           \texttt{8 BASE !}.

hex       (--)
           Sets BASE to 16. Forth-2012 6.2.1660.
```

4.1.13 Pop-up Operations

Pop-up Operations

```
lineChart (--)
           Displays a line chart representing the stack.

barChart  (--)
           Displays a bar chart representing the stack.

pieChart  (--)
           Displays a pie chart representing the stack with
           slices in proportion to its value's weight compared
           to the stack's sum.
```

4.1.14 Constants and Variables

Constants and Variables

```

constant (n --)
    Takes a value from the stack and a name and creates a
    constant of that value called by the name provided.

variable (--)
    Creates a variable whose name will be the first string
    of characters following variable, initially zero.

!      (n address --)
    Stores a number to the address provided.

@      (address -- n)
    Gives the value from address.

?      (address --)
    Prints the value from address to the terminal.

c!     (char addr --)
    Stores a single character at the specified memory
    address.

c@     (addr -- char)
    Fetches a single character from the specified memory
    address and places it on the stack.

create (--)
    Creates an array named by the first string of
    characters following the create word.

,      (n --)
    Takes the top two values from the stack and stores the
    second value as part of the array in the address of
    the first value.

allot  (n --)
    Allocates n cells of data space. Used after CREATE to
    allocate memory for arrays or data structures.

here   ( -- addr)
    Returns the address of the next available data space
    location.

cells  (n1 -- n2)
    Converts a count to an address offset by multiplying
    by the cell size.

cell+  (addr1 -- addr2)
    Adds the size of one cell to an address, advancing it
    to the next cell boundary.

+!     (n addr --)

```

```

        Adds n to the value stored at the given address.

count    (c-addr1 -- c-addr2 u)
        Converts a counted string (length byte followed by
        characters) to an address and length suitable for TYPE.

b1       ( -- char)
        Pushes the ASCII value for space character (32) onto
        the stack.

2@       (addr -- x1 x2)
        Fetches two consecutive cells from memory at the given
        address.

2!       (x1 x2 addr --)
        Stores two consecutive values to memory at the given
        address.

fill     (addr u char --)
        Fills u bytes of memory starting at addr with the
        specified character value.

move     (addr1 addr2 u --)
        Copies u address units from addr1 to addr2. Handles
        overlapping memory regions correctly.

erase    (addr u --)
        Fills u address units with zeros, effectively clearing
        the memory region.

allocate (u -- a-addr ior)
        Allocates u cells of contiguous data space. Returns the
        start address and an I/O result code (0 = success, -1 =
        failure). Reuses previously freed blocks when possible.

free     (a-addr -- ior)
        Releases previously allocated memory starting at addr.
        Returns 0 on success. Adjacent freed blocks are merged
        to reduce fragmentation.

resize   (a-addr u -- a-addr2 ior)
        Changes the size of an allocation. If the new size fits
        within the existing block, returns the same address.
        Otherwise allocates a new block, copies existing data,
        and frees the old block.

c,       (char --)
        Reserves one character of data space and stores char
        in it.

char+    (c-addr1 -- c-addr2)
        Adds the size of one character to the address.

chars    (n1 -- n2)

```

```

Returns the size in address units of n characters.
In this system, 1 char = 1 unit.

align    ( -- )
Aligns the data-space pointer to a cell boundary.

aligned  (addr -- a-addr)
Returns the first aligned address greater than or
equal to addr.

```

4.1.15 Terminal Operators

Terminal Operators

```

cr        (--)
Newline added to terminal.

space     (--)
Adds a single space to terminal.

spaces    (n --)
Takes a value from the stack and adds that number
of spaces to the terminal.

emit      (n --)
Takes a value from the stack and emits its ASCII
code.

(         (--)
Starts inline comment. Everything between ( and )
will be ignored. Can appear anywhere on a line.

)         (--)
Ends inline comment.

\textbackslash      (--)
Line comment. Everything after \textbackslash{} to
the end of the line is ignored. Supported in .fs
files. Example: \textbackslash{} this is a comment

.s        (--)
Show stack on terminal.

.rs       (--)
Displays the return stack on the terminal. Henceforth
extension --- Forth-2012 only specifies \texttt{.s}
for the data stack.

clear     (i*x --)
Empties the data stack, return stack, and terminal

```

<code>just</code>	screen. Henceforth extension --- non-standard. For the screen use <code>\texttt{page}</code>; for stacks alone use <code>\texttt{abort}</code>.
<code>bye</code>	(--) Clears everything, resets to default settings.
<code>."</code>	(--) Start print. Everything between quotes is printed.
<code>"</code>	(--) Ends print.
<code>s"</code>	(-- addr u) Creates a string literal. Returns the address and length of the string on the stack.
<code>type</code>	(addr u --) Takes an address and length from the stack and displays the string at that address to the terminal.
<code>page</code>	(--) Clears the terminal screen (Forth-2012 6.2.2030). In Henceforth's append-only buffer this empties every prior entry so the next emission starts at the top. Does not affect the data, return, or data stack.
<code>ms</code>	(u --) Wait at least u milliseconds before the next loop iteration (Forth-2012 FACILITY 10.6.2.1905). The request is staged on <code>\texttt{pendingSleepMs}</code> and drained by the surrounding async loop driver (<code>\texttt{do}</code>)/(<code>\texttt{loop}</code>), <code>\texttt{?do}</code>)/(<code>\texttt{loop}</code>)
<code>},</code>	<code>\texttt{begin}</code>)/(<code>\texttt{until}</code>), <code>\texttt{begin}</code>)/(<code>\texttt{while}</code>)/(<code>\texttt{repeat}</code>), <code>\texttt{begin}</code>)/(<code>\texttt{again}</code>). Use it to pace animation and screen updates.
<code>char</code>	(-- char) Parses the next space-delimited word and returns the ASCII value of its first character.
<code>[char]</code>	(-- n) Compile-time version of CHAR. Compiles the character value into the current definition.
<code>word</code>	(char -- c-addr) Parses the input stream until the delimiter character is found and returns a counted string address.
<code>parse</code>	(char -- c-addr u)

```

    Parses the input stream until the delimiter
    character is found and returns address and length.

key      ( -- n)
    Waits for a single keypress and pushes its ASCII
    value onto the stack. Blocks execution until a key
    is pressed. Works with both hardware and software
    keyboards.

?terminal ( -- flag)
    Returns -1 if the keyboard buffer has input or a
    terminal interrupt has been requested (break key
    pressed), 0 otherwise. The Forth-2012 standard name
    is \texttt{ekey?} (FACILITY 10.6.2.1306); both
    spellings dispatch to the same handler. \texttt{?
terminal}
    is the original FIG-FORTH name.

accept   (c-addr n1 -- n2)
    Receives up to n1 characters from the input source
    and stores them at the buffer address c-addr.
    Returns n2, the actual number of characters
    received.

sessionInput (--)
    Displays session input.

dictionary (--)
    Shows the user's defined words, constants, and
    variables. Henceforth extension. For all words
    (built-in plus user-defined) use \texttt{words} or
    \texttt{vlist}.

vlist     (--)
    Displays a list of every built-in word Henceforth
    offers. The Forth-2012 standard name is
    \texttt{words} (TOOLS 15.6.1.2465); both spellings
    dispatch to the same handler.

forth     (--)
    Resets vocabulary to standard built-in words,
    removing all user definitions.

c"        ( -- c-addr)
    Creates a counted string literal. Returns the
    address of a counted string (length byte followed
    by characters).

abort     (--)
    Clears all stacks and resets the interpreter state.

abort"    (flag --)
    If the flag is non-zero, displays the message and
    ABORTs. Otherwise discards the message and

```

```

        continues.
        Usage: 0= abort" value must not be zero"

quit      (--)
Clears the return stack and enters interpretation
state.

source    ( -- c-addr u)
Returns the address and length of the current
input buffer.

environment? (c-addr u -- false | i*x true)
Queries the system for an environmental parameter.
Returns false if unknown, or the value and true
if known.

```

4.1.16 Other Words

Other Words

```

date&time (-- second minute hour day month year)
Adds the device's current time to the stack.

pay      (--)
Presents pay sheet, where you can send bitcoin.

.fs      (--)
Filename followed by .fs extension will load that
file's contents to Henceforth.

startup.fs
A special file that runs automatically when
Henceforth launches. Created as a blank template
on first launch. Add your custom word definitions,
aliases, and INCLUDE calls here so they are
available every session.

```

4.1.17 Data Conversion

Henceforth has two stacks: the integer stack (main) and the data stack (for raw bytes, used by Bitcoin Script operations). These words bridge between them.

Data Conversion

```

hex2data  ( -- )
Converts the following hex string to bytes and
pushes them onto the data stack.
Usage: hex2data 48656c6c6f

```

```

data2hex    ( -- )
            Converts the top data stack item to a hex string
            and displays it on the terminal.

.ds         ( -- )
            Displays the contents of the data stack.

>data      ( -- )
            Converts the following token to raw data bytes and
            pushes them onto the data stack.

>addr      (n -- )
            Marks the top-of-stack integer value as a Bitcoin
            address string for transaction building.

```

4.1.18 String Operations

String Operations

```

cmove      (c-addr1 c-addr2 u -- )
            Copies u characters from addr1 to addr2, proceeding
            low address to high (safe when addr2 > addr1).

cmove>     (c-addr1 c-addr2 u -- )
            Copies u characters from addr1 to addr2, proceeding
            high address to low (safe for overlapping regions
            when addr2 < addr1).

/string    (c-addr1 u1 n -- c-addr2 u2)
            Adjusts a string address and length by n characters.
            Advances the address by n and reduces the length by
            n.

search     (c-addr1 u1 c-addr2 u2 -- c-addr3 u3 flag)
            Searches for string2 within string1. If found,
            returns the match address, remaining length, and
            true. If not found, returns the original string and
            false.

blank     (c-addr u -- )
            Fills u characters of memory starting at addr with
            spaces (BL, ASCII 32).

```

4.1.19 Networking Operations

Networking Operations

```

wocbitcoinprice      ( -- n)
                     Fetches the bitcoin price in USD and
                     adds it to the stack in pennies.

woccirculatingsupply  (--)
                     Fetches the circulating supply of
                     bitcoin.

wocblockchaininfo     (--)
                     Fetches latest general block info from
                     WhatsOnChain and prints to terminal.

wocaddressinfo        (--)
                     Takes an address and displays its
                     information to the terminal.

wocgetbalance         (--)
                     Takes an address and displays its
                     balance information to the terminal.

wocgethistory         (--)
                     Takes an address and displays its
                     history information to the terminal.

wocgetblockbyheight   (n--)
                     Takes a block height from the stack and
                     searches WhatsOnChain for info on that
                     block.

```

4.1.20 Transaction Builder

The transaction builder words allow programmatic construction of Bitcoin transactions directly from the FORTH terminal. Build a transaction step by step, then broadcast it.

Transaction Builder

```

tx-new              ( -- )
                   Initialises a new transaction builder. Clears
                   any previous transaction state.

tx-set-fee          (n -- )
                   Sets the fee rate in satoshis per kilobyte for
                   the current transaction.
                   Usage: 500 tx-set-fee

tx-add-output       (n -- )
                   Adds a P2PKH output to the transaction. Expects

```

```

the amount in satoshis on the stack and the
destination address as the next word.
Usage: 1000 tx-add-output 1A1zP1...

tx-add-data      ( -- )
Adds an OP_RETURN data output to the current
transaction.

tx-preview-toggle ( -- )
Toggles preview mode. When ON, TX-BROADCAST shows
the transaction without sending it; when OFF,
TX-BROADCAST broadcasts. The new state is
reported in the terminal.

tx-show          ( -- )
Displays the current transaction being built
(inputs, outputs, fee).

tx-clear         ( -- )
Clears the transaction builder, discarding all
inputs and outputs.

tx-broadcast     ( -- )
Builds, signs, and broadcasts the current
transaction to the BSV network via ARC.

send             ( amount c-addr u -- )
Standard payment in a single word. Pops the
destination string from the data stack (placed
there by S") and the amount from the integer
stack. The string holds one address (single
recipient) or N space-separated addresses
(equal-split with the remainder going to the
first recipient). Validates the inputs, then
presents PayView with the amount + address
pre-filled. The user long-presses to confirm;
Face ID gates the actual broadcast via ARC.
Terminal output on success is a single line:
"sent TXID: <id>".
Usage: 1000 s" 1A1zP1..." send

send-many        ( amount1 ... amountN c-addr u -- )
Multi-recipient payment with per-recipient
amounts. Pops the address string first to
derive N (the recipient count) from the
space-separated address list, then pops N
amounts. Pairs amount[i] with address[i]
in left-to-right order. Validates every
payee, then presents MultiPaySheet with a
per-recipient grid so the user reviews the
output set before Face ID. On confirm, builds
one transaction with N P2PKH outputs and
broadcasts via ARC. Atomic --- any validation
failure (zero amount, invalid address,

```

```
insufficient funds) rejects the whole
transaction without partial broadcast.
Usage: 1000 5000 250 s" 1A 1B 1C" send-many
```

Transaction Builder Example: Send 1000 satoshis to an address with a custom fee rate using the step-by-step builder:

```
tx-new
250 tx-set-fee
." 1ExampleAddress..." 1000 tx-add-output
tx-show
tx-broadcast
```

Standard Payment Example: The send word wraps the entire PayView payment flow into a single command. It uses the default wallet (marked with a star on the wallet card):

\ Single recipient:

```
1000 s" 1A1zP1eP5QGefi2DMPTfTL5SLmv7DivfNa" send
```

\ Multiple recipients (equal-split, 2500 sats each):

```
5000 s" 1A1zP1... 1BvBMS..." send
```

Addresses ride the data stack via S" (FORTH-2012's string literal). S" pushes the address bytes plus their length pair (c-addr u) onto the stack; send pops them after popping the amount. Multiple addresses can be space-separated within a single S" string for an equal-split transaction.

Multi-Recipient Payment with Per-Recipient Amounts: When recipients should receive different amounts, use send-many. The recipient count is derived from the address string (one count source of truth), and the function pops exactly that many amounts from the integer stack:

\ Three recipients with unequal amounts:

```
1000 5000 250 s" 1A1zP1... 1BvBMS... 1FfmbHfn..." send-many
```

The amounts pair with the addresses by position: amount[i] goes to address[i] reading left-to-right. The function rejects atomically – if any amount is zero, any address is invalid, or the total exceeds the wallet balance, the whole transaction is aborted before the biometric prompt fires.

Reading rule for both send and send-many: amounts come first, the recipient string comes last. This places the address string at the top of the stack so send-many can read it first and infer N before consuming the amount block – no explicit count parameter is needed.

Standard Transaction Script

Every installation includes a standard-transaction.fs file in the Files tab. This is a Bitcoin Script file that defines the OP_RETURN output attached to your payments. It is automatically loaded each time you open the Pay view.
(Standard Transaction Script)

```
SCRIPT-BEGIN
OP_FALSE OP_RETURN
." Hello, you are welcome." >data data>script
```

SCRIPT-END

How it works:

1. SCRIPT-BEGIN activates script recording mode
2. OP_FALSE OP_RETURN emits the opcodes for a data-carrying output
3. ." places the message on the terminal output
4. >data converts it to raw bytes on the data stack
5. data>script emits those bytes as PUSHDATA into the script buffer
6. SCRIPT-END finalises the compiled script

To customise your standard transaction, edit the message string in the file. The Pay view re-reads the file from disk each time it opens, so edits take effect immediately. The file also appears in the Script tab of the script picker if you need to switch between scripts.

Note on comments: Script files use () parenthetical comments rather than \ line comments. The script picker flattens newlines when compiling, which causes \ comments to consume the rest of the file.

4.1.21 Bitcoin Cryptography

Bitcoin Cryptography

```
sign-msg      ( -- )
               Signs a message with the current wallet key using
               Bitcoin Signed Message (BSM).
               Usage: sign-msg <message>

verify-msg    ( -- flag)
               Verifies a BSM signature against an address. Pushes
               true (-1) or false (0) to stack.
               Usage: verify-msg <address> <signature> <message>

encrypt-msg   ( -- )
               Encrypts a message for a recipient using BRC-2
               Electrum ECIES (ECDH + AES-CBC + HMAC-SHA256).
               Wire-compatible with @bsv/sdk EncryptedMessage.
               Usage: encrypt-msg <recipientPubKeyHex> <message>

decrypt-msg   ( -- )
               Decrypts a BRC-2 ECIES-encrypted message using the
               current wallet key. The plaintext is displayed.
               Usage: decrypt-msg <ciphertextHex>
```


4.1.22 BAP Identity

BAP (Bitcoin Attestation Protocol) provides a decentralised identity system built on Bitcoin. Identity keys are derived using Type42 (BRC-42) key derivation from the wallet's master key.

BAP Identity Operations

```

bap-id      ( -- )
             Shows the BAP identity key (ID) and signing address
             for the current wallet.

bap-sign    ( -- )
             Signs a message with the BAP identity key (Type42
             derived). Usage: bap-sign <message>

bap-verify  ( -- flag)
             Verifies a BAP-signed message. Pushes true (-1) or
             false (0) to the stack.
             Usage: bap-verify <address> <signature> <message>

bap-register ( -- )
             Builds a BAP ID registration transaction
             (OP_RETURN with BAP + AIP attestation).

```

AIP signatures are over raw message bytes, not hex. bap-sign and the AIP attestation inside bap-register apply the Bitcoin Signed Message wire format (prefix "\x18Bitcoin Signed Message:\n" + varint length + payload) directly to the raw payload bytes. Earlier versions signed the ASCII hex rendering of those bytes, which decoded consistently only within Henceforth itself. Signatures produced by current builds verify against any BAP / AIP implementation that follows the standard (including @bsv/sdk); signatures produced by older Henceforth builds will not.

4.1.23 Script Recording

Script recording is a macro assembler for Bitcoin Script. When recording is active, op_* words emit their opcodes into a script buffer rather than executing. Standard FORTH control flow still runs normally, allowing programmatic script construction.

Script Recording Operations

```

script-begin ( -- )
             Start recording Bitcoin Script. op_* words emit
             opcodes to the script buffer. FORTH control flow
             still runs normally.

script-end   ( -- )
             Stop recording and finalise the script. Displays
             the compiled script hex.

script-show  ( -- )

```

```

                                Display the current script buffer contents as hex.

script-clear  ( -- )
              Discard the current script buffer and stop
              recording.

script-use    ( -- )
              Set the recorded script as the selected transaction
              script (for building transactions).

script-save   ( -- )
              Save the current script with a name.
              Usage: script-save <name>

script-load   ( -- )
              Load a previously saved script by name.
              Usage: script-load <name>

script-list   ( -- )
              List all saved scripts.

```

Raw bytes require a 0x prefix during recording. When script recording is active, a bare hex-looking token such as `ff` is not emitted as the byte `0xff` – it is parsed according to the current BASE (255 in DECIMAL, 255 in HEX) and pushed to the integer stack. To emit raw opcode bytes into the script buffer, use an explicit `0x`-prefixed literal (e.g. `0xdeadbeef`). This eliminates the earlier base-dependent ambiguity where `ff` silently meant different things in DECIMAL versus HEX mode.

4.1.24 Script Bridge Words

The bridge words connect FORTH's stacks to the script recording buffer, enabling dynamic script construction with computed values, strings, and file data.

Script Bridge Operations

```

>script      (n -- )
              Takes an integer from the stack and emits it as a
              Bitcoin Script number to the script buffer.

data>script   ( -- )
              Takes the top item from the data stack and emits
              it as PUSHDATA to the script buffer. Use after
              crypto operations to inject computed hashes.

text>script   ( -- )
              Converts the following token to UTF-8 bytes and
              emits as PUSHDATA to the script buffer.
              Usage: text>script image/jpeg

file>script   ( -- )

```

```

Reads a file's raw contents and emits them as
PUSHDATA to the script buffer. For uploading
images, videos, or data on-chain.
Usage: file>script photo.jpg

```

4.1.25 Script Helper Words

Pre-built script templates for common Bitcoin transaction patterns.

Script Helpers

```

make-p2pkh-script      ( -- )
                        Creates a standard P2PKH (Pay-to-Public-
                        Key-Hash) locking script from an address.

make-opreturn-script   ( -- )
                        Creates an OP_RETURN output script from
                        data on the stack.

make-2of3-multisig     ( -- )
                        Creates a 2-of-3 multisig script from
                        three public keys on the stack.

script-pushdata        ( -- )
                        Pushes raw data bytes to the script
                        recording buffer using OP_PUSHDATA.

```

Example: Upload an image to the blockchain using the B:// protocol:

```

script-begin
  op_false op_return
  text>script 19HxigV4QyBv3tHpQVcUEQyq1pzZVdoAut
  file>script photo.jpg
  text>script image/jpeg
  text>script binary
  text>script my_photo
script-end
script-use
pay

```

Example: Build a hash-locked script with a computed HASH160:

```

script-begin
  op_dup op_hash160
  " secret" op_sha256 op_hash160
  data>script
  op_equalverify op_checksig
script-end

```

Here data>script bridges the data stack (where the hash was computed) into the script buffer – something impossible without the bridge words.

Example: Use a FORTH loop to generate repetitive script patterns:

```
script-begin
  10 0 do op_1 op_add loop
script-end
```

This emits 10 copies of OP_1 OP_ADD into the script. FORTH's full control flow (loops, variables, conditions) runs normally during recording – only op_* words emit to the buffer.

Example: Build a simple P2PKH locking script:

```
script-begin op_dup op_hash160 <pubKeyHash> op_equalverify op_checksigt
script-end
```

Scripts saved with script-save appear in the Files tab with an orange icon and can be selected as transaction scripts via script-use or the Script pop-up.

4.1.26 OPCODES

Push Data OP Codes

```

op_0      ( -- 0)      Zero is pushed on to the stack.
op_1      ( -- 1)      One is pushed on to the stack.
op_2      ( -- 2)      Two is pushed on to the stack.
op_3      ( -- 3)      Three is pushed on to the stack.
op_4      ( -- 4)      Four is pushed on to the stack.
op_5      ( -- 5)      Five is pushed on to the stack.
op_6      ( -- 6)      Six is pushed on to the stack.
op_7      ( -- 7)      Seven is pushed on to the stack.
op_8      ( -- 8)      Eight is pushed on to the stack.
op_9      ( -- 9)      Nine is pushed on to the stack.
op_10     ( -- 10)     Ten is pushed on to the stack.
op_11     ( -- 11)     Eleven is pushed on to the stack.
op_12     ( -- 12)     Twelve is pushed on to the stack.
op_13     ( -- 13)     Thirteen is pushed on to the stack.
op_14     ( -- 14)     Fourteen is pushed on to the stack.
op_15     ( -- 15)     Fifteen is pushed on to the stack.
op_16     ( -- 16)     Sixteen is pushed on to the stack.

op_false  ( -- 0)      Zero (false flag) pushed to stack.

op_pushdata1  (--)      The byte after will contain how many
                        bytes are to be pushed on to the stack.

op_pushdata2  (--)      The next two bytes will contain how many
                        bytes will be pushed on to the stack.

op_pushdata4  (--)      The next four bytes will contain how many
                        bytes will be pushed on to the stack.

op_1negate  ( -- -1)    Minus one pushed on to the stack.

```

Control Flow OP Codes

```

op_nop      (--)      Does nothing.

op_ver      ( -- version)
Pushes the transaction version onto the stack.
Returns 1 (legacy) or 2 (Chronicle, post block
943,816).

op_if       (f--)      Executes code depending on the expression's flag.

op_notif    (n--)      Executes code depending on the expression's flag.

op_verif    ( threshold -- flag)
Pushes TRUE if tx version >= threshold, FALSE

```

```

        otherwise. Chronicle upgrade.

op_vernotif ( threshold -- flag)
Pushes TRUE if tx version < threshold, FALSE
otherwise. Chronicle upgrade.

op_else      (--)
Executes if the preceding OP_IF, OP_NOTIF, or
OP_ELSE were not executed.

op_endif     (--)
Ends the if/else statement.

op_verify    (f--)
Marks the transaction as INVALID if the flag is
false.

op_return    (--)
Ends script. Often used to add data to the
blockchain.

```

Stack Operator OP Codes

```

op_toaltstack (n--)
Takes the top value from the stack and pushes
it to the alt stack.

op_fromaltstack (--n)
Takes the top value from the alt stack and
pushes it to the stack.

op_2drop      (n n1--)
Discards the top 2 elements from the stack.

op_2dup        (n n1 -- n n1 n n1)
Duplicates the top two values from the stack
adding back both original and copy.

op_3dup        (n n1 n2 -- n n1 n2 n n1 n2)
Duplicates the top three values from the stack
adding back both original and copy.

op_2over       (n n1 n2 n3 -- n n1 n2 n3 n n1)
Copies the fourth and third items in the stack
over the first and second.

op_2rot        (n n1 n2 n3 n4 n5 -- n2 n3 n4 n5 n n1)
Copies the fifth and sixth items in the stack
over the first and second.

op_2swap       (n n1 n2 n3 -- n2 n3 n n1)
Takes four values from the stack and swaps
their order as pairs.

```

<code>op_ifdup</code>	<code>(n -- 0 n n)</code> Duplicates the top value from the stack if it is NOT zero. Leaves 0 unchanged.
<code>op_depth</code>	<code>(--n)</code> Adds the number of items on the stack to the stack.
<code>op_drop</code>	<code>(n--)</code> Discards the top item from the stack.
<code>op_dup</code>	<code>(n -- n n)</code> Duplicates the top item from the stack.
<code>op_nip</code>	<code>(n n1 -- n1)</code> Discards the second item in the stack.
<code>op_over</code>	<code>(n n1 -- n n1 n)</code> Copies the second item in the stack over the top.
<code>op_pick</code>	<code>(xu ... x0 u -- xu ... x0 xu)</code> Copies the u-th item on the stack to the top.
<code>op_roll</code>	<code>(xu xu-1 ... x0 u -- xu-1 ... x0 xu)</code> Moves the u-th item on the stack to the top, shifting items above it down.
<code>op_rot</code>	<code>(n n1 n2 -- n1 n2 n)</code> The top three items on the stack are rotated left, with the third item going to the top.
<code>op_swap</code>	<code>(n n1 -- n1 n)</code> The top two items on the stack's order is reversed.
<code>op_tuck</code>	<code>(n n1 -- n1 n n1)</code> The top item on the stack is copied in front of the second item.

Size & Separator OP Codes

<code>op_size</code>	<code>(x -- x n)</code> Pushes the byte length of the top stack element without consuming it.
<code>op_codeseparator</code>	<code>(--)</code> Marks the beginning of signature-checked data. All signature checks only use data after the most recent <code>OP_CODESEPARATOR</code> .
<code>op_true</code>	<code>(-- 1)</code>

Pushes 1 onto the stack. Alias for OP_1.

Splice Operator OP Codes

op_cat	(--) Concatenates the two strings provided.
op_split	(n n1--) Splits byte sequence n at n1.
op_num2bin	(n n1--) Converts value n into a byte sequence of length n1.
op_bin2num	(n--) Converts byte sequence n into a numerical value.
op_substr	(start length --) data: (data -- substring) Extracts a substring by start index and length. Chronicle upgrade (0xb3).
op_left	(n --) data: (data -- left) Extracts the leftmost N bytes. Chronicle upgrade (0xb4).
op_right	(n --) data: (data -- right) Extracts the rightmost N bytes. Chronicle upgrade (0xb5).

Bitwise Operator OP Codes

op_invert	(n -- n) Flips all the bits in the input.
op_and	(n1 n2 -- AND) Logical AND performed and the result added to the stack.
op_or	(n1 n2 -- OR) Logical OR performed and the result added to the stack.
op_xor	(n1 n2 -- XOR) Logical XOR performed and the result added to the stack.
op_equal	(n n1 -- f) Returns a flag depending on if n1 and n2 are equal. 1 if true, 0 if false.
op_equalverify	(n1 n2 -- f) OP_EQUAL then OP_VERIFY.


```

op_reserved1    (--)
                Renders transaction invalid unless in
                unexecuted OP_IF statement.

op_reserved2    (--)
                Renders transaction invalid unless in
                unexecuted OP_IF statement.

```

Arithmetic Operator OP Codes

```

op_1add          (n -- n+1)
                1 is added to the top value on the stack.

op_1sub          (n -- n-1)
                1 is subtracted from the top value.

op_2mul          (n -- n*2)
                The top value on the stack is doubled.

op_2div          (n -- n/2)
                The top value on the stack is halved.

op_negate        (n -- -n)
                The top value's sign is flipped.

op_abs           (n -- |n|)
                The absolute value of the top item on
                the stack is returned.

op_not           (n -- f)
                Logical NOT. Returns 1 if the input is 0,
                otherwise returns 0.

op_0notequal     (n -- f)
                Returns true if the value is not zero,
                else false.

op_add           (n n1 -- n3)
                Top two items from the stack are summed
                and the value returned.

op_sub           (n n1 -- n3)
                The top value from the stack is
                subtracted from the second value.

op_mul           (n n1 -- n3)
                The top value is multiplied by the
                second value in the stack.

op_div           (n n1 -- n3)
                The second value in the stack is divided
                by the top value.

```

<code>op_mod</code>	(n n1 -- n3) The second value is divided by the top value and the remainder returned.
<code>op_lshift</code>	(n n1 -- n3) The second value is logical left shifted by the top value.
<code>op_rshift</code>	(n n1 -- n3) The second value is logical right shifted by the top value.
<code>op_lshiftnum</code>	(n shift -- result) Numeric left shift preserving sign.
<code>Distinct</code>	from <code>op_lshift</code> which is bitwise on bytes. Chronicle upgrade (0xb6).
<code>op_rshiftnum</code>	(n shift -- result) Numeric right shift preserving sign.
<code>Distinct</code>	from <code>op_rshift</code> which is bitwise on bytes. Chronicle upgrade (0xb7).
<code>op_booland</code>	(n n1 -- f) True flag returned if both n and n1 are non-zero, else false.
<code>op_boolor</code>	(n n1 -- f) True flag returned if either n or n1 is not 0, else false.
<code>op_numequal</code>	(n n1 -- f) True if n is equivalent to n1, else false.
<code>op_numequalverify</code>	(n n1 -- f) OP_NUMEQUAL then OP_VERIFY.
<code>op_numnotequal</code>	(n n1 -- f) True if n is NOT equal to n1, else false.
<code>op_lessthan</code>	(n n1 -- f) True if n is less than n1, else false.
<code>op_greaterthan</code>	(n n1 -- f) True if n is greater than n1, else false.
<code>op_lessthanorequal</code>	(n n1 -- f) True if n is less than or equal to n1, else false.

```

op_greaterthanequal (n n1 -- f)
                    True if n is greater than or equal to
                    n1, else false.

op_min              (n n1 -- n)
                    The top two values from the stack are
                    taken and the smaller returned.

op_max              (n n1 -- n)
                    The top two values from the stack are
                    taken and the larger returned.

op_within           (n n1 n2 -- f)
                    True is returned if n is in between n1
                    and n2.

```

Crypto Operator OP Codes

```

op_ripemd160        (--)
op_sha1              (--)
op_sha256            (--)
op_hash160           (--)
op_hash256           (--)
op_checksigs         (--)
op_checksigsverify   (--)
op_checkmultisig     (--)
op_checkmultisigverify (--)

```

Lock Time Operator OP Codes

```

op_nop2              (--)
op_nop3              (--)
op_pubkeyhash        (--)
op_pubkey            (--)
op_invalidopcode     (--)

```

Reserved OP Codes

```

op_nop1              (--)
op_nop4              (--)
op_nop5              (--)
op_nop6              (--)
op_nop9              (--)
op_nop10             (--)

```

Chronicle Upgrade (Block 943,816): NOP4-8 (0xb3-0xb7) were repurposed as op_substr, op_left, op_right, op_lshiftnum, and op_rshiftnum. The transaction version (op_ver) auto-switches from 1 to 2 at the activation block.

Henceforth includes a full Bitcoin SV (BSV) wallet, enabling users to create wallets, receive and send transactions, and interact with the blockchain – all from the same app that runs FORTH programs.

5.1 Wallet Architecture

The wallet is built on a hierarchical deterministic (HD) key structure, meaning a single seed phrase generates an unlimited number of addresses.

- **Seed Phrase:** A 12-word BIP-39 mnemonic is generated when creating a new wallet. This seed phrase is the master backup – from it, every key can be regenerated.
- **Key Derivation:** Two derivation methods are supported:
 - **Type42 (BRC-42)** – the default for new wallets. Uses elliptic curve key tweaking (private key addition, public key multiplication) for more flexible derivation paths.
 - **BIP-44** – the legacy standard. Retained for restoring wallets created by other software. Uses the standard path `m/44'/236'/0'/0/n`.
- **Address Rotation:** After each transaction, a new receiving address is derived automatically. This improves privacy by avoiding address reuse.

Security: Private keys and seed phrases are stored exclusively in the iOS Keychain, protected by the device's Secure Enclave. They never leave the device and are never transmitted over the network.

5.1.1 Address Discovery

The wallet discovers addresses with funds using a shared Type42 scanner (`scanType42-Addresses`). The scanner is derivationType-independent – it always tries Type42 first if the master key exists in Keychain, regardless of what derivationType says on the wallet card. This prevents funds from becoming invisible if the derivation type metadata is wrong.

- **Dynamic scan range:** Scans at least 20 addresses (gap limit) past the last address with activity, with a minimum floor of 50 addresses.

- **Receive and change chains:** Scans both 1-wallet-`{N}` (receive) and 0-change-`{N}` (change) invoice numbers.
- **BIP-44 fallback:** After Type42, scans standard BIP-44 paths. A wallet can have funds on both derivation paths.
- **Auto-repair:** If Type42 addresses are discovered but derivationType is wrong, the scanner automatically corrects it and persists the fix.

5.2 Wallet Cards

Each wallet is represented by a Wallet Card in the app interface. A card stores:

- **Wallet title** – a user-chosen name
- **Main address** – the primary receiving address
- **Derived addresses** – additional addresses generated through key rotation
- **Balance** – confirmed and unconfirmed satoshis, reconciled from the UTXO set
- **Derivation type** – Type42 or BIP-44

Multiple wallets can be created and managed simultaneously. The wallet card interface supports creating, renaming, and deleting wallets, with biometric (Face ID / Touch ID) authentication required to access sensitive details.

Default Wallet

One wallet can be marked as the default wallet, indicated by a star on the wallet card. The default wallet is used by the terminal send word and other non-UI operations. If no default is set, the first wallet is used.

To change the default wallet, open the wallet details view and tap **Set as Default Wallet**. The setting persists across app launches.

5.3 Transactions

5.3.1 Receiving

To receive BSV, share your wallet's receiving address or scan its QR code. The wallet monitors for incoming transactions using:

1. **JungleBus REST polling** – polls every 30 seconds for new transactions via the GET `/v1/address/get/{address}` endpoint. When a new transaction ID is detected, the wallet triggers an automatic refresh.

2. Periodic sync – full balance and UTXO refresh as a safety net

When a new transaction is detected, the wallet automatically refreshes the balance, UTXOs, and transaction history.

5.3.2 Notifications

The wallet uses a UTXO-based deposit detection system. Instead of comparing balances (which can fluctuate mid-sync), it tracks known UTXO outpoints (txHash:txPos) per wallet in UserDefaults. Only genuinely new outpoints trigger a notification – the system is immune to confirmation state changes and mid-sync transient balances.

When a wallet is first seen, existing outpoints are seeded silently (no “received entire balance” notification on first install).

5.3.3 Sending

Transactions are built locally on the device:

1. **UTXO Selection:** The wallet selects unspent transaction outputs to fund the payment, avoiding ordinal-protected UTXOs.
2. **Fee Calculation:** Fees are calculated using the current rate from the preferred miner (GorillaPool or TAAL) via ARC policy endpoints.
3. **Change Output:** Any excess is returned to a fresh change address derived from the wallet.
4. **Signing:** Each input is signed with the correct private key for its address (Type42 or BIP-44 derived).
5. **Anti-Fee-Sniping:** The nLockTime field is set to the current block height, preventing miners from re-mining old transactions for higher fees.
6. **Broadcasting:** The signed transaction is submitted via ARC with automatic failover between GorillaPool and TAAL.

The pay word in the FORTH terminal opens the transaction builder. The pay view has three tabs for selecting what to broadcast:

- **OP_RETURN** – write a text message to embed on-chain
- **Script** – select a saved script or a .fs script file
- **Upload** – pick a photo, video, or file from the device and upload it on-chain via the B:// protocol

Terminal Send Words

In addition to pay, two terminal words compose payments directly from the stack:

- **send** – (amount c-addr u -). Example: 1000 s" 1A..." send sends 1000 satoshis to the given address. Space-separated addresses in the string equally split the amount across all recipients.
- **send-many** – (amount1 ... amountN c-addr u -). Example: 1000 5000 250 s" 1A 1B 1C" send-many sends 1000, 5000, and 250 satoshis to three recipients in one transaction. Per-recipient amounts; the count is derived from the address string, so no explicit count parameter is needed.

Both words accept P2PKH addresses only – paymail aliases must be resolved through the single-recipient send flow first. send-many surfaces a specific error message when it sees an @ character so the user knows why.

Mandatory pre-signing review. Neither word broadcasts directly. send pre-fills the existing pay view; send-many presents a new **MultiPaySheet** with a scrollable grid showing each (recipient, amount) row plus the total. The user sees the exact output set before the long-press triggers signature. This is non-negotiable: a malicious script that pushes different values onto the stack between the user's intent and the signing step cannot bypass the visual review. The single canonical confirmation line sent TXID: <id> appears on the terminal after broadcast success; no pre-sheet echo clutters the output.

Fragmentation-Aware Selection

UTXO selection switches to a fragmentation-aware policy when the wallet has more than 100 UTXOs OR when the average UTXO value is below 5000 satoshis with more than 40 UTXOs. In this mode:

- The dust-input cap rises from 10 to 50, draining more of the dust pile per send.
- Regular UTXO sort flips from largest-first to smallest-first, tilting the regular sweep toward consolidation.
- Smart-change splitting (which normally creates extra change outputs for large change) is disabled – the residual coalesces into a single primary change output instead of re-fragmenting.
- A transaction-size ceiling refuses to assemble a transaction larger than maxStandardTxSize (100KB) before biometric prompts, surfacing a user-actionable "consolidate across multiple smaller sends first" message rather than letting ARC reject after Face ID.

The user initiates an ordinary send; the wallet consolidates as a side effect. No separate "Consolidate" button is needed in the normal flow.

Smart Sync: When a payment is initiated, UTXOs are loaded from the local disk cache first (instant). A network fetch only occurs on genuine first launch when no UTXO file exists. Fee quotes are cached for 5 minutes. A times-table circle animation (cardioid pattern) plays during broadcast. The payment flow trusts local UTXO state – if a UTXO turns out to be already spent, ARC will reject with DOUBLE_SPEND_ATTEMPTED.

After a successful broadcast, the wallet builds a local transaction model from the data it already has (inputs, outputs, addresses, amounts) and inserts it into the transaction history immediately – no network fetch required. The ARC-returned txid is verified against the locally computed txid as cryptographic proof that the network accepted exactly what was built. Spent UTXOs are removed from memory (preventing double-spend on rapid re-send) and change UTXOs are added. Full transaction details from WhatsOnChain overwrite the local entry on the next sync.

Trust Local State: Per the Bitcoin white paper (§2), we built the transaction and signed it with our private keys – we know exactly what it contains. There is no need to ask a third party (WhatsOnChain) what we just sent. ARC confirms the network saw it; the rest we already know.

5.3.4 Paymail

Paymail allows sending BSV to human-readable addresses (e.g., `user@example.com`) instead of raw Bitcoin addresses. The wallet implements:

- **BRC-30 receive-transaction callbacks** – P2P payment destinations resolved via the `.well-known/bsvalias` capability discovery. The payee’s server provides a fresh output script for each payment.
- **Automatic resolution** – when a paymail address is entered in the pay view, the wallet resolves it to a Bitcoin address transparently.

5.3.5 Transaction History

The wallet displays a chronological transaction history with:

- **Direction detection** – incoming (received) vs outgoing (sent), determined by checking whether any inputs belong to the wallet
- **Grouping** – transactions are grouped by: Pending, Today, Yesterday, This Week, This Month, Earlier
- **Search and filter** – filter by amount, date range, or search by transaction ID
- **SPV verification** – transactions can be verified against a locally chain-linked block header store anchored to a hardcoded checkpoint. See the SPV Architecture section below.

5.4 SPV Architecture

The wallet implements Simplified Payment Verification per Section 8 of the Bitcoin white paper: clients trust a locally maintained chain of block headers and verify individual transactions against it using Merkle proofs. The entire SPV trust model rests on the invariants below; violating any of them reopens a trust hole.

SPV trust boundary: every header in the local store is either the hardcoded checkpoint or transitively chain-links back to it via a series of PoW-validated, chain-linked intermediate headers. There is no silent network fallback in the verification path – if Henceforth doesn't have the header locally, it refuses to verify the transaction and reports a pending-sync state instead.

5.4.1 Trust Anchor

The wallet ships with a hardcoded checkpoint in `SPVCheckpoint.mainnet` – a tuple of (height, hash, previousblockhash, merkleroot, version, time, nonce, bits) for a recent mainnet block. This is the only header trusted without chain-linkage proof. The current pinned checkpoint is at a block roughly 500 confirmations below the then-tip, providing orders-of-magnitude safety margin against reorganization.

The checkpoint hash doubles as its own migration version marker: bumping `SPVCheckpoint.mainnet` in source automatically triggers a wipe of every user's local header store on next launch, followed by a fresh re-sync from the new anchor. There is no sidecar file or explicit version field.

5.4.2 Header Store

The local header store is `FORTH.blockHeaders: [Int: WOCGetHeadersModel]`, a dictionary keyed by block height. Every entry must satisfy four invariants:

1. **Non-empty merkleroot** – enforced by `FORTH.isAuthoritativeBlockHeader`. Pre-Phase-1 placeholder rows from the legacy hash-only ledger are dropped on load.
2. **Individual PoW validates** – double-SHA256 of the serialized header must be below the target encoded in the header's bits field.
3. **Chain-linked to parent** – the header's previousblockhash must equal the hash of the header at height - 1 in the store.
4. **Transitively anchored to the checkpoint** – walking backward through parents eventually reaches `SPVCheckpoint.mainnet`.

5.4.3 Validated Tip

`FORTH.validatedTipHeight` is the highest block height whose header transitively chain-links back to the checkpoint via a contiguous run in `blockHeaders`. It initializes to the checkpoint height on first launch and advances only when a new run chain-links continuously from the current tip.

This distinction matters: a header may be structurally present in `blockHeaders` yet not covered by `validatedTipHeight`. That happens when the WebSocket sync streams headers faster than chain validation links them forward – the incoming batch is stored but the validated tip doesn't advance until the gap is filled. SPV verification uses `validatedTipHeight` as the trust upper bound, so unvalidated islands are invisible to proof checks.

validatedTipHeight vs latestBlockHeight: these are different concepts owned by different subsystems. `latestBlockHeight` is the live chain tip (driven by the `wocGetHeaders tip-10` fetch) and is used for `txVersion` activation gates and UI display. `validatedTipHeight` is "highest height I can prove SPV for right now" (driven by the `HeaderSyncService batch-commit` path). Never conflate them; never write one from code that belongs to the other.

5.4.4 Commit Path

`FORTH.commitValidatedHeaderRun(_:)` is the single entry point for adding headers to `blockHeaders` with trust. It requires:

1. The run's first header has a local anchor at `firstHeight - 1` (i.e., the parent is already in the store).
2. The anchor's hash equals the run's first `previousblockhash` (the chain link is structurally correct).
3. The full `[anchor] + run batch` passes `SPVService.validateBlockHeaderChain`, which PoW-validates every header and chain-links consecutive pairs.

Only runs satisfying all three are committed. Rejections log the exact reason so debugging sync gaps is straightforward. The legacy `wocGetHeaders tip-10` fetch is still allowed to place unvalidated headers for display purposes, but those entries are invisible to SPV verification because they fall outside the bounded-lookup range.

5.4.5 Auto-Sync Service

`HeaderSyncService` (an `@MainActor` class conforming to `WebSocketConnectionDelegate`) runs the background sync loop. On every launch, `ContentView.task` calls `getSavedBlockHeaders` (which enforces the checkpoint seed and recomputes the validated tip) and then `HeaderSyncService.shared.resume(forth:)`.

The sync loop:

1. Opens a `WebSocket` to `wss://socket.whatsonchain.com/websocket/history?from=<validated-TipHeight+1>`.
2. Consumes each incoming text frame via `onMessage(connection:text:)` and buffers decoded headers.
3. When the buffer reaches 500 headers, splits into contiguous runs and flushes each via `commitValidatedHeaderRun`.
4. Idle detection via a cancellable `Task.sleep(for: 3s)` armed on every message – when the sleep completes uncancelled, the `WebSocket` disconnects cleanly and the sync transitions to caught up.
5. On no-progress sessions (socket dropped before any headers committed), exponential backoff from 1s to a 60s cap, then retry.

A force resync debug button in `Settings → Bitcoin → Headers` wipes the store back to the checkpoint and restarts sync, behind a confirmation dialog.

5.4.6 Bounded Lookup and Verification

`SPVService.verifyTransaction(txid:blockHeaders:checkpointHeight:validatedTipHeight:)` is the single SPV entry point. It:

1. Fetches the TSC (BRC-74) Merkle proof for the transaction from `WhatsOnChain`.
2. Looks up the containing block header via `findBoundedBlockHeader` – a nonisolated static helper that returns the header only when its height falls in `[checkpointHeight ... validatedTipHeight]`.
3. PoW-validates the local header (defense in depth).
4. Verifies the TSC proof against the local header's merkle root.

If step 2 returns `nil`, verification returns `blockHeaderNotFound` – without fetching the header from `WoC`. The pre-Phase-5 code had a silent network fallback here that fetched the missing header and used it anyway. A single PoW-valid header in isolation is **not SPV**: the attacker can produce any chain they like with valid PoW, and a MITM'd `WoC` response would preserve the format. Removing that fallback is the single most important line of the full-SPV work.

The terminal wrapper `FORTH.verifySPV(txid:)` distinguishes "still syncing" from "genuinely invalid" by checking the error case: when the failure is `blockHeaderNotFound`, it prints " Δ SPV PENDING: header chain still syncing (local tip N)" so the user doesn't mistake a sync gap for fraud.

5.4.7 Checkpoint Maintenance

Bumping the checkpoint is a deliberate operation, not routine. The runbook lives inline in `SPVCheckpoint.swift` but the summary is:

1. Pick a target block at least 500 confirmations below the current chain tip; never within the last 144 blocks.
2. Fetch the header from a primary source (`WhatsOnChain`) and **cross-verify** every field against a second independent source.
3. Update `SPVCheckpoint.mainnet` in source. Commit.
4. Every user's next launch detects the new checkpoint hash, wipes the local store, and auto-sync re-downloads from the new anchor.

Never bump without cross-verification. A compromised or cached response at bump time would silently become the new trust anchor baked into the binary shipped to every user. The second source is non-optional.

5.5 Cold Mode and Air-Gap Bundles

Cold Mode is a per-wallet flag (`WalletCard.coldModeEnabled`) that defers broadcast. When set, a transaction the user has approved with Face ID is signed and stored locally as a pending action rather than submitted to ARC. The user releases it later from the **Pending Broadcasts** view – on the same device or, in the air-gap workflow, after handing off to a watcher iPhone via AirDrop.

5.5.1 Bundle Formats

Three serialisable JSON formats carry data across the air-gap. All three are exchanged via AirDrop, routed by file extension, and validated on import.

- **.hfheaders (HFHeaderBundle)** – a contiguous run of validated block headers anchored to a checkpoint hash. The signer exports headers it has validated to the watcher (or vice versa); the importer hands the run to the same `commitValidatedHeaderRun` path that the live WSS sync uses, so chain-link, proof-of-work, and checkpoint-anchor invariants self-enforce.
- **.hfreceipt (HFReceiptBundle)** – proof that a specific transaction was included in the blockchain. Carries (txid, raw transaction hex, block height, block hash, TSC Merkle proof, containing block header). `SPVService.verifyTransaction(fromBundle:)` validates inclusion against the importer's own local header at the same height with no network call. Inclusion alone proves the transaction exists on chain, not that it pays this wallet. After SPV passes, the importer re-derives output ownership by parsing the raw transaction and refusing the receipt unless at least one output's address resolves to one of the wallet's known derived addresses (across all wallets on the device). Defeats forged receipts for real but unrelated on-chain transactions.
- **.hfaddrpack (HFAddressPack)** – pre-derived receive addresses pushed outward from signer to watcher. Each entry carries the address, derivation scheme (type42 or bip44), and the scheme-specific derivation reference (BRC-43 invoice number or BIP-44 path). The pack is signed by the wallet's m/0/0 BIP32 identity key with a DER ECDSA signature over the canonical pre-signature digest (version || length-prefixed walletTitle || sorted "scheme:derivationKey:address" lines). The watcher's decode verifies the signature against the embedded signer pubkey and refuses tampered packs.

5.5.2 Air-Gap Tools UI

Settings → **Bitcoin** → **Air-Gap Tools** exposes three exporters and a single import button. The importer routes by file extension. Exports go through the system file picker / share sheet so AirDrop, iCloud Drive, and email are all reachable destinations on both iOS and macOS.

v1 .hfreceipt uses raw transaction plus TSC Merkle proof. A v2 schema bump may upgrade to BRC-62 BEEF for full ancestor-script validation. The wire format carries a one-byte version so the v1 reader can refuse a v2 file loudly rather than silently producing garbage.

5.5.3 Watcher-Side Persistence

In v1.0, .hfaddrpack import validates the signature and counts the addresses; persisting the entries into a watch-only monitoring store wired to MempoolMonitor-Service is staged for the v1.0.2 follow-up. The wire format and signature check ship in v1; the loop closure ships next.

5.6 Wallet Data Management

UTXO and transaction persistence is the most security-critical layer of the wallet. The rules below are invariants, not preferences – violating any of them risks losing user funds or transaction history.

- **Never overwrite UTXO files with partial data.** A UTXO file is saved only when all addresses queried successfully. A partial query (network blip, rate limit) leaves the previous snapshot intact.
- **Conservative merge.** The wallet only removes a UTXO when its owning address was queried and the UTXO was not in the response. A UTXO whose address wasn't queried this cycle stays.
- **Never persist a smaller transaction set than what's on disk.** `persistTransactionsToDisk` reads the disk count before writing and refuses the write if the in-memory snapshot has fewer entries, logging “Refused to shrink tx file” loudly. Belt-and-braces against any future code path that mutates `myTransactions` downward.
- **Per-wallet file scoping.** Transactions, UTXOs, and pending broadcast amounts live in wallet-scoped files (`transactionDetails_{walletTitle}`, `{walletTitle}UTXOS`, `pendingBroadcastAmounts_{walletTitle}`). On wallet open, in-memory state is cleared and reloaded from that wallet's files only – no cross-wallet bleed.
- **Trust the per-wallet file on load.** An earlier `byOwnership` filter on the transaction load path was dropping outputs paying to Type42-derived change addresses or paymail-derived receive addresses not yet recorded on the card. The filter wrote the smaller set back to disk on the next save, silently deleting entries. With per-wallet files the scoping is enforced at write time; load-time filtering was both redundant and destructive. The filter has been removed from the load path. Display-time filtering (`byOwnership` in the wallet details views) is non-destructive and remains in place.

5.7 UTXOs and Balance

A UTXO (Unspent Transaction Output) represents a discrete amount of Bitcoin that can be spent. The wallet tracks all UTXOs across all addresses.

Balance from UTXOs: The displayed balance is computed solely from the UTXO set – no separate balance API call is needed. When UTXOs are fetched, the balance is calculated as:

confirmed = sum of UTXOs with block height > 0

unconfirmed = sum of UTXOs with block height = 0

total = confirmed + unconfirmed

Satoshi conversions use the named constant `satoshisPerBSV` (100,000,000) and price conversions use `priceCentsDivisor` (100.0). Raw magic numbers are never used.

5.7.1 Ordinal Protection

1Sat Ordinals are NFTs inscribed on single-satoshi UTXOs. The wallet protects ordinals at three levels:

1. **Transaction builder:** UTXOs with a value of 1 satoshi are excluded from UTXO selection during transaction building – a fast local check with no network call.
2. **Inscription scanner:** For display in the Ordinals view, 1-sat UTXOs are scanned by fetching the raw transaction and detecting the `OP_FALSE OP_IF ... OP_ENDIF` inscription pattern in the current output's locking script. Non-1-sat UTXOs are skipped entirely (ordinals are always exactly 1 sat). Results are cached per outpoint – once a UTXO has been scanned, it is never re-fetched from the network.
3. **1Sat indexer fallback:** The inscription scanner only finds inscriptions in the current output's script. Ordinals that were transferred to this wallet from elsewhere carry an empty locking script at the receiving output – the inscription lives in the ancestor minting transaction. To catch these, 1-sat UTXOs with no detectable current-output inscription are checked against the GorillaPool 1Sat indexer (ordinals.gorillapool.io). The lookup is tri-state: the indexer confirms is-ordinal, confirms not-ordinal (HTTP 404 or no ancestor outpoint), or fails closed on HTTP 5xx, network error, or malformed response. On fail-closed, the UTXO is treated as a potential ordinal and protected from spending – trusting local state over ambiguous remote state.

5.7.2 UTXO Split

From the UTXO detail view, a single UTXO can be split into up to 240 separate outputs across fresh derived addresses. This is useful for:

- Preparing UTXOs for future transactions (avoiding the need to wait for change confirmations)
- Distributing funds across addresses for privacy
- Creating multiple 1-sat UTXOs for ordinal inscriptions

5.8 API Providers

The wallet uses a hybrid architecture with multiple blockchain service providers:

Capability	WhatsOnChain	GorillaPool	TAAL	JungleBus
UTXOs (balance derived)	✓	X	X	X
Transaction history	✓	X	X	✓
SPV Merkle proofs	✓	X	X	X
BSV price	✓	X	X	X
Fee quotes	X	✓	✓	X
Broadcast (ARC)	X	✓	✓*	X
Real-time monitoring	X	X	X	✓

*TAAL requires a user-configured API key. GorillaPool is the primary broadcaster; TAAL is failover.

Each provider handles what it does best. API keys and subscription IDs are stored securely in the iOS Keychain and can be configured in Settings → API & Miners.

5.9 Security

- **Biometric authentication** – Face ID or Touch ID required to view private keys, seed phrases, and wallet details. Sessions expire after 120 seconds of inactivity. The same 120-second window is used by the payment approval cache (below) so multiple broadcasts within a session don't re-prompt for every send.
- **Keychain storage** – All sensitive material (keys, seeds, API tokens) stored with `.whenUnlockedThisDeviceOnly` accessibility – encrypted at rest, tied to the device.
- **Seed verification** – After creating a wallet, users are prompted to verify their seed phrase via a 3-word quiz.
- **No server dependency** – The wallet is fully self-custodial. No account, no registration, no server holds your keys.
- **Message encryption (BRC-2)** – Electrum ECIES format for end-to-end encrypted messages between BSV keys. Uses ECDH key agreement, AES-256-CBC encryption, and HMAC-SHA256 authentication. Wire-compatible with the `@bsv/sdk EncryptedMessage` class. Format: "BIE1" || pubkey || ciphertext || HMAC.
- **Wallet file encryption** – Wallet data files encrypted with AES-256-GCM using a Keychain-backed key before syncing to iCloud.

5.9.1 Payment Approval Cache

To avoid re-prompting Face ID for every successive broadcast in a single working session, the wallet keeps a session-scoped approval cache (`PaymentApprovalRecord`).

A successful biometric approval stamps the cache with (surface, amountSats, outputsDigest, timestamp). A subsequent broadcast within the 120-second window can skip the prompt when all three scoping axes match.

The outputsDigest is a SHA-256 over a canonical encoding of the sorted output set. Each output contributes `UInt32-LE(recipientKey.utf8.count) || recipientKey.utf8 || Int64-LE(satoshis)`. The length-prefix defeats engineered concatenation collisions: ("ab",1)+("c",2) no longer collides with ("a",1)+("bc",2) after sort-and-concat.

The recipientKey must be the final resolved destination, never an alias. For paymail surfaces, this means the resolved P2PKH address returned by the paymail server, never the `alice@example.com` alias string. Using the alias would defeat the cache's protective contract – a paymail server could change the resolution between the approval at time T and the broadcast at $T + 30$ seconds, and the cache would hit (same alias) while signing a transaction to a different address. Binding the digest to the resolved key forces a re-prompt whenever the destination changes.

The empty-digest fallback is permitted for surfaces with deterministic destinations (Consolidate and Split send to the wallet's own change address; raw tx-broadcast ships bytes the user crafted) and prohibited for resolution-flexible surfaces (Paymail-TransactionHelper passes the resolved addresses as the digest input). Cache hits never bridge across the empty / non-empty boundary – a real-digest approval cannot satisfy a later empty-digest gate, and vice versa.

5.9.2 Encrypted Off-Device Backup

The Keychain-bound wallet encryption above is device-local: the encrypted files on disk are useless on any other device because the key lives in the Secure Enclave of the original phone. If the user loses or factory-resets their phone without having manually recorded the seed phrase elsewhere, the wallet is unrecoverable.

The encrypted off-device backup feature (.bep files, produced by BackupService) solves this by emitting a portable, password-encrypted blob that can be stored anywhere – iCloud Drive, AirDrop to another device, email to self, a USB stick – and restored on any device, including a fresh install of Henceforth, by re-entering the original password.

- **Key derivation:** PBKDF2-HMAC-SHA256 with a per-backup 16-byte random salt, 600,000 iterations (roughly 500ms of CPU on modern iOS hardware). Raises the cost of offline brute-force against weak passwords.
- **Encryption:** AES-256-GCM over the plaintext (typically a BIP-39 mnemonic). GCM is authenticated – any bit flip in the salt, nonce, ciphertext, or tag fails verification and returns a `.invalidPassword` error indistinguishable from a genuine wrong-password attempt (no timing oracle).
- **Wire format:** magic prefix "HFBK1" (5 bytes), salt (16 bytes), iteration count (4 bytes big-endian), nonce (12 bytes), AES-GCM ciphertext + 16-byte tag. The iteration count is carried in-band so future backups can raise it without breaking the restore path for older backups.
- **Forward compatibility:** the version byte in the magic prefix allows a future format bump to coexist with older backups on disk.

- **Freshness:** the same plaintext encrypted twice under the same password produces different ciphertexts, because salt and nonce are both fresh random.

The .bep file protects only the seed phrase (the BIP-39 mnemonic from which every wallet key is derived). It does not contain UTXO cache, transaction history, or user preferences – those are regenerated from the blockchain after restore. A .bep plus its password is sufficient to recover every wallet this seed ever spawned on any Henceforth install.

5.9.3 QR Code Scanner

A unified QR scanner in Settings handles three QR code types, routed automatically by content:

1. **hfauth: prefix** – BRC-103 authentication flow (see below)
2. **WIF private key** (Base58Check version byte 0x80) – prompts for a wallet name, then imports via `Wallet.restoreFromWIF()`
3. **Bitcoin address** (version byte 0x00) – opens the pay view pre-filled with the scanned address

5.9.4 BRC-103 Authentication

BRC-103 provides passwordless authentication to web services using Bitcoin key pairs:

1. A web service displays a QR code containing a challenge and callback URL (prefixed with hfauth:)
2. The wallet scans the QR, displays the requesting domain, and asks for user approval
3. On approval, the wallet signs the challenge with the wallet's identity key and sends the signature to the callback URL
4. The web service verifies the signature against the wallet's public key

No passwords, no accounts – just cryptographic proof of key ownership.

5.9.5 BRC-100 Wallet Interface

The wallet exposes a subset of its capabilities via a URL scheme for integration with external applications:

`henceforth://wallet/{method}?params=...`

Supported operations include key derivation, signing, encryption, and certificate management (BRC-52/53). All sensitive operations require user approval via an on-screen confirmation sheet with biometric authentication.

The interface follows the BRC-100 specification: a `WalletInterface` protocol defines the contract, and a `HenceforthWallet` adapter bridges to the existing wallet, FORTH interpreter, and ARC broadcasting infrastructure.

Certificate Proofs (BRC-52/53)

Selective-disclosure certificate proofs follow BRC-52 (field-level HMAC keyring) and BRC-53 (certificate envelope) with the following hardened semantics:

- **Per-field HMAC keyring, ECDH-bound.** When the wallet proves a subset of certificate fields to a verifier, each field's HMAC key is encrypted with an ECDH shared secret derived between the prover's and verifier's BRC-42 identity keys. Only the intended verifier can decrypt the keyring and recompute the field HMACs – a leaked proof is useless against any other party.
- **Issuer signature verification.** `verifyProof` checks the issuer's BSM signature over the certificate's canonical field set before accepting any field as authentic. A well-formed proof with a missing or invalid issuer signature is rejected – `format-valid` is not the same as cryptographically valid.
- **Serial number carried in the proof.** Each proof includes the certificate's serial number so the verifier can correlate against revocation or re-issuance records maintained out-of-band.