

Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces

Prof Dr. Frank Kurth

LECTURE AT INSTITUT FÜR INFORMATIK, UNIVERSITÄT BONN
WINTER TERM

Signals and Signal Spaces	2
Signals	2
CT- and DT-Signals	3
Even, Odd & Periodic Signals	4
Sine- & Exponential Signals	5
Exponential Signals	6
The sinc Function	7
The Graph of the sinc Function	8
Chirp Signals	9
Chirp-Signals	10
Box Function	11
Heaviside or Unit Step Function	12
Sampling	13
Sampling	14
Sampling	15
Sampling	16
Discrete Unit Impulse	17
Discrete Unit Step Function	18
Discrete Frequency Signals	19
Discrete Frequency Signals	20
Discrete Sine Signals	21
Discrete Sine Signals	22
Signal Spaces	23
Superposition & Amplification of Signals	24
Effects of Superpositions	25
Effects of Superpositions	26
Effects of Superpositions	27
Effects of Superpositions	28
Superposition with a Noise Signal	29
Comments on Signal Spaces	30
Metric Spaces	31
Normed vector spaces	32
Norms: Examples	33
Unit circles in \mathbb{R}^2	34
Scalar products in real spaces	35
Scalar products in the complex domain	36
Hilbert spaces	37
Hilbert bases	38

Fundamental Theorems	39
The L^p - and ℓ^p -Spaces	40
Lebesgue Spaces for DT Signals	41
Norms for the $\ell^p(\mathbb{Z})$ -Spaces	42
Relationships between the ℓ^p Spaces	43
Three important ℓ^p Spaces	44
Lebesgue Spaces for CT Signals: Preliminaries	45
Lebesgue Spaces for CT Signals	46
Norms on the $L^p(\mathbb{R})$ -Spaces	47
$L^2(\mathbb{R})$ is a Hilbert Space	48
Lebesgue Spaces for Periodic CT Signals	49
$L^2([0, 1])$ is a Hilbert Space	50

Signals

- A **signal** is a **function** f assigning a uniquely determined element of the range Y of f to each element of the domain X of f . Notation:

$$f : X \rightarrow Y, \quad X \ni x \mapsto f(x) \in Y.$$

- Example 1: **Analog audio signal** f .

X : real time-interval, Y : sound pressure level (SPL), f assigns the current SPL $f(t)$ to every point in time t .

- Example 2: **Digital Image** f .

$X = [0 : 255] \times [0 : 255]$ pixel domain, $Y = [0 : 255]$: gray scale value,
 f assigns a gray scale value $f(i, j)$ to every pixel position (i, j) .

- An analog audio signal is an example of a **(time) continuous signal**.
- A digital image is an example of a **discrete signal**.

CT- and DT-Signals

- If X is an interval in \mathbb{R}^n , then

$$f : X \rightarrow \mathbb{R} \quad \text{resp.} \quad f : X \rightarrow \mathbb{C}$$

is a **continuous** real- or complex-valued **signal** (in n variables).

- If X is an interval in \mathbb{Z}^n , then

$$f : X \rightarrow \mathbb{R} \quad \text{resp.} \quad f : X \rightarrow \mathbb{C}$$

is a **discrete** real- or complex-valued **signal** (in n variables).

- We mostly consider the cases $n = 1$ or $n = 2$. As X is often a time interval ($n = 1$), we will talk of **continuous time** and **discrete time signals**, respectively.

- **CT-signals** and **DT-signals** are the shorthands for continuous time and discrete time signals, respectively.
- In case of CT-signals and DT-signals, the variable is typically denoted by t and n , respectively.

Even, Odd & Periodic Signals

Let $X \in \{\mathbb{R}, \mathbb{C}\}$. A function $f : X \rightarrow \mathbb{C}$ is called

- **even**, if $f(-x) = f(x)$ for all $x \in X$,
- **odd**, if $f(-x) = -f(x)$ for all $x \in X$.
- **T -periodic**, $T > 0$, if $f(x) = f(x + T)$ for all $x \in X$.

The smallest such T (if it exists!) is called the **fundamental period** of f .

Theorem. Every function $f : X \rightarrow \mathbb{C}$ can be written as the sum of its **even and odd part**,

$$f^+(x) := \frac{1}{2}(f(x) + f(-x)) \quad \text{resp.} \quad f^-(x) := \frac{1}{2}(f(x) - f(-x))$$

$$f(x) = f^+(x) + f^-(x).$$

Proof. It is easy to see that f^+ is an even and f^- is an odd function. Furthermore, it is easy to prove that $f = f^+ + f^-$. \square

Sine- & Exponential Signals

- Let A , f and φ be real numbers. Then the mapping

$$t \mapsto A \cdot \sin(2\pi ft + \varphi)$$


defines the **sine signal** with **amplitude** A , **frequency** f and **phase** φ .

- Musical point of view: amplitude \equiv sound level; frequency \equiv pitch
- zero-phase sine signals are odd functions.
- If C and a are complex, $t \mapsto C \cdot e^{at}$ defines a complex **exponential signal**.
- Important special case: $C = 1$ und a purely imaginary, e.g., $a = i\omega$ with $0 \neq \omega \in \mathbb{R}$. The signal

$$t \mapsto e^{i\omega t}$$

is a periodic signal with **wavelength** $T = 2\pi/|\omega|$.

Exponential Signals



Matlab Example ➔

The sinc Function


- In the context of the sampling theorem the following sinc function will play a fundamental role:

$$\text{sinc}(t) := \begin{cases} \frac{\sin(\pi t)}{\pi t} & \text{if } t \neq 0 \\ 1 & \text{if } t = 0. \end{cases}$$

- Exercise: The sinc function is continuous at $t = 0$.
- Note: the set of roots of the sinc function is just the set of all non-zero integers:

$$\{t \in \mathbb{R} | \text{sinc}(t) = 0\} = \mathbb{Z} \setminus \{0\}.$$

The Graph of the sinc Function



Chirp Signals

- Sine, exponential- and sinc function are signals of constant frequency.
- A class of signals with persistent frequency changes are the (linear) chirp signals. These chirps are defined by


$$t \mapsto \sin(2\pi(f_0 + \frac{k}{2}t)t)$$

- with real constants f_0 and $k > 0$.
- For such signals, the frequency increases linearly with k .
 - Remark: Bats locate objects with the help of chirp signals!
 - Technical applications: remote sensing (SAR), modulation process (CSS)

Chirp-Signals

$$t \mapsto \sin(2\pi(f_0 + \frac{k}{2}t)t)$$

with $f_0 = 0$ and $k = 2$




Audio example ($f_0 = 100$ und $k = 30$):

Box Function

- The **box function** of width $w > 0$ is defined by

$$b_w(t) := \begin{cases} 1 & \text{if } |t| \leq w/2 \\ 0 & \text{otherwise.} \end{cases}$$




- Note: b_w is a CT-signal, but it has two discontinuities (jumps) at $t = \pm \frac{w}{2}$.

Heaviside or Unit Step Function

- The **Heaviside or unit step function** is defined by

$$u(t) := \begin{cases} 0 & \text{if } t < 0 \\ 1 & \text{if } t \geq 0. \end{cases}$$




- Note: u is a CT-signal, but it has a jump discontinuity at $t = 0$.

Sampling


DT-signals are often derived from CT-signals via sampling.

- If $T > 0$, then the CT-signal $f : \mathbb{R} \rightarrow \mathbb{C}$ is transformed by **T -sampling** into the DT-Signal $x : \mathbb{Z} \rightarrow \mathbb{C}$:
$$x(n) := f(T \cdot n).$$
- The **sampling rate** is the number of samples per second. unit: Hertz (Hz).
- The sampling rate of x is $\frac{1}{T}$ Hz.
- The sampling rate is important for the signal's quality. Side effects caused by sampling are called **aliasing**.
- Common sampling rates for speech and music signals (1 kHz = 1000 Hz):
 - ◆ Telephone: 8 kHz
 - ◆ Digital Radio: 32 kHz
 - ◆ Compact Disk: 44,1 kHz
 - ◆ Studio applications 48, 96 kHz


Sampling



Sampling




Sampling



Discrete Unit Impulse

- The time discrete **unit impulse function** $\delta : \mathbb{Z} \rightarrow \{0, 1\}$ is equal to 1 at $n = 0$ and vanishes everywhere else:

$$\delta(n) := \begin{cases} 1 & \text{if } n = 0 \\ 0 & \text{if } n \neq 0. \end{cases}$$




- Note: The sinc function restricted to \mathbb{Z} coincides with the unit impulse!

Discrete Unit Step Function

- The time discrete **unit step function** $u : \mathbb{Z} \rightarrow \{0, 1\}$ is equal to zero for all negative integers and equal to 1 for all non-negative integers:

$$u(n) := \begin{cases} 0 & \text{if } n < 0 \\ 1 & \text{if } n \geq 0. \end{cases}$$



Discrete Frequency Signals


- Discrete time **frequency signals** of frequency $\omega \in [0, 1)$ are signals of the form

$$(c \cdot e^{2\pi i \omega n})_{n \in \mathbb{Z}}$$

with $0 \neq c \in \mathbb{C}$.

- A frequency signal of frequency ω is periodic iff ω is rational, i.e., there exist $k, \ell \in \mathbb{Z}$, $\ell \neq 0$, with $\omega = k/\ell$.

Discrete Frequency Signals



Matlab Example ➔

Discrete Sine Signals

- Discrete time **sine signals** are of the form

$$\mathbb{Z} \ni n \mapsto A \cdot \cos(2\pi\omega n + \varphi)$$


with a real φ .

- Such a signal contains the (complex) frequencies ω and $-\omega$, for

$$\cos(2\pi\omega n + \varphi) = \frac{1}{2} \left(e^{i(2\pi\omega n + \varphi)} + e^{-i(2\pi\omega n + \varphi)} \right).$$

Discrete Sine Signals

$$\mathbb{Z} \ni n \mapsto A \cdot \cos(2\pi\omega n + \theta)$$



Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 22 / 50

Signal Spaces

- Within an orchestra, every musician generates an audio signal. The audience perceive a **superposition** of these signals. In addition, some subsignals are amplified (at least in an idealized scenario), think of all the first violinists.
- From a mathematical point of view, superposition and amplification can be viewed as addition and scalar multiplication, respectively. Notions from Linear Algebra form an adequate tool for modeling.
- In the following, we consider a signal to a lesser extent as a single object, but as a point in a high dimensional vector space. This point of view allows us to use **methods from Linear Algebra** for signal analysis.
- These methods will be combined with **methods from Analysis**. On this basis, we can design good tools for the analysis as well as the synthesis of signals.

Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 23 / 50

Superposition & Amplification of Signals

Definition. Let $f : X \rightarrow \mathbb{C}$ and $g : X \rightarrow \mathbb{C}$ be signals with a common domain X , e.g., $X = \mathbb{R}$ or $X = \mathbb{Z}$. Furthermore, let $\lambda \in \mathbb{C}$.

- The **superposition** (mathematically: **sum**) $f + g$ of f and g is defined by

$$(f + g)(x) := f(x) + g(x) \quad \text{for } x \in X.$$

- The **amplification** (mathematically: **scalar multiple**) λf of f by the factor λ is defined by

$$(\lambda f)(x) := \lambda \cdot f(x) \quad \text{for } x \in X.$$

Theorem. The set $\mathbb{C}^X := \{f | f : X \rightarrow \mathbb{C}\}$ with the above addition and scalar multiplication defines a vector space over the complex numbers. For infinite X , this space is of infinite dimension.

Proof. A good exercise! □

Effects of Superpositions


We consider the superposition of two audio signals of (roughly) the same frequency.

- (1) Let $f(t) := A \cdot e^{i\omega t}$ and $g(t) := B \cdot e^{i\omega t}$ with real constants A, B . Comparing $f + g$ with f we observe:
 - ◆ $A > 0, B > 0$ yields an **amplification** of the signal;
 - ◆ $A > 0, B < 0$ yields an **attenuation** of the signal;
 - ◆ $A = -B$ yields a **cancellation** of the signal.
- (2) Let $f(t) := A \cdot e^{i\omega t}$ and $g(t) := B \cdot e^{i(\omega+\epsilon)t}$ with real constants A, B , and with a small positive ϵ . For the sum of f and g we obtain:

$$(f + g)(t) = (A + Be^{i\epsilon t})e^{i\omega t}.$$

The amplitude of the resulting function $f + g$ is subject to a constant change, which can be perceived as an unpleasant **amplitude vibrato**.


Effects of Superpositions



Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 26 / 50


Effects of Superpositions



Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 27 / 50

Effects of Superpositions




Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 28 / 50

Superposition with a Noise Signal

The superposition of a signal with a noise signal is another typical example for the addition of signals. The next figure shows the superposition of a chirp signal with a noise signal:



Foundations of Audio Signal Processing

§3 Audio Signals and Signal Spaces – 29 / 50

Comments on Signal Spaces

- The signal spaces $\mathbb{C}^{\mathbb{Z}}$ and $\mathbb{C}^{\mathbb{R}}$ contain by far too many signals. Most signals contained in those spaces are irrelevant for applications as they have no physical realization.
- From a **physical point of view**, one is mainly interested in signals of finite energy.
- From a **mathematical point of view**, signal spaces are desirable, where
 - ◆ a distance between two signals may be defined (comparability)
 - ◆ a signal may be suitably transformed and analyzed, e.g., in order to determine its pitch .
- In the following we give some mathematical preparations.

Metric Spaces

- A metric allows to specify
 - ◆ the **distance** between two signals,
 - ◆ the **length** or the **energy** of an individual signal.

Definition. A **metric** on a set M is specified by a mapping

$$d : M \times M \rightarrow \mathbb{R},$$

such that for all $x, y, z \in M$ the following properties hold:

- $d(x, y) \geq 0$,
- $d(x, y) = 0$ iff. $x = y$,
- $d(x, y) = d(y, x)$,
- $d(x, z) \leq d(x, y) + d(y, z)$ (triangle inequality).

Normed vector spaces

- A metric may be defined for an arbitrary set M .
- Up to now, all signal spaces we considered are vector spaces, which are as such equipped with a linear structure.
- The following definition links metric and linear structures.

Definition. A **norm** on a \mathbb{C} -vector space V is defined by a mapping

$$\|\cdot\| : V \rightarrow \mathbb{R},$$

such that for all $x, y \in V$ and all $\lambda \in \mathbb{C}$ the following properties hold:

- $\|x\| = 0$ iff. $x = 0$,
- $\|\lambda \cdot x\| = |\lambda| \cdot \|x\|$,
- $\|x + y\| \leq \|x\| + \|y\|$ (triangle inequality).

Remark. A norm on V induces a metric d on V : $d(x, y) := \|x - y\|$.

Norms: Examples

- \mathbb{C}^n equipped with the **euclidean norm** $\|x\|_2 := (\|x_1\|^2 + \dots + \|x_n\|^2)^{1/2}$.
- \mathbb{C}^n equipped with the **sum norm** $\|x\|_1 := (|x_1| + \dots + |x_n|)$. The corresponding metric is also called **Manhattan metric**. Why?
- \mathbb{C}^n equipped with the **maximum norm** $\|x\|_\infty := \max\{|x_1|, \dots, |x_n|\}$.
- More generally: For a real $p \in [1, \infty)$, \mathbb{C}^n equipped with the **p -norm**

$$\|x\|_p := (\|x_1\|^p + \dots + \|x_n\|^p)^{1/p}.$$

Replacing \mathbb{C} by \mathbb{R} in the above, one obtains normed \mathbb{R} -vector spaces.


With this, we have already introduced the most important signal spaces for finite signals!

Unit circles in \mathbb{R}^2

It is important to understand the notion of "length" in \mathbb{R}^n for the different p -norms. For the case of $n = 2$ we consider the corresponding unit circle

$$\{z \in \mathbb{R}^2 : \|z\|_p = 1\}.$$

The unit circles in \mathbb{R}^2 for different p -norms look as follows:



Scalar products in real spaces

- Besides the notion of length, angles - and particularly right angles - are of fundamental importance.
- The scalar product of real-valued vectors gives a connection between the euclidean length and the angle via

$$\langle x|y \rangle := \sum_{i=1}^n x_i y_i = \|x\|_2 \cdot \|y\|_2 \cdot \cos \alpha,$$

where α denotes the angle enclosed by $x \in \mathbb{R}^n$ and $y \in \mathbb{R}^n$.

- In the above formula, $\|y\|_2 \cdot \cos \alpha$ denotes the **scalar projection** of y onto x .
- Geometrical description of the scalar product in the \mathbb{R}^2 :
- Particularly interesting is the case $\cos \alpha = 0$ where the enclosed angle is 90° . In this case, the vectors are perpendicular, x and y are then called **orthogonal**.

Scalar products in the complex domain

Definition. A **scalar product** or **inner product** on a \mathbb{C} -vector space V is defined by a mapping

$$\langle \cdot | \cdot \rangle : V \times V \rightarrow \mathbb{C},$$

such that for all $x, y \in V$ the following properties hold:

- $\langle x|x \rangle \geq 0$,
- $\langle x|x \rangle = 0$ iff. $x = 0$,
- $\langle \cdot | \cdot \rangle$ is \mathbb{C} -linear in the first component,
- $\langle x|y \rangle = \langle y|x \rangle^* = \overline{\langle y|x \rangle}$.

Remark. A scalar product on V induces a norm on V by

$$\|x\| := \sqrt{\langle x|x \rangle}.$$

Hilbert spaces

Definition. A complete (i.e., all Cauchy sequences converge) vector space with a norm induced by a scalar product is called **Hilbert space**.

Definition. Two vectors of a Hilbert space are called **orthogonal**, if their scalar product is zero: $\langle x|y \rangle = 0$.

Theorem.

- (1) \mathbb{C}^n together with the p -norm is a Hilbert space if and only if $p = 2$.
- (2) For $p = 2$, the induced scalar product is given by

$$\langle x|y \rangle := \sum_{i=1}^n x_i \overline{y_i},$$

for $x, y \in \mathbb{C}^n$.

- (3) The unit vectors e_1, \dots, e_n constitute an **orthonormal basis** of \mathbb{C}^n , this is, $\langle e_i|e_j \rangle = \delta_{ij}$.

We will now considerably generalize statement (3).

Hilbert bases

Theorem. Let I denote a non-empty set of indexes and let $(e_i)_{i \in I}$ denote an **ON-system** of the Hilbert space V , i.e. $\langle e_i | e_j \rangle = \delta_{ij}$ for $i, j \in I$. Then the following statements are equivalent:

- (1) **Completeness:** If $x \in V$ is orthogonal to all e_i , then $x = 0$.
- (2) **Parseval equality:** For each $x \in V$ $\|x\|^2 = \sum_{i \in I} |\langle x | e_i \rangle|^2$ holds.
- (3) **Fourier series:** Every $x \in V$ has a representation

$$x = \sum_{i \in I} \langle x | e_i \rangle e_i,$$

where the number of non-zero scalar products $\langle x | e_i \rangle$ is at most countably infinite and the series unconditionally (i.e., regardless of the arrangement of the coefficients) converges towards x .

Definition. A complete ON-system is called **Hilbert basis** of V .

Fundamental Theorems

Theorem of Pythagoras: If x_1, \dots, x_n are pairwise orthogonal elements of the Hilbert space V , then the energy of the sum of the x_i is the same as the sum of the single energies:

$$\left\| \sum_{j=1}^n x_j \right\|^2 = \sum_{j=1}^n \|x_j\|^2.$$

Cauchy-Schwarz inequality: For elements x, y of a Hilbert space V the following holds:

$$|\langle x | y \rangle| \leq \|x\| \cdot \|y\|.$$

Parseval identity: A unitary isomorphism $T : V \rightarrow W$ between Hilbert spaces conserves both the norm and the scalar product:

$$\|x\| = \|Tx\| \quad \text{and} \quad \langle x | y \rangle = \langle Tx | Ty \rangle.$$

The L^p - and ℓ^p -Spaces

- We are now sufficiently prepared to introduce signal spaces of practical relevance.
- These spaces were named after the French mathematician Henri Léon Lebesgue.
- The short-hands for these spaces begin with
 - ◆ a lower case ℓ (for DT signals) and
 - ◆ an upper case L (for CT signals).
- On the one hand, we will introduce ℓ^p spaces like $\ell^p(\mathbb{Z})$ or $\ell^p(\mathbb{N})$,
- on the other hand, we will discuss L^p spaces like $L^p(\mathbb{R})$ or $L^p([0, 1])$.
- We will start with the ℓ^p spaces for DT signals.

Lebesgue Spaces for DT Signals

Definition. Let $p \in [1, \infty)$. The **Lebesgue space** $\ell^p(\mathbb{Z})$ consists of all sequences $x : \mathbb{Z} \rightarrow \mathbb{C}$, which are of finite p -length. More formally:

$$\ell^p(\mathbb{Z}) := \{x : \mathbb{Z} \rightarrow \mathbb{C} \mid \sum_{n \in \mathbb{Z}} |x_n|^p < \infty\}.$$

If $p = \infty$, the space $\ell^\infty(\mathbb{Z})$ is defined as the space of all bounded signals with common domain \mathbb{Z} :

$$\ell^\infty(\mathbb{Z}) := \{x : \mathbb{Z} \rightarrow \mathbb{C} \mid \exists B > 0 \forall n \in \mathbb{Z} : |x_n| \leq B\}.$$

Remark. If the parameter p is large, then small values are attenuated ($|x_n| < 1 \Rightarrow |x_n|^p \ll 1$) while large values are amplified ($|x_n| > 1 \Rightarrow |x_n|^p \gg 1$).

Theorem. For $p \in [1, \infty]$ the set $\ell^p(\mathbb{Z})$ is a linear subspace of $\mathbb{C}^\mathbb{Z}$.

Norms for the $\ell^p(\mathbb{Z})$ -Spaces

Theorem. The mappings

$$\begin{aligned}\ell^p(\mathbb{Z}) \ni x &\mapsto \|x\|_p := \left(\sum_{n \in \mathbb{Z}} |x(n)|^p \right)^{1/p} \quad \text{for } 1 \leq p < \infty \text{ and} \\ \ell^\infty(\mathbb{Z}) \ni x &\mapsto \|x\|_\infty := \sup\{|x(n)| : n \in \mathbb{Z}\}\end{aligned}$$

define a norm on $\ell^p(\mathbb{Z})$ and $\ell^\infty(\mathbb{Z})$, respectively.

Remark. Replacing in $\ell^p(\mathbb{Z})$ the common domain \mathbb{Z} of the signals by an arbitrary finite or countable infinite set I , we obtain corresponding spaces $\ell^p(I)$. In case $I = [1 : n]$, the space $\ell^p(I)$ is just \mathbb{C}^n equipped with the p -norm.

Relationships between the ℓ^p Spaces

Theorem. (Jensen's Inequality) For $1 \leq p < q \leq \infty$ the following holds:

- (1) $\ell^p(\mathbb{Z})$ is a proper linear subspace of $\ell^q(\mathbb{Z})$. In particular

$$\ell^1(\mathbb{Z}) \subset \ell^2(\mathbb{Z}) \subset \ell^3(\mathbb{Z}) \subset \dots \subset \ell^\infty(\mathbb{Z}).$$

- (2) For all $x \in \ell^p(\mathbb{Z})$ we have $\|x\|_q \leq \|x\|_p$. In particular, for $x \in \ell^1(\mathbb{Z})$

$$\|x\|_1 \geq \|x\|_2 \geq \|x\|_3 \geq \dots \geq \|x\|_\infty.$$

Three important ℓ^p Spaces

For us, the ℓ^p spaces $\ell^1(\mathbb{Z})$, $\ell^2(\mathbb{Z})$, and $\ell^\infty(\mathbb{Z})$ are of particular interest. Here,

$$\begin{aligned}\ell^1(\mathbb{Z}) &= \text{space of all absolute summable sequences} \\ \ell^2(\mathbb{Z}) &= \text{space of all square-summable sequences} \\ \ell^\infty(\mathbb{Z}) &= \text{space of all bounded sequences.}\end{aligned}$$

Theorem. The space $\ell^2(\mathbb{Z})$ is the only Hilbert space among the Banach spaces $\ell^p(\mathbb{Z})$, $p \in [1, \infty]$. The 2-norm is induced from the scalar product

$$\langle x|y \rangle := \sum_{n \in \mathbb{Z}} x(n)\overline{y(n)}.$$

The indicator functions $(\delta_n)_{n \in \mathbb{Z}}$ corresponding to the elements of \mathbb{Z} form a Hilbert basis of $\ell^2(\mathbb{Z})$.

In a little while, we will discuss other Hilbert bases of $\ell^2(\mathbb{Z})$, which will play a crucial role in signal analysis.

Lebesgue Spaces for CT Signals: Preliminaries

- We are going to discuss the $L^p(\mathbb{R})$ spaces.
- $L^p(\mathbb{R})$ is the CT analogon to the DT space $\ell^p(\mathbb{Z})$.
- Memory hook: $L^p(\mathbb{R})$ evolves from $\ell^p(\mathbb{Z})$, by replacing \mathbb{Z} with \mathbb{R} and summation with integration.
- Some of the results for DT signals carry over to CT signals.
- However, there are CT specific phenomena! One reason for this is the fact that $|\mathbb{Z}| \ll |\mathbb{R}|$.

For proofs of the next non-trivial results, we refer to the literature on Functional Analysis.

Lebesgue Spaces for CT Signals

Definition. Let $p \in [1, \infty)$. The **Lebesgue space** $L^p(\mathbb{R})$ consists of all measurable functions $f : \mathbb{R} \rightarrow \mathbb{C}$, which are of finite p -length. More formally:

$$L^p(\mathbb{R}) := \{f : \mathbb{R} \rightarrow \mathbb{C} \mid f \text{ measurable and } \int_{\mathbb{R}} |f(t)|^p dt < \infty\}.$$

For $p = \infty$ the space $L^\infty(\mathbb{R})$ is defined as the space of all measurable functions $f : \mathbb{R} \rightarrow \mathbb{C}$, which are essentially bounded:

$$L^\infty(\mathbb{R}) := \{f : \mathbb{R} \rightarrow \mathbb{C} \mid f \text{ measurable and } \text{ess sup}_{t \in \mathbb{R}} |f(t)| < \infty\}.$$

Here,

$$\text{ess sup}_{t \in \mathbb{R}} |f(t)| := \inf\{a \geq 0 \mid \mu(\{t : |f(t)| > a\}) = 0\},$$

and μ denotes the so-called **Borel measure** on \mathbb{R} . This measure generalizes the notion of the length of an interval to more general subsets of \mathbb{R} .

Theorem. For $p \in [1, \infty]$ the space $L^p(\mathbb{R})$ is a linear subspace of $\mathbb{C}^{\mathbb{R}}$.

Norms on the $L^p(\mathbb{R})$ -Spaces

Theorem. The mappings

$$\begin{aligned} L^p(\mathbb{R}) \ni f &\mapsto \|f\|_p := \left(\int_{\mathbb{R}} |f(t)|^p dt \right)^{1/p} \quad \text{for } 1 \leq p < \infty \text{ and} \\ L^\infty(\mathbb{R}) \ni f &\mapsto \|f\|_\infty := \text{ess sup}\{|f(t)| : t \in \mathbb{R}\} \end{aligned}$$

define a norm on $L^p(\mathbb{R})$ and $L^\infty(\mathbb{R})$, respectively. With respect to these norms, the spaces $L^p(\mathbb{R})$ are complete, hence are Banach spaces.

Remark. Strictly speaking: $L^p(\mathbb{R})$ consists of equivalence classes of functions: two functions $f, g \in L^p(\mathbb{R})$ are equivalent iff $\|f - g\|_p = 0$.

Warning. Between the L^p spaces there is no analogon to $p < q \Rightarrow \ell^p(\mathbb{Z}) \subset \ell^q(\mathbb{Z})$. E.g., define

$$f(t) := \begin{cases} t^{-1/2} & \text{for } t \in (0, 1] \\ 0 & \text{otherwise} \end{cases} \quad \text{and} \quad g(t) := \begin{cases} t^{-1} & \text{for } t \in [1, \infty) \\ 0 & \text{otherwise} \end{cases}.$$

Then $f \in L^1(\mathbb{R}) \setminus L^2(\mathbb{R})$ and $g \in L^2(\mathbb{R}) \setminus L^1(\mathbb{R})$.

$L^2(\mathbb{R})$ is a Hilbert Space

Theorem. The space $L^2(\mathbb{R})$ is a Hilbert space with respect to the scalar product

$$\langle f|g \rangle := \int_{\mathbb{R}} f(t)\overline{g(t)}dt,$$

for $f, g \in L^2(\mathbb{R})$. In particular

$$\langle f|f \rangle = \|f\|_2^2.$$

Remark. $L^2(\mathbb{R})$ is the only Hilbert space among the $L^p(\mathbb{R})$ spaces.

Lebesgue Spaces for Periodic CT Signals

- The Lebesgue spaces $L^p(\mathbb{R})$ are an accumulation of CT Signals $f : \mathbb{R} \rightarrow \mathbb{C}$ that satisfy certain integrability conditions.
- In the next slides we will discuss another class of CT signals: **periodic signals**.

Definition. Let $\lambda \in \mathbb{R}_{>0}$. A signal $f : \mathbb{R} \rightarrow \mathbb{C}$ is called **λ -periodic**, if $f(t) = f(t + \lambda)$, for all $t \in \mathbb{R}$.

Remarks.

- Every λ -periodic function f is completely specified, if f is known on the interval $[0, \lambda]$.
- On the other hand, every function $g : [0, \lambda] \rightarrow \mathbb{C}$ can be uniquely extended to a λ -periodic function $f : \mathbb{R} \rightarrow \mathbb{C}$.
- If f is λ -periodic, then $t \mapsto f(\lambda \cdot t)$ defines a 1-periodic function. By this transformation we can w.l.o.g. restrict our study to 1-periodic functions.

$L^2([0, 1])$ is a Hilbert Space

Theorem. The space $L^2([0, 1])$ is a Hilbert space with respect to the scalar product

$$\langle f | g \rangle := \int_0^1 f(t) \overline{g(t)} dt,$$

for $f, g \in L^2([0, 1])$. In particular

$$\langle f | f \rangle = \|f\|_2^2.$$

Remarks.

- Among the Banach spaces $L^p([0, 1])$, $p \in [1, \infty]$, $L^2([0, 1])$ is the only one, whose norm is induced from a scalar product, i.e., $L^2([0, 1])$ is the only Hilbert space among the $L^p([0, 1])$ spaces.
- If $a < b$ are real, one can analogously define the Hilbert space $L^2([a, b])$ of all measurable functions $f : [a, b] \rightarrow \mathbb{C}$ which are square-integrable.