Computational Rheology via LAMMPS, October 12, 2013 85th Meeting of the Society of Rheology

9: Common Non-Equilibrium Calculations

Jeremy B. Lechman

Engineering Sciences Center Sandia National Laboratories, Albuquerque, New Mexico







Why Non-Equilibrium MD (NEMD)?

- Classical Molecular Dynamics often used as a thermodynamic equilibrium technique
 - Newton's Equations + pairwise central forces conserve energy
 - At long times (depending on IC's and BC's) → Microcanonical Ensemble
- We are interested in non-equilibrium properties
 - Transport: rheology

$$\sigma = \eta \dot{\gamma}$$

- How to obtain?
 - Near equilibrium or fluctuations about equilibrium
 - Linear response regime
 - Effectively zero rate transport coefficients
 - Need long-time for good statistics
- What about far from equilibrium?
 - High rates, large gradients
 - General time dependent behavior





Non-Equilibrium Ensemble Averages

- Rheological observables compute pxy, fix ave/spatial
 - Stress and strain-rate (linear regime)
 - Irving-Kirkwood (1950) J Chem Phys, v. 18, p. 817

$$\sigma_{\alpha\beta} = \left\langle \frac{1}{V} \sum_{i=1}^{N} \left[\sum_{j \neq i} \frac{r_{ij}^{\alpha} f_{ij}^{\beta}}{2} + m_i (v_i^{\alpha} - u^{\alpha}) (v_j^{\beta} - u^{\beta}) \right]; f^{N}(\mathbf{r}, \mathbf{p}, t) \right\rangle$$

$$\dot{\gamma} = \left[\nabla \left\langle \sum_{i=1}^{N} \mathbf{v}_{i} \delta(\mathbf{r}_{i} - \mathbf{r}) \right\rangle \right]_{\alpha\beta} = \left[\nabla \mathbf{u}(r) \right]_{\alpha\beta} \qquad \sigma_{\alpha\beta} / \dot{\gamma} = \eta$$

- Again, in practice these become time averages
- How long is long enough?





Non-Equilibrium Steady States

- What happens when a constant force (through boundary conditions – applied gradient, or external field) is applied to Equilibrium System following Newton's Equations for particle dynamics?
 - E.g., cause particles to flow
 - For pairwise central forces, Newton's Equations conserve energy
 - Constant force gives constant acceleration so kinetic energy (temperature) increases with time
- What to do for constant (steady-sate) temperature?
 - Thermostat (on fluctuations about average) to balance energy input
 - Section 6.16 of How to $k_B T = \frac{3(N-1)}{2} \left\langle \sum_i m_i (\mathbf{v}_i(t) \mathbf{u}(r,t))^2 \right\rangle$





Typical NEMD Techniques (Rheology)

- Non-Hamiltonian Systems "perturb" equations of motion
 - SLLOD + Parrinello-Rahman: shear flow
 - fix nvt/sllod + fix deform
- Boundary Modifications
 - Lees-Edwards
 - Steady Couette Flow
 - Muller-Plathe: shear or heat flow
 - fix viscosity
 - fix thermal/conductivity
 - Deletion and insertion



Mass flow



Perturbations to Equations of Motion

General Approach

$$\dot{\mathbf{q}} = \mathbf{p} / m + \mathbf{A}_{\mathbf{p}}(\mathbf{q}, \mathbf{p}) \cdot \mathbf{\mathcal{F}}(t)$$
$$\dot{\mathbf{p}} = \mathbf{F} - \mathbf{A}_{\mathbf{q}}(\mathbf{q}, \mathbf{p}) \cdot \mathbf{\mathcal{F}}(t)$$

- Shear
- Heat flow

$$\dot{\mathbf{q}}_i = \mathbf{p}_i / m_i$$

$$\dot{\mathbf{p}}_{i} = \mathbf{F}_{i} - \delta \varepsilon_{i} \boldsymbol{\mathcal{F}}(t) + \frac{1}{2} \sum_{j} \mathbf{F}_{ij} (\mathbf{r}_{ij} \cdot \boldsymbol{\mathcal{F}}(t)) - \frac{1}{2N} \sum_{j} \sum_{k} \mathbf{F}_{jk} (\mathbf{r}_{jk} \cdot \boldsymbol{\mathcal{F}}(t))$$


Diffusion





Lees-Edwards Boundary Conditions

- Remap positions and velocities of particles crossing PBC
- Steady Shear (Couette) Flow
- Thermostat
 - E.g., Nose-Hoover
- No time dependent flow



Evans and Morris, Statistical Mechanics of Nonequilibrium Liquids





SLLOD + Parinello-Rahman

- Apply Shear Perturbation to each particle
 - Deform Box/particle positions

$$\dot{\mathbf{q}}_i = \mathbf{p}_i / m_i + \mathbf{q}_i \cdot \nabla \mathbf{u}$$

$$\dot{\mathbf{p}}_i = \mathbf{F}_i - \mathbf{p}_i \cdot \nabla \mathbf{u}$$





Fig. 7.3 Changing box-shape.

Evans and Morris, Statistical Mechanics of Nonequilibrium Liquids

- Remap positions and/ velocities across PBC
- Thermostat!
 - E.g., Nose-Hoover



 $\nabla \mathbf{u}(\mathbf{r},t) = \begin{vmatrix} 0 & 0 \\ & \ddots \end{vmatrix}$

Profile biased vs. profile unbiased

Muller-Plathe Approach

Bin system in z


Viscosity: swap opposed velocities in top and middle

bins

- fix viscosit
- fix ave/spat,

$$j_z(p_x) = -\eta \frac{\partial v_x}{\partial z}$$

$$j_z(p_x) = \frac{P_{tot}}{2tL_xL_y}$$




 Can swap "hot" and "cold" (difference in squared velocity magnitude) atoms for thermal conductivities





Additional Rheology Relevant NE Simulations

- Initial and boundary conditions
 - Oscillatory
 - Large amplitude, high frequency
 - Failure, crazing
 - Phase changes
 - Concentration gradients
 - Dispersion stability
 - Evaporation
 - Shock







Rheology Applications

- What's possible?
- Practical issues
 - Long time averages how long is long enough!
 - statistics